

## **Branding Customizations**

- Branding Overview, on page 1
- Branding Prerequisites, on page 1
- Branding Task Flow, on page 2
- Branding File Requirements, on page 4

### **Branding Overview**

The Branding feature lets you upload customized branding for Cisco Unified Communications Manager. Branding gets applied to the Cisco Unified CM Administration login and configuration windows. Among the items that you can modify include:

- · Company logos
- · Background colors
- · Border colors
- Font colors

### **Append Logo in Self Care Portal**

The Branding feature allows you to append your company logo to the Unified Communications Self Care Portal login page and to the user interface header. You must include the branding\_logo.png file in your branding.zip file and upload the zip file into Cisco Unified Communications Manager. The logo displays in the Self Care Portal after you enable branding in Cisco Unified Communications Manager.

There is no option to customize background colors or fonts for the Self-Care portal.

## **Branding Prerequisites**

You must create your branding. zip file that contains the specified folder structure and files. For details, see Branding File Requirements, on page 4.

### **Branding Task Flow**

Complete these tasks to apply branding in Cisco Unified Communications Manager and the Unified Communications Self-Care Portal.

### Before you begin

Review Branding Prerequisites, on page 1

#### **Procedure**

	Command or Action	Purpose
Step 1	Configure your branding settings using one of these procedures:	Apply branding across the Cisco Unified Communications Manager cluster.
	<ul><li>Enable Branding, on page 2</li><li>Disable Branding, on page 3</li></ul>	
Step 2	Restart the Tomcat Service, on page 4	You must restart the Cisco Tomcat service for the new branding setting to get picked up by the Unified Communications Self-Care Portal.

### **Enable Branding**

Use this procedure to enable branding customization for Unified Communications Manager. Branding updates appear even if the system is enabled for SAML Single Sign-On.



Note

To enable branding, you must use the primary administrator account with privilege level 4 access. This is the main administrator account that is created during installation.



Note

Ensure that you use only one among GUI and CLI to enable branding as well as to disable it. For example, if you enable branding using the GUI interface, you must use the GUI interface itself to disable branding. Else, it will not function properly.

#### Before you begin

Prepare your branding. zip file and save it in a location that Unified Communications Manager can access.

### **Procedure**

- **Step 1** Log in to Cisco Unified OS Administration.
- **Step 2** Choose **Software Upgrades** > **Branding**.

- **Step 3 Browse** to your remote server and select the branding.zip file.
- Step 4 Click Upload File.
- **Step 5** Click **Enable Branding**.

Note You can also enable branding by running the utils branding enable CLI command.

- **Step 6** Refresh your browser.
- **Step 7** Repeat this procedure on all Cisco Unified Communications Manager cluster nodes.

If you want to append your company logo to the Self-Care Portal user interface, see Restart the Tomcat Service, on page 4.

### **Disable Branding**

Use this procedure to disable branding in your Cisco Unified Communications Manager cluster. You also need to disable branding if you want to remove your company logo from the Self-Care Portal.



Note

To disable branding, you must use the primary administrator account with privilege level 4 access. This is the main administrator account that is created during installation.



Note

Ensure that you use only one among GUI and CLI to enable branding as well as to disable it. For example, if you enable branding using the GUI interface, you must use the GUI interface itself to disable branding. Else, it will not function properly.

### **Procedure**

- **Step 1** Log in to Cisco Unified OS Administration.
- **Step 2** Choose **Software Upgrades** > **Branding**.
- Step 3 Click Disable Branding.

Note You can also disable branding by running the utils branding disable CLI command.

- **Step 4** Refresh your browser.
- **Step 5** Repeat this procedure on all Cisco Unified Communications Manager cluster nodes.

If you want to remove your company logo from the Self-Care Portal user interface, see Restart the Tomcat Service, on page 4

### **Restart the Tomcat Service**

You must restart the Cisco Tomcat service for the branding updates to reflect in the Self-Care Portal.

#### Before you begin

Make sure that you have completed the following:

- To append your logo to the Self-Care Portal, you must first enable branding in Cisco Unified Communications Manager. The branding.zip upload file must include a 44x25 pixel branding logo.png file with your company logo. For details, Enable Branding, on page 2.
- To remove your logo from the Self-Care Portal, you must disable branding in Cisco Unified Communications Manager. For details, Disable Branding, on page 3.

#### **Procedure**

- **Step 1** Log in to the Command Line Interface.
- Step 2 Run the utils service restart Cisco Tomcat CLI command.
- **Step 3** Repeat this procedure on all Cisco Unified Communications Manager cluster nodes.

#### What to do next

After the service restarts, refresh your browser to see the changes in the Self-Care Portal.

# **Branding File Requirements**

Before you apply customized branding to your system, create your branding.zip file according to the prescribed specifications. On a remote server, create a Branding folder and fill the folder with the specified contents. Once you have added all the image files and subfolders, zip the entire folder and save the file as branding.zip.

There are two options for the folder structure, depending on whether you want to use a single image for the header or a combination of six images in order to create a graded effect for the header.

**Table 1: Folder Structure Options** 

Branding Option	Folder Structure	
Single Header Option	If you want a single image for the header background (callout item 3), your branding folder must contain the following subfolders and image files:	
	Branding (folder) ccmadmin (folder) BrandingProperties.properties (properties file) brandingHeader.gif (2048*1 pixel image) ciscoLogo12pxMargin.gif (44*44 pixel image) branding_logo.png (44*25 pixel image)	

Branding Option	Folder Structure	
Graded Header Option	If you want to create a graded image for the header background, you need six separate image files to create the graded effect. Your branding folder must contain these subfolders and files	
	Branding(folder)  ccmadmin (folder)  BrandingProperties.properties (file)  brandingHeaderBegLTR.gif (652*1 pixel image)  brandingHeaderBegRTR.gif (652*1 pixel image)  brandingHeaderEndLTR.gif (652*1 pixel image)  brandingHeaderEndRTR.gif (652*1 pixel image)  brandingHeaderMidLTR.gif (652*1 pixel image)  brandingHeaderMidRTR.gif (652*1 pixel image)  brandingHeaderMidRTR.gif (652*1 pixel image)  ciscoLogo12pxMargin.gif (44*44 pixel image)  branding_logo.png (44*25 pixel image)	

### **User Interface Branding Options**

The following images display the customization options for the Cisco Unified CM Administration user interface:

Figure 1: Branding Options for Unified CM Administration Login Screen





Figure 2: Branding Options for Unified CM Administration Logged In Screen



The following table describes the callout options.

Table 2: User Interface Branding Options: Login Screen

Item	Description	Branding edits
1	Company Logo	To add your logo to Cisco Unified Communications Manager, save your company logo as a 44x44 pixel image with the following filename:
		ciscoLogo12pxMargin.gif(44*44 pixels)
		Note  If you also want to append your logo to the header and login screen of the Self-Care Portal, you should also save your logo as the 44x25 pixel branding_logo.png file.
2	Unified CM Administration header font color	heading.heading.color

Description	Branding edits
Header Background	You can use a single image or a combination of six images to create a grading effect.
	<b>Single Image option</b> —Save your header background as a single image:
	• brandingHeader.gif (2048*1 pixel)
	<b>Graded background option:</b> —Save your header background as six images for a graded effect:
	• brandingHeaderBegLTR.gif (652*1 pixel)
	• brandingHeaderBegRTR.gif (652*1 pixel)
	brandingHeaderEndLTR.gif (652*1 pixel)
	• brandingHeaderEndRTR.gif (652*1 pixel)
	• brandingHeaderMidLTR.gif (652*1 pixel)
	• brandingHeaderMidRTR.gif (652*1 pixel)
Navigation text	header.navigation.color
Go button	header.go.font.color
	header.go.background.color
	header.go.border.color
Username text	splash.username.color
Password text	splash.password.color
Login button	splash.login.text.color
	splash.login.back.ground.color
Reset button	splash.reset.text.color
	splash.reset.back.ground.color
Bottom background color – right	splash.hex.code.3
Bottom background color – left	splash.hex.code.2
Banner	splash.hex.code.1
	Navigation text Go button  Username text Password text Login button  Reset button  Bottom background color – right Bottom background color – left

### Table 3: User Interface Branding Options: Logged In Screen

Item	Description	Branding edits
13	User text (for example, 'admin')	header.admin.color
14	Search, About and Login text	header.hover.link.color

Item	Description	Branding edits
15	Unified CM Administration text heading	splash.header.color
16	System Version, VMware Installation text	splash.reset.text.color splash.version.color

### **Branding Properties Editing Example**

Branding properties can be edited by adding the hex code in the properties file (BrandingProperties.properties). The properties file uses HTML-based hex code. For example, if you want to change the color of the Navigation text item (callout item #4) to red, add the following code to your properties file:

header.navigation.color="#FF0000"

In this code, header.navigation.color is the branding property that you want to edit, and "#FF0000" is the new setting (red).