



## Subdialog Return

In most situations, the `CVP Subdialog Return` element (see [CVP Subdialog Return](#)) **should be used instead of this one**, to offer full compatibility with ICM. However, there is **one exception** to this. If the voice application will *only* be called by a Subdialog Invoke element (that is, never by ICM), then the `Subdialog Start` and `Subdialog Return` elements may be used instead. In this scenario, using this element allows an arbitrary number of return values to be retrieved from the subdialog, whereas the `CVP Subdialog Return` element allows only four.

- [Settings, on page 1](#)
- [Exit States, on page 2](#)
- [Folder and Class Information, on page 2](#)

## Settings

Name (Label)	Type	Req'd	Single Setting Value	Substitution Allowed	Default	Notes
return_value (Return Value)	string	No	false	true	None	Optional return argument that holds a name/value pair to be returned to the calling application. The format should be: the name of the argument followed by an equal sign and the value of the argument. For example; <i>name=John Doe</i> . The element will take the text up to the first equal sign to be the name of the argument and the text following the equal sign to the value.



**Note** The following characters are not allowed in the return argument:

< > ' ' &

## Exit States

Name	Notes
done	The element is successfully run.

## Folder and Class Information

Studio Element Folder Name	Class Name
General	com.audium.server.voiceElement.internal.DefaultSubdialogReturnElement