



## **Cisco Unified Contact Center Enterprise Developer Reference, Release 12.5(1)**

**First Published:** 2020-02-29

### **Americas Headquarters**

Cisco Systems, Inc.  
170 West Tasman Drive  
San Jose, CA 95134-1706  
USA  
<http://www.cisco.com>  
Tel: 408 526-4000  
800 553-NETS (6387)  
Fax: 408 527-0883

THE SPECIFICATIONS AND INFORMATION REGARDING THE PRODUCTS IN THIS MANUAL ARE SUBJECT TO CHANGE WITHOUT NOTICE. ALL STATEMENTS, INFORMATION, AND RECOMMENDATIONS IN THIS MANUAL ARE BELIEVED TO BE ACCURATE BUT ARE PRESENTED WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED. USERS MUST TAKE FULL RESPONSIBILITY FOR THEIR APPLICATION OF ANY PRODUCTS.

THE SOFTWARE LICENSE AND LIMITED WARRANTY FOR THE ACCOMPANYING PRODUCT ARE SET FORTH IN THE INFORMATION PACKET THAT SHIPPED WITH THE PRODUCT AND ARE INCORPORATED HEREIN BY THIS REFERENCE. IF YOU ARE UNABLE TO LOCATE THE SOFTWARE LICENSE OR LIMITED WARRANTY, CONTACT YOUR CISCO REPRESENTATIVE FOR A COPY.

The Cisco implementation of TCP header compression is an adaptation of a program developed by the University of California, Berkeley (UCB) as part of UCB's public domain version of the UNIX operating system. All rights reserved. Copyright © 1981, Regents of the University of California.

NOTWITHSTANDING ANY OTHER WARRANTY HEREIN, ALL DOCUMENT FILES AND SOFTWARE OF THESE SUPPLIERS ARE PROVIDED "AS IS" WITH ALL FAULTS. CISCO AND THE ABOVE-NAMED SUPPLIERS DISCLAIM ALL WARRANTIES, EXPRESSED OR IMPLIED, INCLUDING, WITHOUT LIMITATION, THOSE OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NON-INFRINGEMENT OR ARISING FROM A COURSE OF DEALING, USAGE, OR TRADE PRACTICE.

IN NO EVENT SHALL CISCO OR ITS SUPPLIERS BE LIABLE FOR ANY INDIRECT, SPECIAL, CONSEQUENTIAL, OR INCIDENTAL DAMAGES, INCLUDING, WITHOUT LIMITATION, LOST PROFITS OR LOSS OR DAMAGE TO DATA ARISING OUT OF THE USE OR INABILITY TO USE THIS MANUAL, EVEN IF CISCO OR ITS SUPPLIERS HAVE BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.

All printed copies and duplicate soft copies of this document are considered uncontrolled. See the current online version for the latest version.

Cisco has more than 200 offices worldwide. Addresses and phone numbers are listed on the Cisco website at [www.cisco.com/go/offices](http://www.cisco.com/go/offices).

The documentation set for this product strives to use bias-free language. For purposes of this documentation set, bias-free is defined as language that does not imply discrimination based on age, disability, gender, racial identity, ethnic identity, sexual orientation, socioeconomic status, and intersectionality. Exceptions may be present in the documentation due to language that is hardcoded in the user interfaces of the product software, language used based on standards documentation, or language that is used by a referenced third-party product.

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: <https://www.cisco.com/c/en/us/about/legal/trademarks.html>. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1721R)

© 1994–2020 Cisco Systems, Inc. All rights reserved.



## CONTENTS

---

<b>CHAPTER 1</b>	<b>Working with Unified CCE APIs</b> 1
	Change Log 1
	API Operations 1
	Access 3
	Usage and Behavior 4
	Error Responses 6
	Pagination 7
	Shared Parameters 8
	Permissions 8
	Synchronous vs. Asynchronous Writes 9
	Search 10
	Sort 11

---

<b>CHAPTER 2</b>	<b>Active Directory Domain API</b> 13
	Active Directory Domain API 13

---

<b>CHAPTER 3</b>	<b>Administrator API</b> 15
	Administrator API 15

---

<b>CHAPTER 4</b>	<b>Agent API</b> 17
	Agent API 17

---

<b>CHAPTER 5</b>	<b>Agent Team API</b> 23
	Agent Team API 23

---

<b>CHAPTER 6</b>	<b>Attribute API</b> 27
------------------	-------------------------

Attribute API 27

---

**CHAPTER 7**      **Bucket Interval API 31**

Bucket Interval API 31

---

**CHAPTER 8**      **Bulk Job API 33**

Bulk Job API 33

---

**CHAPTER 9**      **Business Hours 37**

Business Hours API 37

Business Hour Status Reason API 40

Time Zone API 41

---

**CHAPTER 10**     **Call Type 43**

Call Type 43

---

**CHAPTER 11**     **Congestion Control API 47**

Congestion Control API 47

---

**CHAPTER 12**     **Contact Share Group API 49**

Contact Share Group API 49

---

**CHAPTER 13**     **Contact Share Rule API 51**

Contact Share Rule API 51

---

**CHAPTER 14**     **Cloud Connect Device Configuration 53**

Cloud Connect Configuration 53

---

**CHAPTER 15**     **Deployment API 57**

Deployment API 57

---

**CHAPTER 16**     **Deployment Type Info API 59**

Deployment Type Info API 59

---

<b>CHAPTER 17</b>	<b>ECC Payload API</b>	<b>63</b>
	ECC Payload API	63

---

<b>CHAPTER 18</b>	<b>Expanded Call Variable API</b>	<b>67</b>
	Expanded Call Variable API	67

---

<b>CHAPTER 19</b>	<b>Internet Script Editor API</b>	<b>71</b>
	Internet Script Editor API	71

---

<b>CHAPTER 20</b>	<b>Machine Inventory API</b>	<b>73</b>
	Machine Inventory API	73

---

<b>CHAPTER 21</b>	<b>Media Routing Domain API</b>	<b>81</b>
	Media Routing Domain API	81

---

<b>CHAPTER 22</b>	<b>Operation API</b>	<b>85</b>
	Operation API	85

---

<b>CHAPTER 23</b>	<b>Outbound API</b>	<b>89</b>
	Outbound Campaign API	90
	Campaign Status API	97
	Do Not Call API	98
	Create Do Not Call List	100
	Import API	100
	Personal Callback API	105
	Time Zone API	110

---

<b>CHAPTER 24</b>	<b>Precision Queue API</b>	<b>113</b>
	Precision Queue API	113

---

<b>CHAPTER 25</b>	<b>Scan API</b>	<b>117</b>
	Scan API	117

---

<b>CHAPTER 26</b>	<b>Single Sign-On Global State API</b>	<b>119</b>
	Single Sign-On Global State API	119

---

<b>CHAPTER 27</b>	<b>Single Sign-On Registration API</b>	<b>121</b>
	Single Sign-On Registration API	121

---

<b>CHAPTER 28</b>	<b>Single Sign-On Status API</b>	<b>123</b>
	Single Sign-On Status API	123

---

<b>CHAPTER 29</b>	<b>Skill Group API</b>	<b>127</b>
	Skill Group API	127

---

<b>CHAPTER 30</b>	<b>Status API</b>	<b>131</b>
	Configuration Rules	132
	Operation Rules	133



# CHAPTER 1

## Working with Unified CCE APIs

---

- [Change Log](#), on page 1
- [API Operations](#), on page 1
- [Access](#), on page 3
- [Usage and Behavior](#), on page 4
- [Error Responses](#), on page 6
- [Pagination](#), on page 7
- [Shared Parameters](#), on page 8
- [Permissions](#), on page 8
- [Synchronous vs. Asynchronous Writes](#), on page 9
- [Search](#), on page 10
- [Sort](#), on page 11

### Change Log

This section notes the new and changed APIs in this Unified CCE release.

#### New APIs

- [Expanded Call Variable API](#), on page 67

#### Updated APIs

See	Notes

### API Operations

There are five API operations, and they are invoked by HTTP methods.

Responses are provided using HTTP headers and HTTP body containing XML. For information on XML, see [XML](#), on page 5.

**create**

The create operation uses the HTTP POST method to make one new item and return the URL of that item in the HTTP location header. That URL can then be used to perform the get, update, and delete operations. An XML body containing the parameters and values for the new item must be specified.

**delete**

The delete operation uses the HTTP DELETE method to delete one item. The item may be marked for deletion or permanently deleted depending on the item type.

To delete more than one item at a time, refer to the Operation API.

You cannot delete **BuiltIn** items (those automatically created by the system, such as the **BuiltIn** bucket interval), items referenced in scripts, or items referenced by other items.

**get**

The get operation uses the HTTP GET method to retrieve one item. For example, to return one bucket interval record, perform the get operation using the URL:

```
https://<server>/unifiedconfig/config/bucketinterval/<id> .
```

**list**

The list operation uses the HTTP GET method to retrieve a list of items. For example, to retrieve a list of bucket intervals, perform the list operation using the URL:

```
https://<server>/unifiedconfig/config/bucketinterval. See also Permissions, on page 8, Pagination, on page 7, Search, on page 10, and Sort, on page 11.
```

**Query parameters:**

- **Summary list:** Some APIs have parameters that include a large amount of data when returned, such as collections of references. Use this query parameter to reduce the number of parameters returned for each item in the list. For example, in the Skill Group API, if skill groups contain a large number of agents, a large amount of data may be returned. Use this query option to return the basic skill group data along with the number of agents having the skill. Append the query parameter `summary=true` to the URL for the API; for example,

```
https://<server>/unifiedconfig/config/skillgroup?summary=true.
```

**update**

The update operation uses the HTTP PUT method to modify one item. An XML body containing the parameters and values to update must be specified. For example, to update the name of a bucket interval, perform the update operation on the URL

```
https://<server>/unifiedconfig/config/bucketinterval/(id) with the following body:
```

```
<bucketInterval>
  <name>newName</name>
  <changeStamp>0</changeStamp>
</bucketInterval>
```



# Access

## Administrator Access

Administrator access to Unified CCE Administration APIs and items is defined by the role for which the administrator is responsible.

The following API is not available for administrators:

- [Agent Team API, on page 23](#)

The following APIs allow update with restrictions:

- Agent Call API
  - When updating an agent, administrators can only change the following parameters:
    - skillGroups
    - defaultSkillGroup
    - skillGroupsAdded
    - skillGroupsRemoved
    - agentAttributes
    - agentAttributesAdded
    - agentAttributesRemoved
    - password
- [Skill Group API, on page 127](#)
  - When updating a skill group, administrators can only change the following parameters:
    - agents
    - agentsAdded
    - agentsRemoved

The following APIs are only available in the Contact Director deployment:

- [Contact Share Group API, on page 49](#)
- [Contact Share Rule API, on page 51](#)

## Supervisor Access

The following APIs are read only:

- [Agent Team API, on page 23](#)
  - Supervisors can only see teams that are on their peripheral.
- [Precision Queue API, on page 113](#)

The following APIs allow update with restrictions:

- [Attribute API, on page 27](#)
  - When updating an attribute, supervisors can only modify the collection of agentAttributes by adding, removing, or changing the value of agents who are on their teams.
- Agent Call API
  - Supervisors can only see and update agents who are on their teams.
  - When updating an agent, supervisors can only change the following parameters:
    - skillGroups
    - defaultSkillGroup
    - skillGroupsAdded
    - skillGroupsRemoved
    - agentAttributes
    - agentAttributesAdded
    - agentAttributesRemoved
    - password
  - The Operation API can also be used to perform updates on agents.
- [Skill Group API, on page 127](#):
  - Supervisors can only see and update skill groups that are on their peripheral.
  - When updating a skill group, supervisors can only modify the collections of agents by adding or removing agents who are on their teams.

### Agent Access

Agents have no access to the Unified CCE Administration APIs.

### Authentication

To authenticate administrators and supervisors must provide a fully qualified user name (for example, user@domain.com) and password.

### Deployment

In most deployments, all APIs are available except for the Contact Sharing APIs. You can only use the Contact Sharing APIs in a Contact Director deployment.

## Usage and Behavior

### Duplicate Parameters

If a parameter is duplicated, the final value that is specified will be used by the API.

## Read-Only Fields

Read-only parameters are ignored on create and update operations.

## References

References are a type of parameter that provide a way to connect one item to another item, defining the relationship between them.

For example, to define which team an agent belongs to, the agent contains a reference to a team. When performing list or get operations, the reference contains the refURL of the item and the name. For example:

```
<agent>
  <team>
    <refURL>/unifiedconfig/team/5000</refURL>
    <name>NameOfTeam</name>
  </team>
  ...
</agent>
```

For items that do not have a name parameter, other parameters such as firstName and lastName are included.

```
<agent>
  <refURL>/unifiedconfig/config/agent/5000</refURL>
  <firstName>Jane</firstName>
  <lastName>Doe</lastName>
  <userName>username</userName>
  <agentId>8007</agentId>
  <canRemove>true</canRemove>
</agent>
```

When doing create or update, only the refURL parameter is required. Additional parameters are ignored. For example:

```
<agent>
  <team>
    <refURL>/unifiedconfig/team/5000</refURL>
  </team>
  ...
</agent>
```

Items can also contain a collection of references. For example, if an agent belongs to multiple skill groups, the skillGroups parameter contains a reference to each associated skill group:

```
<agent>
  <skillGroups>
    <skillGroup>
      <refURL>/unifiedconfig/config/skillgroup/5001</refURL>
      <name>FirstSkill</name>
    </skillGroup>
    <skillGroup>
      <refURL>/unifiedconfig/config/skillgroup/5005</refURL>
      <name>AnotherSkill</name>
    </skillGroup>
  </skillGroups>
  ...
</agent>
```

## XML

XML is case sensitive. When XML data is sent to the server, the tag names must match. <Name> and <name> are two different XML elements.

# Error Responses

Operations that fail return an HTTP status code ([HTTP 1.1 Status Codes](#)) indicating if there was a client error or server error. The body of the response contains a collection of API error items to provide additional information about the failure.

## Parameters

- **errorType**: Indicates the type of error. This is the primary identifier for the problem and can be used to map the type to a user readable string. For example, if your application receives an error with the errorType of `invalidInput.fieldRequired`, then you could display "This field is a required field; it cannot be left blank" to the user.
- **errorData**: The name of the parameter that had the error.
- **errorMessage**: Extra information about the error that is intended for the developer. This information is typically a sentence or other string. It is not localized, so it should not be shown to the user.
- **errorDetail**: Some errors contain additional detail parameters that are included in the `errorDetail` parameter.
  - If the error type is `invalidInput.outOfRange`, then `errorDetail` includes the following parameters:
    - **min**: The minimum value allowed.
    - **max**: The maximum value allowed.
  - If you attempt to delete an item that is in use by other items, the `errorType` is `referenceViolation.api` and the `errorDetail` includes the following parameters:
    - **referenceType**: The type of item that references the item you tried to delete.
    - **references**: A collection of references, referencing the item you tried to delete, including the name and `refURL` of each referencing item.
    - **totalCount**: The total number of items referencing the item you attempted to delete.
    - **totalShown**: The total number of items included in the references collection.

## Example Error Response

The following error is returned when attempting to create a call type with a negative value for the `serviceLevelThreshold` parameter:

```
<apiErrors>
  <apiError>
    <errorData>serviceLevelThreshold</errorData>
    <errorDetail>
      <min>1</min>
      <max>2147483647</max>
    </errorDetail>
    <errorMessage>This field must contain a value from 1 to 2147483647</errorMessage>
    <errorType>invalidInput.outOfRange</errorType>
  </apiError>
</apiErrors>
```

# Pagination

Pagination allows you to limit the number of items returned by the list operation and provides information on how to get other pages.

## Query Parameters

- `startIndex`: Specifies the index of the item at which to start. Zero-based: 0 is the first item.
- `resultsPerPage`: Specifies the number of items to retrieve. Minimum:1. Default: 25. Maximum: 100.

## Returned Parameters

- `totalResults`: Total number of items.
- `resultsPerPage`: Number of items requested per page.
- `startIndex`: The index of the first item returned. If you request a `startIndex` that is greater than total items, a full last page is returned.
- `nextPage`: The URL to get the next page. This parameter is not returned if you are on the last page.
- `prevPage`: The URL to get the previous page. This parameter is not returned if you are on the first page.
- `firstPage`: The URL to get the first page.
- `lastPage`: The URL to get the last page.
- `searchTerm`: The value specified in the search query parameter. See [Search, on page 10](#).
- `sortTerm`: The value specified in the sort query parameters. See [Sort, on page 11](#).




---

**Note** Query parameters for search and sort are included in the URL.

---

## Example Response

```
<pageInfo>
  <resultsPerPage>2</resultsPerPage>
  <startIndex>0</startIndex>
  <totalResults>10</totalResults>
  <firstPage> http://<server>/bucketIntervals/?resultsPerPage=2</firstPage>
  <lastPage> http://<server>/bucketIntervals/?startIndex=8&resultsPerPage=2</lastPage>

  <prevPage/>
  <nextPage> http://<server>/bucketIntervals/?startIndex=2&resultsPerPage=2</nextPage>
</pageInfo>

<bucketIntervals>
  <bucketInterval/>
  <bucketInterval/>
</bucketIntervals>
```

# Shared Parameters

## changeStamp

- The version of the item. Initially set during a create ([create, on page 2](#)) operation.
- A changeStamp is a required parameter for the body of a PUT ([update, on page 2](#)) operation for items. If you do not provide a changeStamp, the update fails. This mechanism is in place so that two clients cannot edit the record at the same time.
- If the update is successful, the changeStamp is incremented.

## description

- A description for this item.
- Optional parameter.
- No restriction of characters; OEM locale supported characters are allowed. For information on how to configure your system to support native character sets, see the latest version of the document *Cisco Unified Contact Center Enterprise Installation and Upgrade Guide* at <https://www.cisco.com/c/en/us/support/customer-collaboration/unified-contact-center-enterprise/products-installation-guides-list.html>.
- Maximum length of 255 characters.

## name

- Required parameter.
- Maximum length of 32 characters allowed.
- Valid characters are period (.), underscore (\_), and alphanumeric. The first character must be alphanumeric.
- Does not allow internationalized characters.

## refURL

- The identifier for an item.
- Read-only parameter.

# Permissions

Permissions information is included in list responses to indicate the write operations that the user is allowed to perform. If the API does not support any write operations, then permissions information is not returned.

## Parameters

- canCreate: Indicates whether a create operation is allowed. Values are true/false. If the create operation is not supported by the API, then this parameter is not returned.

- `canUpdate`: Indicates whether an update operation is allowed. Values are true/false. If the update operation is not supported by the API, then this parameter is not returned.
- `canDelete`: Indicates whether a delete operation is allowed. Values are true/false. If the delete operation is not supported by the API, then this parameter is not returned.
- `role`: Type of role of the user performing the request. Values are administrator/supervisor.

### Example Get Response

```
<permissionInfo>
  <canCreate>>false</canCreate>
  <canUpdate>>true</canUpdate>
  <canDelete>>false</canDelete>
  <role>Administrator</role>
</permissionInfo>
```

## Synchronous vs. Asynchronous Writes

Synchronous API calls are blocking calls that do not return until either the change has been completed or there has been an error. For asynchronous calls, the response to the API call is returned immediately with a polling URL while the request continues to be processed. In heavier load conditions, it can be more efficient to submit multiple async calls and periodically check the status than to wait for each call to complete before submitting the next one.

The following examples describe how to use the asynchronous feature to create a call type.

### Performing Asynchronous Operations

The create, update, and delete operations can be performed asynchronously by including the query parameter `async=true`. The request is accepted if the operation is valid and the number of outstanding requests does not exceed the capacity. If the request is accepted, the response includes the following items:

- The response code is HTTP 202, indicating that the request has been accepted for processing.
- The location header specifies a URL that can be polled to receive updated information on the progress of the request.
- The response includes a body. See the next section **Asynchronous result parameters**.

### Asynchronous Result Parameters

- `progress`: Indicates the current state of the request. Values include the following states:
  - `IN_QUEUE`: The request passed validation and capacity checks and was put in the queue.
  - `IN_PROGRESS`: The request is being processed.

### Polling the Asynchronous Request Status

Use the URL from the location header of an asynchronous operation request to get updated status. Responses of this request are:

- If the request has not completed yet, the response contains the HTTP 202 response code, a location header with polling URL, and a response body.
- If the request has completed, the response is identical to the responses of synchronous operations, including the following:

- For a successful create, the response code is HTTP 201 and the location header has the URL of the created item.
- For a successful update or delete, the response code will be HTTP 200.
- For an unsuccessful update, a body will provide information about the failure.
- If the request has been in queue for over 30 seconds, then it is removed and an error indicates that the request timed out.

## Search

The list operation can be modified to return data you are looking for by applying the search query parameter.

### Default Search Parameters

Typically, the name and description fields are searched when specifying a search string. Refer to each API section for the default search parameters permitted. For example, a query parameter of `q=abc` causes the list operation to return only entries with a name or description containing **abc**. The search value for default parameters has the following behaviors and restrictions:

Values:

- Are case-insensitive.
- Can be contained anywhere in the parameter value.
- Can match any of the default parameters.
- Cannot include SQL wildcards. They are not supported.
- Must be URL encoded. For example, **&** must be converted to **%26** so that it is not treated as a separator for additional query parameters.




---

**Note** The default search is a case-insensitive substring search on multiple columns and hence may take a longer time to respond, depending on the number of records and columns to search for.

---

### Advanced Search

Advanced search parameters allow specific parameters to be searched. Refer to each API section for the advanced search parameters permitted. Advanced search parameters can be combined with a default search value. For example, applying the search query parameter of `q=abc routingType:1` to a dialed number list operation returns results where the routingType is set to one, and one of the default search parameters contains **abc**. Advanced search also has the following restrictions:

- Search terms must be separated by a space.
- Search terms can be specified in any order.



# Sort

A sort query parameter can be used to specify the order of the results in a list response.

The query parameter is **sort=<parameterName>** order, where:

- **parameterName**: The name of the parameter that you want to sort on. This is case sensitive, so it must match the parameter in the API exactly.
- **order**: Specifies the order of the sort. Values are as follows:
  - **asc**: Perform an ascending sort. This is the default if no order is specified.
  - **desc**: Perform a descending sort.

## Example

For example, to find all the CallTypes whose name or description contains *supervisor*, sorted in ascending order by *name*:

```
https://<server>/unifiedconfig/config/calltype?q=supervisor&sort=name
```





## CHAPTER 2

# Active Directory Domain API

---

- [Active Directory Domain API, on page 13](#)

## Active Directory Domain API

Use the Active Directory Domain API to list the active directory domains currently defined in your call center environment. It is read-only, and does not require authentication.

### URL

`https://<server>/unifiedconfig/config/activedirectorydomain`

### Operations

- [list](#): Retrieves a list of active directory domains.

### Parameters

- `name`: The name of the domain.
- `systemDomain`: Indicates if the system is a member of this domain. Values are true/false.

### Example List Response

```
<results>
  <activeDirectoryDomains>
    <activeDirectoryDomain>
      <name>boston.com</name>
      <systemDomain>>true</systemDomain>
    </activeDirectoryDomain>
    <activeDirectoryDomain>
      <name>cisco.com</name>
      <systemDomain>>false</systemDomain>
    </activeDirectoryDomain>
  </activeDirectoryDomains>
</results>
```





## CHAPTER 3

# Administrator API

---

- [Administrator API, on page 15](#)

## Administrator API

An administrator is an Active Directory user who has been provided access to the system.

Use the Administrator API to list the administrators currently defined in the database, define new administrators, and view, edit, and delete existing administrators.

### URL

`https://<server>/unifiedconfig/config/administrator`

### Operations

- **create**: Creates one administrator.
- **delete**: Permanently deletes one administrator.
- **get**: Returns one administrator, using the URL  
`https://<server>/unifiedconfig/config/administrator/<id>`.
- **list**: Retrieves a list of administrators.
- **update**: Updates one administrator.

### Parameters

- **refURL**: The refURL of the administrator. See [Shared Parameters, on page 8](#).
- **changeStamp**: See [Shared Parameters, on page 8](#).
- **description**: See [Shared Parameters, on page 8](#).
- **userName**: Required. The unique username of an existing Active Directory account. Maximum length of 64 characters.
- **domainName**: The domain for this administrator. If blank, system uses the default domain name. Maximum length of 64 characters.

- `customer`: A reference to a customer, including the `refURL`.
- `readOnly`: Required. Specifies whether the administrator has read-only access to the APIs and tools. Values are `true/false`.

### Search and Sort Values

The following table shows the parameters that are searched and the parameters that are sortable.

Search parameters	Sort parameters
<ul style="list-style-type: none"> <li>• <code>userName</code></li> <li>• <code>domainName</code></li> <li>• <code>description</code></li> </ul>	<ul style="list-style-type: none"> <li>• <code>userName</code></li> <li>• <code>domainName</code></li> <li>• <code>description</code></li> </ul>

See [Search, on page 10](#) and [Sort, on page 11](#).

### Example Get Response

```
<administrator>
  <changeStamp>0</changeStamp>
  <domainName>domain</domainName>
  <userName>user1</userName>
  <readOnly>false</readOnly>
  <customer>
    <refURL>/unifiedconfig/config/customer/(id)</refURL>
  </customer>
</administrator>
```



## CHAPTER 4

# Agent API

---

- [Agent API, on page 17](#)

## Agent API

Agents respond to contacts from customers. Use the Agent API to list the agents currently defined in the database, and view and edit existing agents.



---

**Note** Access to this API is different for supervisors and administrators. For more information, see [Access, on page 3](#).

---

### URL

`https://<server>/unifiedconfig/config/agent/`

### Operations

- **get:** Returns one agent, using the URL  
`https://<server>/unifiedconfig/config/agent/<id>`
- **list:** Retrieves a list of agents.
  - **Query parameters:**
    - **selectedAttribute:** Use this query parameter to augment the returned agent parameters with an extra parameter called `selectedAttribute`. This parameter indicates if the agent belongs to the attribute with the ID specified in this query parameter. For example, to find out which agents belong to the specified attribute, add `selectedAttribute=5000`.



---

**Note** Using `selectedAttribute` automatically sets the summary list query parameter to `true`.

---

- **selectedSkillGroup:** Use this query parameter to augment the returned agent parameters with an extra parameter called `selectedSkillGroup`. This parameter indicates if the agent belongs to

the skillgroup with the ID specified in this query parameter. For example, to find out which agents belong to the specified skill group, add `selectedSkillGroup=5001`.



---

**Note** Using `selectedSkillGroup` automatically sets the summary list query parameter to true.

---

- `ignoreRole`: Use this query parameter to allow a supervisor to see a list of all agents in the system, including agents that the supervisor does not supervise. For example, to see all agents, add `ignoreRole=true`.
- Summary list: See [list, on page 2](#).
- `update`: Updates one agent.

### Parameters

- `refURL`: The refURL for the agent. See [Shared Parameters, on page 8](#).
- `agentId`: The unique peripheral number. Maximum length of 11 characters allowed. Default is an autogenerated 7-digit number.
- `changeStamp`: See [Shared Parameters, on page 8](#).
- `description`: See [Shared Parameters, on page 8](#).
- `agentStateTrace`: Indicates if agent state tracing is turned on for the agent. True or false.
- `agentDeskSettings`: A reference to the agent's `agentDeskSettings`, including the refURL and name. See [References, on page 5](#).
- `peripheral`: Indicates the peripheral, including the ID and name, on which the agent resides.
- `person`: Required. Includes the following parameters:
  - `firstName`: Agent's first name. Maximum of 32 characters. International characters are allowed.
  - `lastName`: Agent's last name. Maximum of 32 characters. International characters are allowed.
  - `password`: Agent's password. Maximum of 256 ASCII characters. Password is case-sensitive. The password can be used when creating or updating, but is not returned.  
If the `ssoEnabled` parameter is set to true, the password is not saved.
  - `userName`: Agent's login name. Maximum of 255 ASCII characters. Must be unique. For supervisors and for agents with single sign-on (SSO) enabled, the username is the user's Active Directory or SSO account username.
  - `loginEnabled`: Whether the agent can log in. True or false. Default is true.
  - `ssoEnabled`: Whether single sign-on is supported at the agent level. True or false. Default is false. This parameter takes effect only when the global level `SSOEnabled` is mixed.
- `supervisor`: Required. Indicates whether the agent is marked as supervisor. True or false.  
If set to true, the `person userName` is used for the supervisor username and domain.



- **agentAttributes:** A collection of agent attribute ([Attribute API, on page 27](#)) references for this agent, including the description, refURL, name, and dataType for each associated attribute. Also includes the attributeValue parameter which indicates the value (true or false or 1-10) of the attribute for this agent. See [References, on page 5](#).
- **agentAttributesAdded:** A collection of agent attribute references ([Attribute API, on page 27](#)) to be added to the agent, including the agent refURL and the attributeValue of each attribute. If the attributeValue is not specified, it is assigned the default value. Agents that already have this attribute are updated with the specified attributeValue. This parameter is update only, and cannot be used with the agentAttributes parameter. This parameter can be used with the agentAttributesRemoved parameter. See [References, on page 5](#).
- **agentAttributesRemoved:** A collection of agent attribute references ([Attribute API, on page 27](#)) to be removed from the agent, including the refURL of each attribute. This parameter is update only, and cannot be used with the agentAttributes parameter. This parameter can be used with the agentAttributesAdded parameter. See [References, on page 5](#).
- **selectedAttribute:** Indicates if the agent has the specified attribute. Returned only when using the selectedAttribute query parameter. True or false.
- **skillGroups:** A collection of skill group references for this agent, including the refURL and name of each associated skill group. See [References, on page 5](#).
- **skillGroupsAdded:** A collection of skill group references to be added to the agent, including the refURL of each skill group to be added. This parameter is update only, and cannot be used with the skillGroups parameter on an update as it does not affect existing skill groups. This parameter can be used with the skillGroupsRemoved parameter. See [References, on page 5](#).
- **skillGroupsRemoved:** A collection of skill group references to be removed from the agent, including the refURL of each skill group to be removed. This parameter is update only, and cannot be used with the skillGroups parameter on an update as it does not affect existing skill groups. This parameter can be used with the skillGroupsAdded parameter. See [References, on page 5](#).
- **defaultSkillGroup:** A reference to a skill group, including the refURL and name. Identifies the default skill group associated with this agent. See [References, on page 5](#).
- **selectedSkillGroup:** Indicates if the agent has the specified skill group. Returned only when using the selectedSkillGroup query parameter. True or false.
- **agentTeam:** A reference to the agent's team, including the refURL and name. See [References, on page 5](#).
- **supervisorTeams:** If this agent has supervisor access, this collection of references is for this supervisor's teams, including the refURL and name of each supervised team. See [References, on page 5](#).

### Search and Sort Values

The following table shows the parameters that are searched and the parameters that are sortable.

Search parameters	Sort parameters
<ul style="list-style-type: none"> <li>• agentId</li> <li>• description</li> <li>• person.firstName</li> <li>• person.lastName</li> <li>• person.userName</li> </ul>	<ul style="list-style-type: none"> <li>• agentId</li> <li>• description</li> <li>• supervisor</li> <li>• agentStateTrace</li> <li>• agentTeam.name</li> <li>• person.firstName</li> <li>• person.lastName</li> <li>• person.userName</li> <li>• person.loginEnabled</li> <li>• person.ssoEnabled</li>   <li>• peripheral.name</li> </ul>

See [Search](#), on page 10 and [Sort](#), on page 11.

### Advanced search parameters

There are several advanced searches you can perform on the Agent API, including supervisor, attributes, skillgroups, team, and include and exclude (agentId).

- **supervisor: (true/false)** Find agents that are (or are *not*) supervisors.
  - **q=supervisor:true** Returns all agents who are supervisors.
  - **q=supervisor:false** Returns all agents who are *not* supervisors.
  
- **attributes: (attr1 & attr2 & attr3, ...)** find *all* agents that have *all* the specified attributes. Up to ten attributes can be specified. The attribute names are fully matched.
  
- **skillgroups: (skill1 & skill2 & skill3,...)** find *all* agents that have *all* the specified skillgroups. Up to ten skillgroups can be specified. The skillgroup names are fully matched.
  
- **team: (team1|team2|team3, ...)** find *all* agents who belong to *any* of the specified teams. Up to ten team names can be specified. The team name is fully matched.
  
- **usernames:(username1|username2|username3, ...)** find *all* agents who belong to *any* of the specified username. Up to fifteen usernames can be specified. The username name is fully matched.
  
- **include: (ID1 & ID2 & ID3, ...)** find *all* specified agents even if they do not meet other search criteria. Each agentId is fully matched.
  
- **exclude:(ID1 & ID2 & ID3, ...)** exclude *all* specified agents from the results even if they meet all other search criteria. Each agentId is fully matched.



**Note** If a search string contains both basic and advanced search parameters, only the basic search parameter is considered and displayed. The advanced search parameter is ignored from the search criteria.

If a search string contains either the basic or the advanced search parameter, the respective search parameter is considered in the search criteria.

For example, consider the search string "person usernames:(person1@boston.com)".

The above string contains both search criteria [basic — person and advanced — usernames:(person1@boston.com)]. So, the advanced search criteria is ignored and the basic search criteria is considered. The search result is displayed based on the basic search criteria, that is the number of instances of agents.

### Example Get Response

```
<agent>
  <changeStamp>2877</changeStamp>
  <refURL>/unifiedconfig/config/agent/5017</refURL>
  <agentId>8006</agentId>
  <agentStateTrace>>false</agentStateTrace>
  <peripheral>
    <id>5000</id>
    <name>CUCM_PG_1</name>
  </peripheral>
  <description>an agent</description>
  <person>
    <firstName>Agent2</firstName>
    <lastName>Agent2</lastName>
    <loginEnabled>>true</loginEnabled>
    <userName>Agent2@cisco.com</userName>
    <password>mypassword</password>
    <ssoEnalbed>>false</ssoEnabled>
  </person>
  <agentDeskSettings>
    <name>test2</name>
    <refURL>/unifiedconfig/config/agentdesksetting/5434</refURL>
  </agentDeskSettings>
  <supervisor>>true</supervisor>
  <agentAttributes>
    <agentAttribute>
      <attribute>
        <refURL>/unifiedconfig/config/attribute/5004</refURL>
        <name>Sales</name>
        <dataType>4</dataType>
        <description>Sales proficiency</description>
      </attribute>
      <attributeValue>8</attributeValue>
      <description>masters certification</description>
    </agentAttribute>
  </agentAttributes>
  <skillGroups>
    <skillGroup>
      <refURL>/unifiedconfig/config/skillgroup/5229</refURL>
      <name>Support</name>
    </skillGroup>
  </skillGroups>
  <defaultSkillGroup>
    <refURL>/unifiedconfig/config/skillgroup/5229</refURL>
  </defaultSkillGroup>
</agent>
```

```
        <name>Support</name>
    </defaultSkillGroup>

    <agentTeam>
        <refURL>/unifiedconfig/config/agentteam/5003</refURL>
        <name>theTeam</name>
    </agentTeam>
    <supervisorTeams>
        <supervisorTeam>
            <refURL>/unifiedconfig/config/agentteam/5003</refURL>
            <name>theTeam</name>
        </supervisorTeam>
        <supervisorTeam>
            <refURL>/unifiedconfig/config/agentteam/5006</refURL>
            <name>theBTeam</name>
        </supervisorTeam>
    </supervisorTeams>
</agent>
```



## CHAPTER 5

# Agent Team API

---

- [Agent Team API](#), on page 23

## Agent Team API

You can associate a set of agents to a team with a specific supervisor. The supervisor can run reports on that team and receive Supervisor Assist requests from its members.

You can use the Agent Team API to list and view the agent teams currently defined in the database.



---

**Note** Access to this API is different for supervisors and administrators. For more information, see [Access](#), on page 3.

---

### URL

`https://<server>/unifiedconfig/config/agentteam`

### Operations

- **get**: Returns one agent team, using the URL `https://<server>/unifiedconfig/config/agentteam/<id>`.
- **list**: Retrieves a list of agent teams.
  - **Query parameters:**
    - Summary list: See [list](#), on page 2.

### Parameters

- **refURL**: The refURL of the agent team. See [Shared Parameters](#), on page 8.
- **name**: The name of the agent team. See [Shared Parameters](#), on page 8.
- **description**: See [Shared Parameters](#), on page 8.

- **dialedNumber:** A reference to an internal dialed number () for the agent team, including the refURL and dialed number string. See [References, on page 5](#).
- **agents:** A collection of agent (Agent Call API) references, including the refURL, first name, last name, username, and agent ID for each agent on the team. See [References, on page 5](#).
- **agentCount:** Read-only field. Number of agents on the team.
- **supervisors:** A collection of supervisor (Agent Call API) references, including the refURL, first name, last name, username, and agent ID for each supervisor who supervises this team. See [References, on page 5](#).
- **supervisorCount:** Read-only field. Number of supervisors who supervise this team.

### Search and Sort Values

The following table shows the parameters that are searched and the parameters that are sortable.

Search parameters	Sort parameters
<ul style="list-style-type: none"> <li>• name</li> <li>• description</li> </ul>	<ul style="list-style-type: none"> <li>• name (default)</li> <li>• description</li> </ul>

See [Search, on page 10](#) and [Sort, on page 11](#).

### Example Get Response

```
<agentTeam>

  <refURL>/unifiedconfig/config/agentteam/ (id) </refURL>
  <name>team1</name>
  <dialedNumber>
    <refURL>/unifiedconfig/config/dialednumber/ (id) </refURL>
    <dialedNumberString>8885551212</dialedNumberString>
  </dialedNumber>
  <description>test agent team1</description>
  <agents>
    <agent>
      <refURL>/unifiedconfig/config/agent/ (id_1) </refURL>
      <firstName>John</firstName>
      <lastName>Smith</lastName>
      <userName>username</userName>
      <agentId>8006</agentId>
    </agent>
    <agent>
      <refURL>/unifiedconfig/config/agent/ (id_2) </refURL>
      <firstName>Jane</firstName>
      <lastName>Doe</lastName>
      <userName>username</userName>
      <agentId>8007</agentId>
    </agent>
  </agents>
  <supervisor>
    <supervisor>
      <refURL>/unifiedconfig/config/agent/ (id_3) </refURL>
      <firstName>Mary</firstName>
      <lastName>Hart</lastName>
      <userName>username</userName>
      <agentId>8008</agentId>
    </supervisor>
  </supervisor>
</agentTeam>
```

```
</supervisor>
<supervisor>
  <refURL>/unifiedconfig/config/agent/(id_4)</refURL>
  <firstName>Jack</firstName>
  <lastName>Jones</lastName>
  <userName>username</userName>
  <agentId>8009</agentId>
</supervisor>
</supervisors>
<changeStamp>0</changeStamp>
</agentTeam>
```







## CHAPTER 6

# Attribute API

---

- [Attribute API](#), on page 27

## Attribute API

Attributes identify a call routing requirement, such as language, location, or agent expertise. You can create two types of attributes: boolean or proficiency. For example, you can create a Boston attribute that specifies that the agent assigned to this attribute must be located in Boston. Then, if a precision queue requires an agent who lives in Boston, then an agent with the attributes Boston = True is a good match. When you create a proficiency attribute, you assign a proficiency level to the agent.

Use the Attribute API to list the attributes currently defined in the database, define new attributes, and view, edit, and delete existing attributes.

### URL

```
https://<server>/unifiedconfig/config/attribute
```

### Operations

- **create**: Creates an attribute.
- **delete**: Marks one attribute and associated Agent attribute values for deletion, but does not permanently delete them.
- **get**: Returns one attribute, using the URL  
`https://<server>/unifiedconfig/config/attribute/<id>`.
- **list**: Retrieves a list of attributes.
  - **Query parameters**:
    - **selectedAgentCount**: Use this query parameter to augment attribute information about multiple agents. The selectedAgentCount parameter shows the number of specified agents associated with this attribute. For example, to find out how many of agents 5000, 5001, 5002, and 5003 in the list have this associated attribute, add `selectedAgentCount=5000,5001,5002,5003`.



---

**Note** Using `selectedAgentCount` automatically sets the summary list query parameter to **true**.

---

- Summary list: See [list](#), on page 2.

- **update**: Updates one attribute.

- **Query Parameters:**

- **removeNonMatchingDepartmentalRefs**: Use this query parameter to remove all agent attributes from an attribute when they no longer belong to the department id specified in the query parameter or the global department. For example, to remove all agent attributes that do not belong to department 5000 or the global department, add `removeNonMatchingDepartmentalRefs=5000`. If this parameter is not specified, the agent attributes must belong to the attribute's department or the global department.

## Parameters

- **refURL**: The refURL of the attribute. See [Shared Parameters](#), on page 8.
- **name**: The name of the attribute. See [Shared Parameters](#), on page 8.
- **changeStamp**: See [Shared Parameters](#), on page 8.
- **description**: See [Shared Parameters](#), on page 8.
- **dataType**: The data type of the attribute. Values are:
  - 3: Boolean.
  - 4: Proficiency.
- **defaultValue**: Used to specify the default value for the attribute when assigned to an agent, if no explicit value is provided. Values are:
  - Boolean: true/false.
  - Proficiency: 1-10.
- **agentAttributes**: A collection of agent attribute references for this attribute, including the description, refURL, and read-only parameters `agentId`, `userName`, `firstName`, and `lastName`. Also includes the `attributeValue` parameter which indicates the value (true/false or 1-10) of the attribute for this agent. See [References](#), on page 5.
- **agentAttributesAdded**: A collection of agent attribute references ([Attribute API](#), on page 27) to be added to the attribute, including the agent refURL and the `attributeValue` of each agent. If the `attributeValue` is not specified, it is assigned the default value. Agents that already have this attribute are updated with the specified `attributeValue`. This parameter is update only, and cannot be used in conjunction with the `agentAttributes` parameter. This parameter can be used with the `agentAttributesRemoved` parameter. See [References](#), on page 5.

- **agentAttributesRemoved**: A collection of agent attribute references ([Attribute API, on page 27](#)) to be removed from the attribute, including the refURL of each agent. This parameter is update only, and cannot be used in conjunction with the agentAttributes parameter. This parameter can be used with the agentAttributesAdded parameter. See [References, on page 5](#).
- **agentCount**: Read-only field. Number of agents associated with the attribute.
- **selectedAgentCount**: Read-only field. Indicates the number of specified agents associated with this attribute. Returned only when using the selectedAgentCount query parameter.

### Search and Sort Values

The following table shows the parameters that are searched and the parameters that are sortable.

Search parameters	Sort parameters
<ul style="list-style-type: none"> <li>• name</li> <li>• description</li> </ul>	<ul style="list-style-type: none"> <li>• name (default)</li> <li>• dataType</li> <li>• defaultValue</li> <li>• description</li> </ul>

See [Search, on page 10](#) and [Sort, on page 11](#).

### Example Get Response

```
<attribute>
  <refURL>/unifiedconfig/config/attribute/5002</refURL>
  <changeStamp>0</changeStamp>
  <dataType>4</dataType>
  <defaultValue>1</defaultValue>
  <description>test</description>
  <name>AttributeA</name>
</attribute>
```





## CHAPTER 7

# Bucket Interval API

---

- [Bucket Interval API, on page 31](#)

## Bucket Interval API

Configure bucket intervals to report how many calls are handled or abandoned during specific, incremental time slots. Each bucket interval has a maximum of nine configurable time slots, called Upper Bounds. Upper Bounds are ranges measured in seconds to segment and capture call-handling activity. You can run reports that show calls answered and calls abandoned for these intervals.

Use the Bucket Intervals API to add new bucket intervals, edit the name of an existing bucket interval, get a list of all of the configured bucket intervals, and delete existing bucket intervals.

### URL

`https://<server>/unifiedconfig/config/bucketinterval`

### Operations

- **create**: Creates one bucket interval.
- **delete**: Deletes one bucket interval from the database.
- **get**: Returns one bucket interval, using the URL  
`https://<server>/unifiedconfig/config/bucketinterval/<id>`.
- **list**: Retrieves a list of bucket intervals.
- **update**: Updates the name of one bucket interval.

### Parameters

- **refURL**: The refURL of the bucket interval. See [Shared Parameters, on page 8](#).
- **name**: The name of the bucket interval. See [Shared Parameters, on page 8](#).
- **changeStamp**: See [Shared Parameters, on page 8](#).
- **upperBound1**: Required. The first Bucket Interval value, in seconds. Must be greater than 0. This parameter cannot be updated.

- upperBound2 to upperBound 9: Optional. The next Bucket Interval values, in seconds. Each must be greater than the previous upperBound field or be left blank (if blank, all remaining upperBound fields must also be blank). These parameters cannot be updated.

**Search and Sort Values**

The following table shows the parameters that are searched and the parameters that are sortable.

Search parameters	Sort parameters
<ul style="list-style-type: none"> <li>• name</li> </ul>	<ul style="list-style-type: none"> <li>• name (default)</li> <li>• upperBound 1-9</li> </ul>

See [Search](#), on page 10 and [Sort](#), on page 11.

**Example Get Response**

```
<bucketInterval>
  <refURL>/unified/config/bucketInterval/(id)</refURL>
  <name>test</name>

  <upperBound1>10</upperBound1>
  <upperBound2>20</upperBound2>
  <upperBound3>30</upperBound3>
  <upperBound4>40</upperBound4>
  <upperBound5>50</upperBound5>
  <upperBound6>60</upperBound6>
  <upperBound7>70</upperBound7>
  <upperBound8>80</upperBound8>
  <upperBound9>90</upperBound9>
  <changeStamp>0</changeStamp>
</bucketInterval>
```



## CHAPTER 8

# Bulk Job API

- [Bulk Job API, on page 33](#)

## Bulk Job API

Bulk jobs are a fast and efficient way to update existing agent and supervisor usernames to SSO usernames.

You can use the Bulk Job API to return a CSV template with records for agents and supervisors who are not enabled for SSO. You can also use the Bulk Job API to list the bulk jobs currently defined in the database, define new bulk jobs, and view or delete records of existing bulk jobs.



---

**Note** Avoid performing a bulk job transaction during a maintenance window.

---



---

**Note** Limit the bulk job import to 1000 records at any given instance.

---

### URL

`https://<server>/unifiedconfig/config/bulkjob`

### Operations

- **create**: Creates one bulk job.
- **delete**: Permanently deletes one bulk job.
- **get**: Returns one bulk job using the URL  
`https://<server>/unifiedconfig/config/bulkjob/<id>`.
- **get** (template):
  - **ssomigration**

Returns the ssomigration CSV template as a file attachment. The template includes the first 12,000 agent and supervisor accounts that are not enabled for SSO. The form of the request is `https://<server>/unifiedconfig/config/bulkjob/templates/ssomigration`.

If the database contains more than 12,000 non-SSO users, get the first 12,000 and update their credentials for SSO. Then get the next 12,000 users and update their credentials for SSO. Repeat until there are no more agents to migrate.

Non-SSO users can be filtered by `peripheralId`, `agentTeamId`, or both.

To filter by `peripheralId`, use the following URL:

```
https://<server>/unifiedconfig/config/bulkjob/templates/ssomigration?q=peripheralId:<peripheralId>
```

To filter by `agentTeamId`, use the following URL:

```
https://<server>/unifiedconfig/config/bulkjob/templates/ssomigration?q=agentTeamId:<agentTeamId>
```

To filter by both `peripheralId` and `agentTeamId`, use the following URL:

```
https://<server>/unifiedconfig/config/bulkjob/templates/ssomigration?q=peripheralId:<peripheralId>agentTeamId:<agentTeamId>
```

- `list`: Retrieves a list of bulk jobs.

### Parameters

- `refURL`: The refURL of the bulk job. See [Shared Parameters, on page 8](#).
- `description`: See [Shared Parameters, on page 8](#).
- `fileContent`: The content of the bulk CSV file. The size of the file must not exceed 3MB. For information about the CSV file data, see *Manage Bulk Jobs* section in the *Administration Guide for Cisco Unified Contact Center Enterprise* at <https://www.cisco.com/c/en/us/support/customer-collaboration/unified-contact-center-enterprise/products-maintenance-guides-list.html>.
- `createDateTime`: The time the bulk job was submitted. It indicates the time in milliseconds elapsed from the zero epoch value of January 1, 1970, 00:00:00 GMT. Read-only.
- `jobHostName`: The Windows computer name of the AW that initiated the bulk job. Read-only.
- `startDateTime`: The time the bulk job began executing. Read-only.
- `endDateTime`: The time the bulk job completed or failed. Read-only.
- `jobState`: The current state of the job. Read-only.
  - 1: Queued
  - 2: Processing
  - 3: Succeeded
  - 4: Failed
  - 5: Cancelled
  - 6: Partially succeeded
- `jobType`: The job type. Optional. If this parameter is not provided, the value is determined automatically based on the header in the bulk job file. If the parameter is provided, the header must match the job type specified.

The only valid value is 5, for SSO Migration.



- description: See [Shared Parameters, on page 8](#).
- logFile: A URL to download the log file for the bulk job. Read-only.
- csvFile: A URL to download the CSV file that was originally uploaded in the fileContent parameter. Read-only.

### Search and Sort Values

The following table shows the parameters that are searched and the parameters that are sortable.

Search parameters	Sort parameters
<ul style="list-style-type: none"> <li>• description</li> </ul>	<ul style="list-style-type: none"> <li>• description</li> <li>• jobType</li> <li>• jobState</li> <li>• jobHostName</li> <li>• createDateTime</li> <li>• startDateTime</li> <li>• endDateTime</li> </ul>

See [Search, on page 10](#) and [Sort, on page 11](#).

### Example Get Response

Example response for a SSO migration create job that completed successfully:

```
<bulkJob>
  <changeStamp>2</changeStamp>
  <refURL>/unifiedconfig/config/bulkjob/(id)</refURL>
  <jobHostName>CCE_AW</jobHostName>
  <createDateTime>1461785074000</createDateTime>
  <startDateTime>1461785074000</startDateTime>
  <endDateTime>1461785074000</endDateTime>
  <jobState>3</jobState>
  <jobType>5</jobType>
  <description>sso migration bulk job</description>
  <logFile>
    <refURL>/unifiedconfig/config/bulkjob/(id)/log</refURL>
  </logFile>
  <csvFile>
    <refURL>/unifiedconfig/config/bulkjob/(id)/csv</refURL>
  </csvFile>
</bulkJob>
```





## CHAPTER 9

# Business Hours

---

- [Business Hours API](#), on page 37
- [Business Hour Status Reason API](#), on page 40
- [Time Zone API](#), on page 41

## Business Hours API

Use this API to list the currently defined business hours, define new business hours, and view, edit, and delete the existing business hours.

### URL

`https://<server>/unifiedconfig/config/businesshour`

### Operations

- **create**: Creates one business hour.
- **get**: Returns one business hour using the URL  
`https://<server>/unifiedconfig/config/businesshour/<id>`
- **get(template)**: Returns a sample CSV template for Special Hours and Holidays, which is provided by the API, using the URL  
`https://<server>/unifiedconfig/config/businesshour/specialdayschedule/template`.  
The response contains the CSV template as a file attachment.
- **list**: Retrieves a list of business hours.
- **update**: Updates one business hour.
- **delete**: Permanently deletes one business hour.

### Parameters

- **changeStamp**: See [Shared Parameters](#), on page 8.
- **refURL**: The refURL of the business hour. See [Shared Parameters](#), on page 8.
- **name**: The name of the business hour. See [Shared Parameters](#), on page 8.

- description: See [Shared Parameters, on page 8](#).
- type: Required. The type of the business hour.
  - 0: 24x7
  - 1: Custom
- configuredStatus: The configured status of the business hour.
  - status: Required.
    - 0: Calendar Schedule
    - 1: Force Close
    - 2: Force Open
  - statusReason: Required if the status is Force Open or Force Close.
- runTimeStatus: The run time status of the business hour. Available only in Get. It cannot be set or updated.
- timezone: Required. The time zone of the business hour.
- weekDaySchedules: The list of schedules on weekdays of business. Required only when business hour type is Custom.
  - dayOfWeek: Required.
    - 0: Sunday
    - 1: Monday
    - 2: Tuesday
    - 3: Wednesday
    - 4: Thursday
    - 5: Friday
    - 6: Saturday
  - startTime: Required. Format HH:MM
  - endTime: Required. Format HH:MM
- specialDaySchedules: The list of schedules on special days of business.
  - date: Required. Format: DD-MM-YYYY
  - startTime: Required, if the status is Open. Format: HH:MM
  - endTime: Required, if the status is Open. Format: HH:MM
  - description: Optional. Maximum of 255 characters.
  - status: Required.
    - 0: Closed

- 1: Open
- statusReason: Required. The refURL to existing status reason.

### Search and Sort Values

The following table shows the parameters that are searched and the parameters that are sortable.

Search parameters	Sort parameters
<ul style="list-style-type: none"> <li>• name</li> <li>• description</li> </ul>	<ul style="list-style-type: none"> <li>• name</li> <li>• runTimeStatus</li> <li>• runTimeStatusReason</li> <li>• type</li> <li>• timezone.displayName</li> </ul>

See [Search](#), on page 10 and [Sort](#), on page 11.

### Example Get Response

```
<businessHour>
  <refURL>/unifiedconfig/config/businesshour/1000</refURL>
  <changeStamp>0</changeStamp>
  <runTimeStatus>2</runTimeStatus>
  <runTimeStatusReason>closed</runTimeStatusReason>
  <name>credit_card</name>
  <type>1</type>
  <description>Business Line of Credit</description>
  <timezone>
    <refURL>/unifiedconfig/config/timezone/3001</refURL>
    <displayName>(UTC-05:00) Eastern Time (US & Canada)</displayName>
  </timezone>
  <configuredStatus>
    <status>1</status>
    <statusReason>
      <refURL>/unifiedconfig/config/businesshourstatusreason/5000</refURL>
      <reasonText>Emergency</reasonText>
    </statusReason>
  </configuredStatus>
  <specialDaySchedules>
    <specialDaySchedule>
      <refURL>/unifiedconfig/config/businesshour/1000/specialdayschedule/2001</refURL>

      <changeStamp>0</changeStamp>
      <date>04-02-2019</date>
      <startTime>03:26</startTime>
      <endTime>04:16</endTime>
      <description>Thanksgiving Day</description>
      <status>1</status>
      <statusReason>
        <refURL>/unifiedconfig/config/businesshourstatusreason/5000</refURL>
        <reasonText>Emergency</reasonText>
      </statusReason>
    </specialDaySchedule>
  </specialDaySchedules>
  <weekDaySchedules>
```

```

    <weekDaySchedule>
      <refURL>/unifiedconfig/config/businesshour/1000/weekdayschedule/1001</refURL>
      <changeStamp>0</changeStamp>
      <dayOfWeek>1</dayOfWeek>
      <startTime>06:20</startTime>
      <endTime>07:22</endTime>
    </weekDaySchedule>
  </weekDaySchedules>
</businessHour>

```

## Business Hour Status Reason API

Use this API to list the currently defined business hour status reasons, define new status reasons, and view, edit, and delete the existing status reasons.

### URL

`https://<server>/unifiedconfig/config/businesshourstatusreason`

### Operations

- **create**: Creates one business hour status reason.
- **get**: Returns one business hour status reason using the URL  
`https://<server>/unifiedconfig/config/businesshourstatusreason/<id>`
- **list**: Retrieves a list of business hour status reasons.
- **update**: Updates one business hour status reason.
- **delete**: Permanently deletes one business hour status reason.

### Parameters

- **category**: Optional. The category of the reason codes: User-defined or System-defined.
- **reasonCode**: Required. The unique status reason code for business hour. Range is 1001 to 65535.




---

**Note** Codes 1 to 1000 are reserved as system defined reason codes. The System-defined reason codes cannot be deleted.

---

- **reasonText**: Optional. The reason for the business schedule. Maximum of 255 characters.

### Example Create Request

```

<businessHourStatusReason>
  <category>User-defined</category>
  <reasonCode>1234</reasonCode>
  <reasonText>Emergency</reasonText>
</businessHourStatusReason>

```

### Example Get Response

```
<businessHourStatusReason>
  <refURL>/unifiedconfig/config/businesshourstatusreason/5000</refURL>
  <changeStamp>0</changeStamp>
  <category>User-defined</category>
  <reasonCode>2550</reasonCode>
  <reasonText>Open</reasonText>
</businessHourStatusReason>
```

## Time Zone API

Use the Time Zone API to list all available time zones and to get time zone information for a specified zone. Time zone information is stored in the registry of the Windows operating system.



**Important** Microsoft periodically releases cumulative time zone updates. These updates include worldwide changes to time zone names, bias (the amount of time in minutes that a time zone is offset from Coordinated Universal Time (UTC)), and observance of daylight saving time. These patches update the information in the Windows registry. When these updates are available, apply them to all virtual machines in the deployment that are running a Microsoft Windows operating system.

Use this API with the Business Hours API to set the default time zone for a business hour.

This API is read-only.

### URL

`https://<server>/unifiedconfig/config/timezone/v2`

### Operations

- **list**: Retrieves a list of available time zones. The list is sorted by UTC offset from the International Date Line from west to east.
- **get**: Returns information for a specific time zone using the URL  
`https://<server>/unifiedconfig/config/timezone/v2/<id>`.

### Response Parameters

- **name**: The name of the time zone.
- **displayName**: Specific bias and location information about the time zone, such as the offset from UTC and one or more places located within the time zone.  
Example: “(UTC-05:00) Eastern Time (US & Canada)”
- **changeStamp**: See [Shared Parameters, on page 8](#).

### Example Get Response

```
<timezone>
  <refURL>/unifiedconfig/config/timezone/v2/5000</refURL>
  <changeStamp>0</changeStamp>
```

```
<displayName>(UTC-05:00) Eastern Time (US & Canada)</displayName>  
<name>UTC</name>  
</timezone>
```





# CHAPTER 10

## Call Type

---

- [Call Type, on page 43](#)

## Call Type

Call types categorize calls. Based on call type, the system maps a dialed number to a routing script that ultimately sends the call to the appropriate destination.

Use the Call Type API to list the call types currently defined in the database, define new call types, and view, edit, or delete records of existing call types.

### URL

```
https://<server>/unifiedconfig/config/calltype
```

### Operations

- **get**: Returns one call type, using the URL  
`https://<server>/unifiedconfig/config/calltype/<id>`.
- **list**: Retrieves a list of call types.
- **update**: Updates one call type.

### Parameters

- **refURL**: The refURL of the call type. See [Shared Parameters, on page 8](#).
- **name**: The name of the call type. See [Shared Parameters, on page 8](#).
- **changeStamp**: See [Shared Parameters, on page 8](#).
- **description**: See [Shared Parameters, on page 8](#).
- **id**: The database id of the call type. Read-only field. Used in scripting.
- **serviceLevelThreshold**: Maximum time in seconds that a caller should wait before being connected with an agent. Leave blank to use the system default.
- **serviceLevelType**: This value indicates how the system calculates the service level.

- blank: Use the system default.
  - 1: Ignore Abandoned Calls.
  - 2: Abandoned Calls have Negative Impact.
  - 3: Abandoned Calls have Positive Impact.
- bucketInterval: A reference to the bucket interval ([Bucket Interval API, on page 31](#)), including the refURL and name.
  - survey: Is used to map call type with survey type.

The two Survey types are

1. Questionnaire Name: Is used to identify the **Inline Survey** which is Digital Channel (Email and Chat) and Post Call Voice Survey.
2. Dispatch Id: Is used to identify **Deferred Survey** which is Post Call Email and SMS Survey.



**Note** You can associate only one survey to a call type.

The above parameters will be available only if you have added **Cloud Connect** in the Inventory page, and configured **Webex Experience Management** in the system.

### Search and Sort Values

The following table shows the parameters that are searched and the parameters that are sortable.

Search parameters	Sort parameters
<ul style="list-style-type: none"> <li>• name</li> <li>• description</li> <li>• id</li> </ul>	<ul style="list-style-type: none"> <li>• name (default)</li> <li>• description</li> <li>• id</li> <li>• serviceLevelThreshold</li> <li>• serviceLevelType</li> </ul>

See [Search, on page 10](#) and [Sort, on page 11](#).

### Example Get Response

```
<callType>
<department>
<refURL>/unifiedconfig/config/department/5001</refURL>
<name>Sales</name>
</department>
<refURL>/unifiedconfig/config/calltype/(id)</refURL>
<name>test</name>
<description>test call type</description>
<id>5002</id>
```

```
<serviceLevelThreshold>10</serviceLevelThreshold>
<serviceLevelType>1</serviceLevelType>
<changeStamp>0</changeStamp>
<bucketInterval>
<refURL>/unifiedconfig/config/bucketinterval/(id)</refURL>
<name>bucket1</name>
</bucketInterval>
<survey>
<questionnaireName>1d222cb3</questionnaireName>
  OR <dispatchId>115097d3-ea65-432b-b90a-08aa7e5de361</dispatchId>
</survey>
</callType>
```





## CHAPTER 11

# Congestion Control API

---

- [Congestion Control API, on page 47](#)

## Congestion Control API

Congestion control parameters determine how calls are treated by the system when too many calls are received at one time. Use the Congestion Control API to list or edit the current congestion control parameters in the database.

### URL

`https://<server>/unifiedconfig/config/congestioncontrol`

### Operations

- [get](#): Returns the congestion control parameters, using the URL `https://<server>/unifiedconfig/config/congestioncontrol`.
- [update](#): Updates the congestion control parameters.

### Parameters

- `deploymentType`: The type of deployment.
- `congestionEnabled`: Indicates if congestion control is enabled. Value is true/false.
- `congestionTreatmentMode`: Mode to handle congestion. Values are:
  - 1: Dialed Number default label is used for call treatment.
  - 2: Treat call with Routing client default label.
  - 3: Treat call with System default label.
  - 4: Terminate with Dialog Fail/RouteEnd.
  - 5: Release message to the Routing client.
- `systemDefaultLabel`: Default label string to treat the calls subjected to congestion control. Only used if `congestionTreatmentMode` is set to 3 (Treat call with System default label).

- `cpsCapacity`: The maximum number of calls per second allowed.
- `cpsCapacityDefault`: The default value for the `cpsCapacity` parameter for the current deployment type. Read-only.

### Example Get Response

```
<congestionControl>
  <deploymentType>0</deploymentType>
  <congestionTreatmentMode>1</congestionTreatmentMode>
  <congestionEnabled>true</congestionEnabled>
  <systemDefaultLabel></systemDefaultLabel>
  <cpsCapacity>100</cpsCapacity>
  <cpsCapacityDefault>150</cpsCapacityDefault>
</congestionControl>
```



## CHAPTER 12

# Contact Share Group API

---

- [Contact Share Group API, on page 49](#)

## Contact Share Group API

The Contact Share group is a routing entity that operates on a single Contact Share rule with a set of Contact Share queues. It is used to determine to which target Unified CCE to send the call, given the definition of the rule and the realtime data on each of the queues. This API is only available on the Contact Director Deployment.



---

**Note** To learn more about the other Contact Share APIs available in the Contact Director Deployment, see [Access, on page 3](#).

---

### URL

`https://<server>/unifiedconfig/config/contactsharegroup`

### Parameters

- `changeStamp`: See [Shared Parameters, on page 8](#).
- `refURL`: The refURL of the Contact Share group. See [Shared Parameters, on page 8](#).
- `contactShareRule`: Required. The refURL of a Contact Share rule to apply to this group.
- `name`: Required. The name of the Contact Share group.
- `acceptQueueIf`: Optional. A logical expression that qualifies individual queues to be used in the group.
- `description`: Optional. The description of the group.
- `contactShareQueues`: Optional. Information for any Queues in the Contact Share group.

### Operations

- `create`: Creates one Contact Share group.
- `delete`: Deletes one Contact Share group.

- **get**: Returns one Contact Share group, using the URL `https://<server>/unifiedconfig/config/contactsharegroup<id>`.
- **list**: Retrieves a list of Contact Share group.
- **update**: Updates one Contact Share group.

### Search and Sort Values

The following table shows the parameters that are searched and the parameters that are sortable.

Search parameters	Sort parameters
<ul style="list-style-type: none"> <li>• name</li> <li>• description</li> <li>• groupExpression</li> </ul>	<ul style="list-style-type: none"> <li>• name(default)</li> <li>• description</li> <li>• groupExpression</li> </ul>

See [Search](#), on page 10 and [Sort](#), on page 11.

### Example Get Response

```
<contactShareGroup>
  <changeStamp>0</changeStamp>
  <refURL>/unifiedconfig/config/contactsharegroup/5000</refURL>
  <contactShareRule>
    <name>Cisco_MED</name>
    <refURL>/unifiedconfig/config/contactsharerule/5000</refURL>
  </contactShareRule>
  <name>test</name>
  <acceptQueueIf>Call.PeripheralVariable1==1</acceptQueueIf>
  <description>test something</description>
  <contactShareQueues>
    <contactShareQueue>
      <refURL>/unifiedconfig/config/contactsharequeue/5000</refURL>
      <name>CSQ-1</name>
      <queueType>skillGroup</queueType>
      <targetInstance>
        <id>5000</id>
        <name>cs01</name>
      </targetInstance>
    </contactShareQueue>
  </contactShareQueues>
</contactShareGroup>
```





## CHAPTER 13

# Contact Share Rule API

---

- [Contact Share Rule API, on page 51](#)

## Contact Share Rule API

A Contact Share rule is required when configuring a Contact Share group. A group is sent in every routing request to the Contact Share process. Each group has a rule that defines the logic for selecting a skill group or precision queue in that group for a routing request. Use the Contact Share Rules API to create, update, list, and delete rules. This API is only available on the Contact Director deployment.



---

**Note** To learn more about the other APIs available in the Contact Director deployment, see [Access, on page 3](#).

---

### URL

`https://<server>:/unifiedconfig/config/contactsharerule`

### Parameters

- `refURL`: The refURL of the Contact Share rule. See [Shared Parameters, on page 8](#).
- `name`: Required. The name of the Contact Share rule.
- `ruleExpression`: Required. The logical expression with which the rule operates.
- `description`: Optional. The description of the rule.
- `changeStamp`: See [Shared Parameters, on page 8](#).

### Operations

- `create`: Creates one Contact Share rule.
- `delete`: Permanently deletes one Contact Share rule.
- `get`: Returns one Contact Share rule, using the URL `https://<server>:/unifiedconfig/config/contactsharerule<id>`.

- [list](#): Retrieves a list of Contact Share rules.
- [update](#): Updates one Contact Share rule.

### Search and Sort Values

The following table shows the parameters that are searched and the parameters that are sortable.

Search parameters	Sort parameters
<ul style="list-style-type: none"><li>• name</li><li>• description</li><li>• ruleExpression</li></ul>	<ul style="list-style-type: none"><li>• name(default)</li><li>• description</li><li>• ruleExpression</li></ul>

See [Search, on page 10](#) and [Sort, on page 11](#).

### Example Get Response

```
<contactShareRule>
  <refURL>/unified/config/contactsharerule/(id)</refURL>
  <name>test</name>
  <ruleExpression>Call.PeripheralVariable==1</ruleExpression>
  <description>test something</description>
  <changeStamp>0</changeStamp>
</contactShareRule>
```



# CHAPTER 14

## Cloud Connect Device Configuration

- [Cloud Connect Configuration, on page 53](#)

### Cloud Connect Configuration

This is global API for *cloudconnector* (same configuration will be applicable for all the cloud connect present in the system).

The Cloud Connect API is applicable for the following deployments only:

- Unified CCE 2000 Agents.
- PCCE 2000 Agents and
- PCCE LabOnly

#### URL

`https://<server>/unifiedconfig/config/cloudconnectsettings`

#### Operations

- **Get:**

Gets the configuration information of the cloud

connect`https://<server>/unifiedconfig/config/cloudconnectsettings`

- **Put:**

Updates the proxy server and media type mapping to cloud connect.

`https://<server>/unifiedconfig/config/cloudconnectsettings`

with the following body.

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?><CloudConnectSettings>
  <registrationStatus>Registered</registrationStatus>
  <dataGenerationEnabled>
    <changeStamp>310</changeStamp>
    <analyserIntegrated>true</analyserIntegrated>
  </dataGenerationEnabled>
  <dataSource>
    <sideA>
      <address>
```

```

        <refURL>/unifiedconfig/config/machineinventory/9939</refURL>
        <name>ABC</name>
    </address>
    <userName>Cisco</userName>
    <password>Cisco</password>
</sideA>
<sideB>
    <address>
        <refURL>/unifiedconfig/config/machineinventory/9940</refURL>
        <name>XYZ</name>
    </address>
    <userName>Cisco123</userName>
    <password>Cisco</password>
</sideB>
</dataSource>
<proxyAddress>http://10.10.10.10:80</proxyAddress>
<streamerEnabled>true</streamerEnabled>
<deploymentID>9de8bdfc-d513-4ab9-a021-2b729efa9c63</deploymentID>
<deploymentName>CloudConnectSettings</deploymentName>
<changeStamp>6</changeStamp>
</CloudConnectSettings>

```

### Parameters

- **dataGenerationEnabled**: Enables data generation for Cloud Connect.
- **dataSourceAddress**: DataSource address for Cloud Connect.
- **dataSourceUserName**: DataSource user name for Cloud Connect.
- **dataSourcePassword**: DataSource password for Cloud Connect.
- **proxyAddress**: Proxy address or hostname for the Cloud Connect to connect to the Control Hub.
- **streamerEnabled**: Enables the data flow between Cloud Connect and Control Hub.

### Example Get Response

```

<?xml version="1.0" encoding="UTF-8" standalone="yes"?><CloudConnectSettings>
  <registrationStatus>Registered</registrationStatus>
  <dataGenerationEnabled>
    <changeStamp>310</changeStamp>
    <analyserIntegrated>true</analyserIntegrated>
  </dataGenerationEnabled>
  <dataSource>
    <sideA>
      <address>
        <refURL>/unifiedconfig/config/machineinventory/9939</refURL>
        <name>ABC</name>
      </address>
      <userName>Cisco</userName>
    </sideA>
    <sideB>
      <address>
        <refURL>/unifiedconfig/config/machineinventory/9940</refURL>
        <name>XYZ</name>
      </address>
      <userName>Cisco123</userName>
    </sideB>
  </dataSource>
  <proxyAddress>http://10.10.10.10:80</proxyAddress>
  <streamerEnabled>true</streamerEnabled>

```

```
<deploymentID>9de8bdfe-d513-4ab9-a021-2b729efa9c63</deploymentID>  
<deploymentName>CloudConnectSettings</deploymentName>  
<changeStamp>6</changeStamp>  
</CloudConnectSettings>
```





## CHAPTER 15

# Deployment API

---

- [Deployment API, on page 57](#)

## Deployment API

The Deployment API is used to view the deployment type of the installation. It is read-only, and does not require authentication. To change the deployment type, use the Deployment Type Info API.

### URL

```
https://<server>/unifiedconfig/config/deployment
```

### Parameters

- `deploymentType`: The type of deployment.
- `supervisorLoginAllowed`: Indicates whether the current deployment type allows supervisor login.

### Operations

- `get`: Returns the deployment type of the installation using the URL `https://<server>/unifiedconfig/config/deployment`.

### Example Get Response

```
<deployment>
  <deploymentType>7</deploymentType>
  <supervisorLoginAllowed>true</supervisorLoginAllowed>
</deployment>
```







## CHAPTER 16

# Deployment Type Info API

---

- [Deployment Type Info API, on page 59](#)

## Deployment Type Info API

Use the Deployment Type Info API to view or edit the current system deployment type.

### URL

```
https://<server>/unifiedconfig/config/deploymenttypeinfo
```

### Operations

- **get**: Returns the current deployment type and the results of the capacity and system validation tests, using the URL `https://<server>/unifiedconfig/config/deploymenttypeinfo`.
- **update**: Sets the specified deployment type if the system validation check, capacity check, and VM Validation for that deployment type pass and are required.

### Parameters

- **changeStamp**: See [Shared Parameters, on page 8](#).
- **vmHosts**: vmHost information, including name, address, username, and password parameters of Side A and Side B. Only required when switching to Packaged CCE, to allow access to the ESX servers for VM validation.
- **permissionInfo**: See [Permissions, on page 8](#).
- **systemValidationStatus**: A collection of validationRules that show the potential errors regarding system configuration. Each rule contains the following parameters:
  - **name**: The name of the rule.
  - **isValid**: Indicates if the rule is passing. Values are true/false.
  - **min**: The minimum number of items required to match for this rule.
  - **max**: The maximum number of items required to match for this rule.
  - **actual**: The current number of items configured that match this rule.

- **capacityInfo**: A collection of **capacityRules** indicating if the capacity limits are valid. Each rule contains the following parameters:
  - **name**: The name of the capacity rule.
  - **max**: The maximum number of items allowed for the rule.
  - **actual**: The current number of items configured for the rule.
- **vmValidationLogURL**: The URL to download a file about VM layout validation.
- **deploymentType**: The type of deployment. The following types are supported:
  - 0: No deployment type specified. Initial type set at installation. Once set to another deployment type, you cannot switch back to 0.
  - 1: NAM (Deprecated)
  - 2: Contact Director
  - 3: NAM Rogger (Deprecated)
  - 4: ICM Router/Logger
  - 5: UCCE: 8000 Agents Router/Logger
  - 6: UCCE: 12000 Agents Router/Logger
  - 7: Packaged CCE: 2000 Agents
  - 8: ICM Rogger
  - 9: UCCE: 4000 Agents Rogger
  - 10: Packaged CCE: Lab Mode
  - 11: HCS-CC: 2000 Agents
  - 12: HCS-CC: 500 Agents (Deprecated)
  - 13: UCCE: Progger (Lab Only)
  - 14: HCS-CC: 4000 Agents
  - 15: HCS-CC: 12000 Agents
  - 16: UCCE: 2000 Agents
  - 17: Packaged CCE: 4000 Agents
  - 18: Packaged CCE: 12000 Agents
  - 19: UCCE: 24000 Agents Router/Logger
  - 20: HCS-CC: 24000 Agents



---

**Note** You can only use Live Data on deployment types UCCE: 2000 Agents, UCCE: 4000 Agents Rogger, UCCE: 8000 Agents Router/Logger, UCCE: 12000 Agents Router/Logger, UCCE: 24000 Agents Router/Logger, HCS-CC: 2000 Agents, HCS-CC: 4000 Agents, HCS-CC: 12000 Agents, HCS-CC: 24000 Agents, Packaged CCE: 2000 Agents, Packaged CCE: 4000 Agents, Packaged CCE: 12000 Agents, and Packaged CCE: Lab Mode.

---

### Example Get Response

```
<deploymentTypeInfo>
  <changeStamp>59</changeStamp>
  <deploymentType>7</deploymentType>

  <vmHosts>
    <vmHost>
      <name>sideA</name>
      <address>10.86.141.10</address>
      <userName>root</userName>
    </vmHost>
    <vmHost>
      <name>sideB</name>
      <address>10.86.141.29</address>
      <userName>root</userName>
      <password>pwexample</password>
    </vmHost>
  </vmHosts>
</deploymentTypeInfo>
```





## CHAPTER 17

# ECC Payload API

- [ECC Payload API, on page 63](#)

## ECC Payload API

You use expanded call variables to store values that are associated with a call. These variables are commonly called Expanded Call Context (ECC) variables. While you can define many more ECC variables in the system, you can pass a maximum of 2000 bytes of these variables at any time over any interface. To enable you to pass different ECC variables at different times, the solution has ECC payloads.

An ECC payload is a defined set of ECC variables. You can create ECC payloads to suit the necessary information for a given operation. You can include an ECC variable in multiple ECC payloads. The particular ECC variables in a given ECC payload are called its members.



### Note

- ECC payload ID 1 is the default ECC payload. The API prevents the deletion of this ECC payload.
- In solutions that only use the default ECC payload, the Logger does not create an ECC variable that exceeds the 2000-byte limit for an ECC payload or the 2500-byte CTI Message Size limit. The Logger does this because it automatically adds all ECC variables to the default ECC payload if that is the only ECC payload.

If you create another ECC payload, the Logger no longer checks the 2000-byte limit when creating ECC variables. The Logger creates the ECC variables without assigning them to an ECC payload. Assign the new ECC variable to an appropriate ECC payload yourself, either through the ECC Payload API or through the ECC Payload Tool.

- For create and update operations, the ECC Payload API verifies that the members of the ECC payload do not exceed the 2000-byte limit.



### Important

During upgrades, when the system first migrates your existing ECC variables to the Default payload, it does not check the CTI message size limit. The member names might exceed the extra 500 bytes that is allocated for ECC payloads to a CTI client. Manually check the **CTI Message Size** counter in the **Expanded Call Variable Payload List** tool to ensure that the Default payload does not exceed the limit. If the Default payload exceeds the limit, modify it to meet the limit.

## URL

https://<server>/unifiedconfig/config/eccpayload

## Operations

- **create**: Creates one ECC payload and stores it in the database.

- **Query Parameters**

- **name**: The name of the ECC payload (Required)
- **description**: A description of the ECC payload (Optional)
- **variables**: 0 or more ECC variables (Optional)




---

**Note** Specify each variable with the `ecc.refURL` of a valid, non-deleted ECC variable.

---




---

**Note** This API supports synchronous and asynchronous create operations.

---

- **delete**: Permanently deletes one ECC payload and all its members from the database.
- **get**: Returns one ECC payload from the database, using the URL `https://<server>/unifiedconfig/config/eccpayload/<id>`.
- **list**: Retrieves a list of ECC payloads.
- **update**: Updates one ECC payload in the database.
  - **Query Parameters**
    - **changeStamp**: The change stamp for the ECC payload record which the GET returns (Required)
    - **refURL**: The `refURL` of the ECC payload to update (Required)
    - **name**: The name of the ECC payload (Optional)
    - **description**: A description of the ECC payload (Optional)
    - **variables**: 0 or more ECC variables (Optional)




---

**Note** Specify each variable with the `ecc.refURL` of a valid, non-deleted ECC variable.

---

## Parameters

- **refURL**: The refURL of the ECC payload. See [Shared Parameters](#), on page 8.

- name: The name of the ECC payload. See [Shared Parameters, on page 8](#).
- changeStamp: See [Shared Parameters, on page 8](#).
- description: See [Shared Parameters, on page 8](#).
- variables: The members of the ECC payload.

### Search and Sort Values

The following table shows the parameters that are searched and the parameters that are sortable.

Search parameters	Sort parameters
<ul style="list-style-type: none"> <li>• name</li> <li>• description</li> </ul>	<ul style="list-style-type: none"> <li>• name (default)</li> <li>• description</li> </ul>

See [Search, on page 10](#) and [Sort, on page 11](#).



**Note** This API does not support advanced search parameters.

### Example Get Response

```
<eccpayload>
  <refURL>/unifiedconfig/config/eccpayload/1</refURL>
  <changeStamp>18</changeStamp>
  <description>Initial default data.</description>
  <name>Default</name>
  <variables>
    <variable>
      <refURL>/unifiedconfig/config/expandedcallvariable/8</refURL>
      <name>POD.ID</name>
    </variable>
    <variable>
      <refURL>/unifiedconfig/config/expandedcallvariable/5009</refURL>
      <name>user.A1</name>
    </variable>
    <variable>
      <refURL>/unifiedconfig/config/expandedcallvariable/5010</refURL>
      <name>user.A2</name>
    </variable>
  </variables>
</eccpayload>
```







## CHAPTER 18

# Expanded Call Variable API

---

- [Expanded Call Variable API, on page 67](#)

## Expanded Call Variable API

Calls carry data with them as they move through the system. This data, called expanded call variable data, is embedded with the call and is visible on the agent desktop.

Use the Expanded Call Variable API to view and list the expanded call variables currently defined in the database.

### URL

`https://<server>/unifiedconfig/config/expandedcallvariable`

### Operations

- **get:** Returns one expanded call variable, using the URL `https://<server>/unifiedconfig/config/expandedcallvariable/<id>`.
- **list:** Retrieves a list of expanded call variables.

### Parameters

- **refURL:** The refURL of the expanded call variable. See [Shared Parameters, on page 8](#).
- **name:** The name of the expanded call variable. See [Shared Parameters, on page 8](#).
- **changeStamp:** See [Shared Parameters, on page 8](#).
- **description:** See [Shared Parameters, on page 8](#).
- **maxLength:** The maximum length of the expanded call variable. The value is 1 to 210.



---

**Note** Cisco Provided POD.ID variable, **Maximum length** can be modified.

---

- **eccArray:** Indicates whether the expanded call variable is an array. Values are true/false.

- **maximumArraySize:** The maximum number of elements in the array is 1 to 255. Required if `eccArray` is true; must be blank or not specified if `eccArray` is false.
- **enabled:** Indicates whether the expanded call variable is enabled. Values are true/false.
- **persistent:** Specifies whether the expanded call variable is written to the historical database with each Termination Call Detail and Route Call Detail record. Values are true/false.
  - No persistent, enabled arrays are allowed.
  - The maximum number of persistent, scalar, enabled variables is 20.
- **ciscoProvided:** Indicates whether the expanded call variable is provided by Cisco. Values are true/false. Read-only.
- **bytesRequired:** The number of bytes required to store the expanded call variable in the system. Read-only. The size is calculated using the following formula:
  - If `eccArray` is false, the size is  $5 + \text{Maximum Length}$ .
  - If `eccArray` is true, the size is  $5 + (1 + \text{Maximum length}) * \text{Maximum Array size}$ .
- **bytesRequiredInCtiServer:** The number of bytes required to send this variable to CTI Server. Read-only. The size is calculated using the following formula:
  - If `eccArray` is false, the size is  $\text{Length of name} + \text{Maximum length} + 4$ .
  - If `eccArray` is true, the size is  $(\text{Length of name} + \text{Maximum length} + 5) * \text{Maximum array size}$ .

### Search and Sort Values

The following table shows the parameters that are searched and the parameters that are sortable.

Search parameters	Sort parameters
<ul style="list-style-type: none"> <li>• name</li> <li>• description</li> </ul>	<ul style="list-style-type: none"> <li>• name (default)</li> <li>• description</li> <li>• maximumLength</li> <li>• maximumArraySize</li> <li>• eccArray</li> <li>• enabled</li> <li>• persistent</li> <li>• ciscoProvided</li> </ul>

See [Search](#), on page 10 and [Sort](#), on page 11.

### Example Get Response

```
<expandedCallVariable>
  <refURL>/unifiedconfig/config/expandedcallvariable/(id)</refURL>
```

```
<name>test</name>
<maxLength>9</maxLength>
<maximumArraySize>10</maximumArraySize>
<eccArray>true</eccArray>
<enabled>true</enabled>
<ciscoProvided>false</ciscoProvided>
<description>test expanded call variable</description>
<persistent>false</persistent>
<changeStamp>0</changeStamp>
<bytesRequired>105</bytesRequired>
<bytesRequiredInCtiServer>180</bytesRequiredInCtiServer>
</expandedCallVariable>
```





## CHAPTER 19

# Internet Script Editor API

---

- [Internet Script Editor API, on page 71](#)

## Internet Script Editor API

The Internet Script Editor API indicates whether Internet Script Editor is enabled. If Internet Script Editor is enabled in Web Setup, the API displays the download link in the format `https://<server>/install/iScriptEditor.exe`.

### URL

`/internetscripteditor`

### Operations

- `get`: Returns whether Internet Script Editor is enabled and a download link.

### Parameters

- `enabled`: Indicates whether Internet Script Editor is enabled in Web Setup. True or false.
- `downloadLink`: The download link for Internet Script Editor. This link appears only when the `enabled` parameter is true.

### Example Get Response

```
<internetScriptEditor>
  <enabled>true</enabled>
  <downloadLink>https://10.10.10.207/install/iScriptEditor.exe</downloadLink>
</internetScriptEditor>
```





## CHAPTER 20

# Machine Inventory API

- [Machine Inventory API](#), on page 73

## Machine Inventory API

This API returns the machines in the solution.

### URL

`https://<server>/unifiedconfig/config/machineinventory`

### Operations

- **create**: Creates a machine by updating the database. See the following table for restrictions per machine type.
- **delete**: Removes one machine.
- **get**: Returns one machine and all associated addresses and services based on the machine ID, using the URL `https://<server>/unifiedconfig/config/machineinventory/<id>`.
- **list**: Retrieves a list of all machines in the inventory. See the following table for more details.
- **update**: Updates one machine.

Type	Create / Update / Delete operations allowed	Number allowed
CCE_ROUTER	No	0/1 Side A 0/1 Side B
CCE_PROGGER	No	0/1 Side A 0/1 Side B
CCE_CALL_SERVER	No	0/1 Side A 0/1 Side B

Type	Create / Update / Delete operations allowed	Number allowed
CCE_PG	No	0/150 Side A 0/150 Side B
LIVE_DATA	All	0/1 Side A 0/1 Side B
PRIMARY_AW	All	0/2 Primary
SECONDARY_AW	All	0/2 Secondary
CCE_AW	Update only	0/8 Primary
IDS_PUBLISHER	All	0 or more
IDS_SUBSCRIBER	No	0 or more
FINESSE_PRIMARY	All	0 or more
FINESSE_SECONDARY	Update and Delete only	0 or more
CUIC_PUBLISHER	All	0/1
CUIC_SUBSCRIBER	No	0/1
CUIC_PUBLISHER_STANDALONE	All	0 or more
CUIC_SUBSCRIBER_STANDALONE	Update and Delete only	0 or more
EXIERNAL_CUSTOMER_COLLABORATION_PLATFORM	All	0/1
CLOUD_CONNECTOR_PUB	All	0-1
CLOUD_CONNECTOR_SUB	No	0-1





**Note** When you create a `CUIC_PUBLISHER`, `CUIC_PUBLISHER_STANDALONE`, or `FINESSE_PRIMARY` machine, any other machine in the cluster (`CUIC_SUBSCRIBER`, `CUIC_SUBSCRIBER_STANDALONE`, or `FINESSE_SECONDARY`) is automatically added to the inventory. When you delete a `CUIC_PUBLISHER`, `CUIC_PUBLISHER_STANDALONE`, or `FINESSE_PRIMARY` machine, any other machines in the cluster are also removed from the inventory. `CUIC_PUBLISHER` and `CUIC_SUBSCRIBER` have Unified Intelligence Center, Live Data, and Cisco Identity Service installed on the same VM. These machines can only be used in the following deployment types:

- UCCE: 2000 Agents
- UCCE: Progger (Lab Only)
- HCS-CC: 500 Agents (Deprecated)
- HCS-CC: 2000 Agents

If you create a `CUIC_PUBLISHER` on a system that already contains a `LIVE_DATA` machine, the `LIVE_DATA` machine is deleted. If the system already contains a `CUIC_PUBLISHER_STANDALONE` or `IDS_PUBLISHER` machine, you receive an error message of error type `INVENTORY_ONLY_ONE_CUIC_PUB_ALLOWED`.

## Parameters

### Machine parameters:

- `refURL`: The refURL of the machine. See [Shared Parameters, on page 8](#).
- `name`: External name of the machine. For example, the VM hostname. Valid characters are period (`.`), hyphen (`-`), underscore (`_`), and alphanumeric. The first character must be alphanumeric. Maximum length is 128 characters.
- `changeStamp`: See [Shared Parameters, on page 8](#).
- `type`: The type of machine.
- `autogenerated`: Indicates if the information was generated automatically.
- `hostName`: The hostname of the machine.
  - If you provide a hostname, a lookup is performed to find the FQDN for that host. If the FQDN is found, the `hostName` field is then set to that FQDN value and the Machine Address is set to the IP address corresponding to the hostname.
  - If you do not provide a hostname, a lookup is performed using the address field in the API request. If the FQDN is found, the `hostName` field is set to that FQDN value.
- `networks`: A collection of network parameters. See the Network Parameters section.

### Network parameters:

- `type`: Must be public.

- **versionInfo:** Version info available depending on the product type. Includes the following parameters (by product type):
  - UCCE: version, buildNumber, esNumber, patchVersion
  - VOS: version and buildNumber
- **address:** The IP address. Must be valid hostname, IPv4, or IPv6 address.
- **services:** A collection of service parameters. See the Services Parameters section.

#### Services parameters:

- **uri:** The service URL, for example MR\_PG\_A URL.  
For MR\_PG\_A and MR\_PG\_B, the machines on which the MR PGs reside must be configured in the Machine Inventory:

- Most Unified CCE and HCS for Contact Center deployments use the CCE\_PGs.
- Progger deployments use the CCE\_PROGGERs.
- HCS500 and HCS1000 deployments use the CCE\_CALL\_SERVERs.

The URLs must be different, and must follow the pattern  
/unifiedconfig/config/machineinventory/<id>.

- **name:** The hostname of service. This read-only parameter applies only to the MR\_PG\_A and MR\_PG\_B services. It is returned if the uri matches the unifiedconfig machine host (for example /unifiedconfig/config/machineinventory/1234 where 1234 is a valid id).
- **port:** The port for this service.  
For MR\_PG\_A and MR\_PG\_B, the default port is 38001, and the valid range is 10000 to 65535. If you do not specify a value or specify 0, the default port is used. MR\_PG\_A and MR\_PG\_B must use the same port.
- **username:** The username used to access the service. Username maximum is 128 characters.
- **password:** The password used to access the service. The password can be used when creating or updating, but is not returned.
- **description:** The description of the service. See [Shared Parameters, on page 8](#).
- **pairing:** Indicates if services on different machines are related. Related services have a matching value.  
For Contact Share node, if the service type is ACTIVE\_MQ, the pairing value contains the valid ApplicationGatewayID.  
For the service type PRINCIPAL\_AW, the pairing value is "false" for all AWs.
- **type:** The service type. Values for type are as follows:
  - LIVE\_DATA\_API: Connection information for the Live Data Rest API. Requires a username and password.
  - LIVE\_DATA\_CASSANDRA: Connection information for the Live Data Cassandra database.
  - LIVE\_DATA\_WEB\_SOCKETS: Connection information for the Live Data Socket.IO service.

- TIP\_PG: LiveData connection information for peripheral gateways.
- TIP\_ROUTER: LiveData connection information for the router.
- TIP\_PG\_TOS: LiveData test-other-side connection information for peripheral gateways.
- TIP\_ROUTER\_TOS: LiveData test-other-side connection information for the router.
- ACTIVE\_MQ: LiveData Active MQ connection information.
- STORM\_DRPC: LiveData Storm DRPC connection information.
- AW\_REST\_API: Administration & Data Server (AW) Rest API
- SM\_REST\_API: Customer Collaboration Platform REST API. Requires a username and password.
- MR\_PG\_A: Connection information for Side A MR PG. Required for Customer Collaboration Platform machines.
- MR\_PG\_B: Connection information for the Side B MR PG. Required for Customer Collaboration Platform machines.
- MR\_PG\_CONNECTION: Connection information for the MR PG. Required for Customer Collaboration Platform machines.
- IDS: Indicates an Identity Server service. IDS contains the following parameters:
  - userName: The username of the IdS for the IDS\_PUBLISHER machine.
  - components: Information about the component, including the component refURL and component name.
- IDS\_PRIMARY\_REF: When present, the <uri> parameter for this service refers to the primary Identity Server (IdS) to which this component is associated.  
When you update the IDS\_PRIMARY\_REF service type of a machine, the IDS\_SECONDARY\_REF is automatically set to the other IdS in the cluster, if present.
- IDS\_SECONDARY\_REF: Read only. The <uri> parameter for this service refers to the backup IdS to which this component is associated. For a create or update request, this field is automatically filled with the refURL of the secondary IdS (if present).
- PUBLISHER\_REF: The <uri> parameter for this service refers to the publisher/primary machine's IP Address. This service is only applicable for subscriber/secondary machines.
- CLOUD\_CONNECT\_CREDINITIALS: Credinitial information for Cloud Connect Services.

### Search and Sort Values

The following table shows the parameters that are searched and the parameters that are sortable.

Search parameters	Sort parameters
<ul style="list-style-type: none"> <li>• name</li> <li>• description</li> <li>• hostName</li> </ul>	<ul style="list-style-type: none"> <li>• name (default)</li> <li>• description</li> <li>• hostName</li> </ul>

See [Search, on page 10](#) and [Sort, on page 11](#).

### Advanced search parameters

You can perform a machine type search or a service type search on the Machine Inventory API:

- **type:<machine type>**: Returns only machines of the specified type. For example, **type:EXTERNAL\_CUSTOMER\_COLLABORATION\_PLATFORM** returns only external Customer Collaboration Platform machines. The machine type is case-insensitive.
- **serviceType:<service type>**: Returns only machines associated with the specified service type. For example, **serviceType:IDS\_PRIMARY\_REF** returns only SSO-capable machines.

### Example Update Request

`https://<server>/unifiedconfig/config/machineinventory`

```
<machine>
  <name>myLiveDataMachine</name>
  <hostName>liveDataHostName</hostName>
  <type>LIVE_DATA</type>
  <networks>
    <network>
      <type>PUBLIC</type>
      <address>1.2.3.4</address>
      <services>
        <service>
          <type>ACTIVE_MQ</type>
          <port>61616</port>
          <pairing>1</pairing>
        </service>
        <service>
          <type>STORM_DRPC</type>
          <port>3772</port>
          <pairing>1</pairing>
        </service>
        <service>
          <type>LIVE_DATA_WEB_SOCKETS</type>
          <port>12008</port>
          <pairing>1</pairing>
        </service>
        <service>
          <type>LIVE_DATA_API</type>
          <port>12005</port>
          <pairing>1</pairing>
          <userName>user</userName>
          <password>password</password>
        </service>
        <service>
          <type>LIVE_DATA_CASSANDRA</type>
          <port>12000</port>
          <pairing>1</pairing>
        </service>
      </services>
    </network>
  </networks>
</machine>
```

### Example Get Response

`https://<server>/unifiedconfig/config/machineinventory/<id>`

```

<machine>
  <changeStamp>3</changeStamp>
  <refURL>/unifiedconfig/config/machineinventory/5000</refURL>
  <networks>
    <network>
      <address>1.2.3.4</address>
      <services>
        <service>
          <autoGenerated>true</autoGenerated>
          <pairing>0</pairing>
          <port>40034</port>
          <type>TIP_ROUTER</type>
        </service>
        <service>
          <autoGenerated>true</autoGenerated>
          <pairing>0</pairing>
          <port>40035</port>
          <type>TIP_ROUTER_TOS</type>
        </service>
      </services>
      <type>PUBLIC</type>
    </network>
  </networks>
  <autoGenerated>true</autoGenerated>
  <hostName>routerA</hostName>
  <type>CCE_ROUTER</type>
  <name>routerA</name>
</machine>

```

### Example Get Response for IdS

```

<machine>
  <changeStamp>1</changeStamp>
  <refURL>/unifiedconfig/config/machineinventory/5000</refURL>
  <name>IDS-PUB-A</name>
  <type>IDS_PUBLISHER</type>
  <networks>
    <network>
      <type>PUBLIC</type>
      <address>10.10.10.22</address>
      <services>
        <service>
          <type>IDS</type>
          <userName>Admin</userName>
          <components>
            <component>
              <refURL>/unifiedconfig/config/machineinventory/6000</refURL>
              <name>FIN-PUB-A</name>
            </component>
            <component>
              <refURL>/unifiedconfig/config/machineinventory/6001</refURL>
              <name>CUIC-PUB-A</name>
            </component>
          </components>
        </service>
      </services>
    </network>
  </networks>
</machine>

```

### Example Update Request for Primary IdS

This example request updates the primary IdS for Finesse:

```

<machine>
  <changeStamp>1</changeStamp>
  <refURL>/unifiedconfig/config/machineinventory/5000</refURL>
  <name>Finesse primary</name>
  <type>FINESSE_PRIMARY</type>
  <networks>
    <network>
      <type>PUBLIC</type>
      <address>10.10.10.21</address>
      <services>
        <service>
          <type>IDS_PRIMARY_REF</type>
          <uri>/unifiedconfig/config/machineinventory/5001</uri>
        </service>
      </services>
    </network>
  </networks>
</machine>

```

### Example Updating SSO-Capable Components Associated to an IdS

SSO-capable components can be associated to an IdS with the `<components>` element. For example, a PUT request like this updates the `IDS_PRIMARY_REF` and `IDS_SECONDARY_REF` of any SSO-capable components.

This operation also deassociates any existing component references to that IdS that aren't in the list. For example, if there were three components associated to this IdS before the operation, only two components would be associated after the operation was complete.

```

<machine>
  <changeStamp>1</changeStamp>
  <refURL>/unifiedconfig/config/machineinventory/5000</refURL>
  <networks>
    <network>
      <type>PUBLIC</type>
      <address>10.10.10.22</address>
      <services>
        <service>
          <type>IDS</type>
          <components>
            <component>
              <refURL>/unifiedconfig/config/machineinventory/6000</refURL>
            </component>
            <component>
              <refURL>/unifiedconfig/config/machineinventory/6001</refURL>
            </component>
          </components>
        </service>
      </services>
    </network>
  </networks>
</machine>

```



## CHAPTER 21

# Media Routing Domain API

---

- [Media Routing Domain API, on page 81](#)

## Media Routing Domain API

A media routing domain is a collection of skill groups associated with a common media class. It is used to organize how requests for different media are routed.

Use the Media Routing Domain (MRD) API to list the MRDs currently defined in the database, define new MRDs, and view, edit, and delete existing MRDs.

The built-in Cisco\_Voice MRD and legacyMultichannel MRDs are read-only; they cannot be created, updated, or deleted. You can perform all API operations on multichannel MRDs.

### URL

```
https://<server>/unifiedconfig/config/mediaroutingdomain
```

### Operations

- **create**: Creates an MRD.
- **delete**: Permanently deletes one MRD.
- **list**: Retrieves a list of MRDs.
- **get**: Returns one MRD using the URL  
`https://<server>/unifiedconfig/config/mediaroutingdomain/<id>`.
- **update**: Updates one MRD.

### Parameters

- **refURL**: The refURL of the MRD. See [Shared Parameters, on page 8](#).
- **name**: Name of the MRD. See [Shared Parameters, on page 8](#).
- **description**: See [Shared Parameters, on page 8](#).
- **id**: The database id of the MRD. Read-only field.

- **type**: The type of MRD. Values are as follows:
  - **voice**: Used only for the built-in Cisco\_Voice MRD. These MRDs are read-only.
  - **legacyMultichannel**: Used for MRDS for the Enterprise Chat and Email application. These MRDs are read-only.
  - **multichannel**: (Default) Used for MRDs for Task Routing APIs.
- **taskLife**: If the connection goes down, the amount of time, in seconds, that the system waits before ending all tasks. Default is 1200.
- **taskStartTimeout**: The amount of time, in seconds, that the system waits between an agent being selected for a task and an agent being offered or beginning the task. When this time is reached, the system makes the agent Not Routable. Default is 30.
- **maxTaskDuration**: The maximum duration for a task, in seconds. Default is 28800.
- **serviceLevelThreshold**: Maximum time in seconds that a customer should wait before being connected with an agent. Default is 30.
- **interruptible**: Indicates if an agent can be interrupted by assigned tasks from another MRD. Values are true/false.
- **maxTasksInQueue**: The maximum number of tasks allowed to be queued at one time.
- **maxTimeInQueue**: The maximum amount of time, in seconds, a task can be queued.

### Search and Sort Values

The following table shows the parameters that are searched and the parameters that are sortable.

Search parameters	Sort parameters
<ul style="list-style-type: none"> <li>• name</li> <li>• description</li> <li>• id</li> </ul>	<ul style="list-style-type: none"> <li>• name (default)</li> <li>• description</li> <li>• id</li> <li>• interruptible</li> <li>• maxTasksInQueue</li> <li>• maxTaskDuration</li> <li>• maxTimeInQueue</li> <li>• serviceLevelThreshold</li> <li>• taskLife</li> <li>• taskStartTimeout</li> </ul>

See [Search](#), on page 10 and [Sort](#), on page 11.

### Advanced search parameters

You can perform a nonVoiceOnly search on the Media Routing Domain API:

- **nonVoiceOnly**: Set this attribute to true in the search query parameter to make the API return only media routing domains other than the Cisco\_Voice MRD. For example, **q=nonVoiceOnly:true**.



## Example Get Response

```
<mediaRoutingDomains>
  <mediaRoutingDomain>
    <changeStamp>0</changeStamp>
    <refURL>/unifiedconfig/config/mediaroutingdomain/5001</refURL>
    <description>Media channel for routing Chat tasks</description>
    <id>5001</id>
    <type>multichannel</type>
    <interruptible>>false</interruptible>
    <taskLife>1200</taskLife>
    <taskStartTimeout>30</taskStartTimeout>
    <maxTaskDuration>28800</maxTaskDuration>
    <maxTasksInQueue>1000</maxTasksInQueue>
    <maxTimeInQueue>1000</maxTimeInQueue>
    <name>Chat_Task_MRD</name>
    <serviceLevelThreshold>30</serviceLevelThreshold>
  </mediaRoutingDomain>
  <mediaRoutingDomain>
    <changeStamp>0</changeStamp>
    <refURL>/unifiedconfig/config/mediaroutingdomain/1</refURL>
    <description>Default Media Routing Domain for Cisco_Voice</description>
    <id>1</id>
    <type>voice</type>
    <interruptible>>false</interruptible>
    <taskLife>1200</taskLife>
    <taskStartTimeout>30</taskStartTimeout>
    <maxTaskDuration>28800</maxTaskDuration>
    <name>Cisco_Voice</name>
    <serviceLevelThreshold>30</serviceLevelThreshold>
  </mediaRoutingDomain>
</mediaRoutingDomains>
```





## CHAPTER 22

# Operation API

---

- [Operation API, on page 85](#)

## Operation API

Use the Operation API to save changes to several items of the same type in a single request. The following changes are allowed in an operation:

- delete: Multiple items of the same type. Any item that supports the delete operation can be deleted using the Operation API.
- Agent update: Update multiple agents (only available to supervisors).

### URL

`https://<server>/unifiedconfig/config/operation`

### HTTP Method

Use HTTP POST to submit a request to the Operation API.

### Parameters

- operationType: Indicates if the items specified in the refURLs should be updated or deleted. Values are update/delete.
- refURLs: A collection of refURL parameters indicating which items are included in the request. See [Shared Parameters, on page 8](#).
- changeset: Includes the parameters that are changed in an update operation. See Agent Call API.
  - skillGroupsAdded
  - skillGroupsRemoved

### Example Delete Request

```
<operation>
  <operationType>delete</operationType>
  <refURLs>
```

```

    <refURL>/unifiedconfig/config/calltype/5000</refURL>
    <refURL>/unifiedconfig/config/calltype/5001</refURL>
  </refURLs>
</operation>

```

### Example Update Request

```

<operation>
  <operationType>update</operationType>
  <refURLs>
    <refURL>/unifiedconfig/config/agent/5000</refURL>
    <refURL>/unifiedconfig/config/agent/5001</refURL>
  </refURLs>
  <changeSet>
    <agent>

      <skillGroupsAdded>
        <skillGroup>
          <refURL>/unifiedconfig/config/skillgroup/6000</refURL>
        </skillGroup>
      </skillGroupsAdded>
      <skillGroupsRemoved>
        <skillGroup>
          <refURL>/unifiedconfig/config/skillgroup/6001</refURL>
        </skillGroup>
      </skillGroupsAdded>
    </agent>
  </changeSet>
</operation>

```

### Response Parameters

- status: Indicates the state of the operation.
  - success: The operation succeeded for all items.
  - partialSuccess: The operation succeeded for some items, but other items had errors.
  - failure: The operation failed for all items.
- apiErrors: Errors indicate which items had errors and the cause of the error.

### Example Success Response

The following example shows the response when the delete operation is successful:

```

<operationsResult>
  <status>success</status>
</operationsResult>

```

### Example Partial Success Message

The following example shows a partial success response for a request to delete several agents:

```

<operationsResult>
  <apiErrors>
    <apiError>
      <errorDetail xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" xsi:type=

```

```

"resourceErrorDetail">
  <refURL>agent/1</refURL>
  <apiErrors>
    <apiError>
      <errorMessage>The specified ID does not exist
        in the database.</errorMessage>
      <errorType>notFound.dbData</errorType>
    </apiError>
  </apiErrors>
</errorDetail>
<errorMessage>There were one or more errors processing the following
  request: delete agent/1</errorMessage>
<errorType>operation.resourceErrors</errorType>
</apiError>
<apiError>
  <errorDetail xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" xsi:type=
    "resourceErrorDetail">
    <refURL>agent/2</refURL>
    <apiErrors>
      <apiError>
        <errorMessage>The specified ID does not exist
          in the database.</errorMessage>
        <errorType>notFound.dbData</errorType>
      </apiError>
    </apiErrors>
  </errorDetail>
  <errorMessage>There were one or more errors processing the following
    request: delete agent/2</errorMessage>
  <errorType>operation.resourceErrors</errorType>
</apiError>
</apiErrors>
<status>partialSuccess</status>
</operationsResult>

```

### Example Failure Response

The following example shows a failure response for a request to delete a call type that does not exist:

```

<operationsResult>
  <status>failure</status>
  <apiErrors>
    <apiError>
      <errorDetail xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" xsi:type=
        "resourceErrorDetail">
        <refURL>/unifiedconfig/config/calltype/9999</refURL>
        <apiErrors>
          <apiError>
            <errorMessage>The specified ID does not exist in the database.</errorMessage>
            <errorType>notFound.dbData</errorType>
          </apiError>
        </apiErrors>
      </errorDetail>
      <errorMessage>There were one or more errors processing the following request:
        delete /unifiedconfig/config
        /calltype/9999</errorMessage>
      <errorType>operation.resourceErrors</errorType>
    </apiError>
  </apiErrors>
</operationsResult>

```





## CHAPTER 23

# Outbound API

---

Outbound API allows you to use REST APIs to create, modify, and delete Outbound Option campaigns.

Outbound API provides a streamlined mechanism for creating campaigns with a single associated query rule and import rule. As such, if you use the API to create a campaign, that campaign is not available in the Outbound Campaign tool. If a campaign was created with the API, you must use the API to view, edit, or delete it. If a campaign was created with the Outbound Campaign tool, you must use the Outbound Campaign tool to view, edit, or delete it.

Administrative scripts are not required for Outbound Option campaigns created with the Outbound API. If an administrative script is provided, the information in the script overrides the information defined in the API.

Outbound API consists of the following APIs:

- **Outbound Campaign API:** Use this API to define new Outbound Option campaigns, and to view, edit, or delete existing campaigns.
  - **Campaign Status API:** Use this API to get the real-time status of running Outbound Option campaigns.
  - **Do Not Call API:** Use this API to set the Do Not Call (DNC) import rule configuration for Outbound Option. This prevents the dialer from dialing numbers on the DNC list.
  - **Import API:** Use this API to import customer contact information for an Outbound Option campaign.
  - **Personal Callback API:** Use this API to configure your Outbound Option campaign to handle personal callbacks. You can create personal callback records individually or in bulk. You can also update or delete personal callback records.
  - **Time Zone API:** Use this API to list all available time zones and to get information about a specified time zone.
- 
- [Outbound Campaign API, on page 90](#)
  - [Campaign Status API, on page 97](#)
  - [Do Not Call API, on page 98](#)
  - [Import API, on page 100](#)
  - [Personal Callback API, on page 105](#)
  - [Time Zone API, on page 110](#)

# Outbound Campaign API

An Outbound Campaign makes outgoing calls to customers for a specific purpose or task and delivers these calls to agents.

Use the Outbound Campaign API to define new outbound campaigns, and to view, edit, or delete existing outbound campaigns.




---

**Note** In the Role API, when you enable the CampaignStatus or CampaignContact subfeature in the accessList parameter for a custom role then the Outbound Campaign API is provided with Update Only Access instead of Full Access. With Update Only Access, you cannot create and delete a campaign using Outbound Campaign API.

---

## URL

`https://<server>/unifiedconfig/config/campaign`

## Operations

- **create**: Creates one campaign and stores it in the database.
- **delete**: Deletes one campaign from the database. The campaign is saved under **Configuration Manager > Miscellaneous Tools > Deleted Objects**.

You can only delete campaigns that were created using the API. You cannot use the API to delete campaigns that were created in the Outbound Option Campaign tool.

- **list**: Retrieves a list of campaigns from the database. Only campaigns that were created using the Outbound Option API are retrieved. Campaigns created using the Outbound Option Campaign tool do not appear in the list.
- **get**: Returns one campaign from the database using the URL  
`https://<server>/unifiedconfig/config/campaign/<id>`.

You must specify the ID for a campaign that was created using the API. If you specify the ID for a campaign created using the Outbound Option Campaign tool, the request returns `CceDBDataNotFoundException`.

- **update**: Updates one campaign in the database using the URL  
`https://<server>/unifiedconfig/config/campaign/<id>`.

You can only update campaigns that were created using the API. You cannot use the API to update campaigns that were created in the Outbound Option Campaign tool.

## Parameters

- **name**: Required. The name of the campaign. See [Shared Parameters, on page 8](#).
- **description**: Optional description for the campaign. See [Shared Parameters, on page 8](#).
- **linesPerAgent**: The number of lines dedicated to each agent in the campaign. Range is 1 to 100. Default is 1.5. This parameter performs as follows in the Outbound Option dialing modes:



- Preview mode: Ignored (always 1).
  - Progressive mode: Used as defined.
  - Predictive mode: Used as an initial value.
- maximumLinesPerAgent: The upper bound for the number of customers the dialer dials for a reserved agent when a campaign is running in predictive mode. Range is 1 to 100. Default is 2.
  - abandonEnabled: True or false. Default is true.
  - abandonPercent: When enabled (abandonEnabled is set to true), you can set the abandoned calls limit for the percentage of abandoned calls in the campaign. When disabled (abandonEnabled is set to false), the campaign dials without regard to the abandon limit. Range is 1 to 100. The granularity is to one 10th of a percent. Default is 3.
  - predictiveCorrectionPace: A count of the number of live voice connections that must occur before the Dialer adjusts. Increasing this number results in less frequent adjustments based on larger sample size. Decreasing this number results in more frequent adjustments using a smaller sample size. Range is 10 to 5000. Default is 70.
  - predictiveGain: The size of the adjustment to lines per agent each time an adjustment is made. Increasing this number results in larger lines per agent adjustments. Decreasing this number results in smaller lines per agent adjustments. Range is 0.1 to 3.0. Default is 1.
  - noAnswerRingLimit: The number of times the software allows a dialed phone number to ring. Range is from 2 to 10. Default is 4.
  - maxAttempts: The maximum number of attempts, including callbacks and retries. Range is from 1 to 100. Default is 3.
  - minimumCallDuration: Minimum duration (in seconds) of an outbound call. If the outbound call is less than the specified value, Outbound Option considers the call to be customer abandoned and schedules the record for a retry. To disable this feature, set the parameter to 0. Range is 0 to 10. Default is 1.
  - noAnswerDelay: The time (in minutes) that the software waits before calling back a no-answer call. Range is 1 to 99999. Default is 60.
  - busySignalDelay: The time (in minutes) that the software waits before calling back a busy phone number. Range is 1 to 99999. Default is 60.
  - customerAbandonedDelay: If a customer abandons a call, the time (in minutes) that the Dialer waits before calling the customer back. Range is 1 to 99999. Default is 30.
  - dialerAbandonedDelay: If the Dialer abandons a call, the time (in minutes) that the Dialer waits before calling the customer back. Range is 1 to 99999. Default is 60.
  - answeringMachineDelay: If an answering machine answers a call, the time (in minutes) that the Dialer waits before calling the customer back. Range is 1 to 99999. Default is 60.
  - customerNotHomeDelay: If a customer is not home, the time (in minutes) that the Dialer waits before calling the customer back. Range is 1 to 99999. Default is 60.
  - personalizedCallbackEnabled: If enabled, this parameter allows an agent to schedule a callback to a customer for a specific date and time. A personal callback connects the same agent who initiated the callback to the customer. True or false. Default is false.

- **rescheduleCallbackMode:** Determines how Outbound Option handles a personal callback if the agent is not available. Default is useCampaignDN. Options are as follows:
  - Use campaign DN
  - Same time next business day
  - Abandon
- **campaignPurposeType:** The type of campaign. Default is agentCampaign. The options are as follows:
  - **Agent Campaign:** This type of campaign uses an outbound mode that causes the Dialer to transfer every customer call associated with a specific skill group to an agent.
  - **IVR Campaign:** This type of campaign uses an outbound mode that causes the Dialer to transfer every customer call associated with a specific skill group to a service control-based IVR instead of an agent. This option allows a contact center to run unassisted outbound campaigns using prerecorded messages in the IVR.
- **ipAmdEnabled:** When enabled, directs the Dialer to perform a specific action if it detects an answering machine. True or false. Default is true.
- **amdTreatmentMode:** If enabled (ipAmdEnabled is set to true), when the Dialer detects an answering machine, it does one of the following:
  - Abandon call (default)
  - Transfer to agent
  - Transfer to IVR route point
  - Terminate tone detect
- **ipTerminatingBeepDetect:** When this parameter is set to true, the Dialer transfers the call after detecting the answering machine beep. True or false. Default is false.
- **timeZone:** Required. The refURL and display name for the selected time zone. The default time zone is UTC (Universal Coordinated Time). The display name is the text that may be displayed in a user interface and can be localized.




---

**Note** If time zone information changed due to periodic updates and the campaign's configured time zone is no longer valid, the following information is returned:

```
<timeZone>
  <refURL>/unifiedconfig/config/timezone/INVALID</refURL>
  <displayName>INVALID Time Zone</displayName>
</timeZone>
```

---

- **startTime:** The time the campaign starts dialing customer numbers. The format for this parameter is hours:minutes. Range is from 00:00 to 23:59. The default value is taken from the Blended\_Agent\_Options table column values for DialStartHours and DialStartMinutes.

- **endTime**: The time the campaign stops dialing customer numbers. The format for this parameter is hours:minutes. Range is from 00:00 to 23:59. The default value is taken from the Blended\_Agent\_Options table column values for DialEndHours and DialEndMinutes.
- **enabled**: Whether the dialer is available to call contacts. True or false. Default is false.
- **startDate**: The date that the campaign starts. The format is YYYY-MM-DD.
- **endDate**: The date that the campaign ends. The format is YYYY-MM-DD.
- **campaignPrefix**: Digits to prefix to each customer number dialed from this campaign. Maximum length of 15 digits.
- **dialingMode**: The dialing mode to use for the campaign skill groups. Valid values are as follows:
  - INBOUND
  - PREDICTIVEONLY
  - PREVIEWONLY
  - PROGRESSIVEONLY
  - PREVIEWDIRECTONLY
- **reservationPercentage**: The percentage of agents to reserve within the skill groups associated with the campaign. Range is from 0 to 100. Default is 100.
- **callProgressAnalysis**: A collection of parameters for Call Progress Analysis (CPA). Any combination of parameters within this collection can be set. If none of the parameters are provided and CPA is enabled for the campaign by default, CPA recording is set to false and default parameter values are set from the Blended\_Agent\_Options table.
  - **enabled**: When set to false, CPA for all calls made from this Dialer is disabled on a campaign-by-campaign basis, including voice detection, fax/modem detection, and answering machine detection. True or false. Default is true.
  - **record**: If enabled is set to true, you can specify this parameter. If you set it to true, the gateway provides a media stream and the Dialer records .wav files. True or false. Default is false.
  - **minSilencePeriod**: The minimum silence period (in milliseconds) required to classify a call as voice detected. If many answering machine calls are being passed through to agents as voice, then increasing this value accounts for longer pauses in answering machine greetings. Range is from 100 to 1000. Default is 608.
  - **analysisPeriod**: The number of milliseconds spent analyzing this call. If there is a short agent greeting on an answering machine, then a longer value categorizes that answering machine call as voice. If the call is to a business where the operator has a longer scripted greeting, a shorter value categorizes the long, live greeting as an answering machine call. Range is from 1000 to 10000. Default is 2500.
  - **minimumValidSpeech**: Minimum number of milliseconds of voice required to classify a call as voice detected. Range is 50 to 500. Default is 112.
  - **maxTimeAnalysis**: The maximum number of milliseconds allowed for analysis before identifying a problem analysis as dead air/low volume. Range is 1000 to 10000. Default is 3000.
  - **maxTermToneAnalysis**: The maximum number of milliseconds the dialer analyzes an answering machine voice message looking for a termination tone. If the message has an odd tone and the

analysis does not recognize it, the call is not transferred or dropped until this timeout occurs. Range is 1000 to 60000. Default is 30000.

- **skillGroupInfos**: A collection of information about the skill groups associated with the campaign.
  - **skillGroupInfo**: A collection of information about one skill group.
    - **skillGroup**: The name and the refURL of the skill group assigned to the campaign.
    - **overflowAgents**: This parameter ensures that at least one extra agent is reserved before the dialer begins dialing for a Progressive campaign. If the parameter is set to 1, at least two agents must be reserved before the dialer begins dialing. Range is 0 to 100. Default is 0.
    - **dialedNumber**: The digits that are dialed to reserve an agent in the configured skill group. This parameter can contain letters, numbers, periods (.), and underscores (\_) and can be up to ten characters in length.
    - **recordsToCache**: The minimum number of dialing numbers that each dialer caches for each of the Outbound Option skill groups. Range is 1 to 400. Default is 1.
    - **ivrPorts**: The total number of IVR ports allocated for the skill group. This parameter indicates how many ports are available for the dialer to transfer customer calls. Because this value indicates the total number of ports supported by the IVR for the current skill group, multiple skill groups can make transfer to IVR calls. One IVR can also be used to play different messages based on the route point where the contact is transferred. If multiple dialers are associated with the skill group, each dialer dials a fraction of the total number of ports. Default is 0.
    - **ivrRoutePoint**: If the campaign is a Transfer to IVR campaign or is configured to transfer AMD calls to an IVR, this parameter indicates the route point required to run the transfer to IVR routing script. This parameter must coincide with a route point configured on Unified Communications Manager and be assigned to a PGUser. Contacts are transferred to the route point, which points to a routing script. The script transfers the call to an IVR. Maximum length of 32 characters.
    - **abandonedRoutePoint**: If the campaign is a Transfer to IVR campaign or is configured to transfer AMD calls to an IVR, this number allows the dialer to play a message to calls about to be disconnected because no agents are available. This number must coincide with a route point configured on Unified Communications Manager and be assigned to the agent PG's CTI application (for example, PGUser). Contacts are transferred to this route point, which points to a routing script. The script transfers the call to an IVR. Maximum length of ten characters.
- **skillGroupInfosAdded**: A collection of skill group references to be added to the campaign, including the skill group refURL. This parameter is update only. This parameter can be used with the **skillGroupInfosRemoved** parameter. See [References, on page 5](#).
- **skillGroupInfosRemoved**: A collection of skill group references to be removed from the campaign, including the skill group refURL of each skill group. This parameter is update only. This parameter can be used with the **skillGroupInfosAdded** parameter. See [References, on page 5](#).

## Search and Sort Parameters

The following table shows the parameters that are searched and the parameters that are sortable.

Search parameters	Sort parameters
<ul style="list-style-type: none"> <li>• name</li> <li>• description</li> </ul>	<ul style="list-style-type: none"> <li>• name (default)</li> <li>• description</li> </ul>

See [Search](#), on page 10 and [Sort](#), on page 11.

### Disable All Campaigns (Emergency Stop)

The Outbound Campaign API provides a method to immediately disable all outbound campaigns that are currently enabled. To disable all of the campaigns, perform a PUT on the following URL:

`https://<server>/unifiedconfig/config/campaign/disable`

This request retrieves a list of all campaigns created using the Outbound Campaign API that are currently enabled and sets the enabled parameter to false. The Campaign Manager stops sending out records to the Dialer for these campaigns. All active records in the Dialer's memory are removed.

### Example Get Response

```
<campaign>
  <changeStamp>48</changeStamp>
  <refURL>/unifiedconfig/config/campaign/5168</refURL>
  <import>
    <refURL>/unifiedconfig/config/import/5000</refURL>
  </import>
  <abandonEnabled>true</abandonEnabled>
  <abandonPercent>3.0</abandonPercent>
  <amdTreatmentMode>abandonCall</amdTreatmentMode>
  <campaignPrefix>978</campaignPrefix>
  <campaignPurposeType>agentCampaign</campaignPurposeType>
  <dialingMode>PREVIEWONLY</dialingMode>
  <enabled>true</enabled>
  <endDate>2016-01-15</endDate>
  <endTime>17:00</endTime>
  <ipAMDEnabled>true</ipAMDEnabled>
  <ipTerminatingBeepDetect>false</ipTerminatingBeepDetect>
  <linesPerAgent>1.5</linesPerAgent>
  <maxAttempts>3</maxAttempts>
  <maximumLinesPerAgent>100.0</maximumLinesPerAgent>
  <minimumCallDuration>1</minimumCallDuration>
  <name>APIoct1</name>
  <noAnswerRingLimit>4</noAnswerRingLimit>
  <personalizedCallbackEnabled>false</personalizedCallbackEnabled>
  <predictiveCorrectionPace>70</predictiveCorrectionPace>
  <predictiveGain>1.0</predictiveGain>
  <rescheduleCallbackMode>useCampaignDN</rescheduleCallbackMode>
  <reservationPercentage>100</reservationPercentage>
  <retries>
    <answeringMachineDelay>60</answeringMachineDelay>
    <busySignalDelay>60</busySignalDelay>
    <customerAbandonedDelay>30</customerAbandonedDelay>
    <customerNotHomeDelay></customerNotHomeDelay>
    <dialerAbandonedDelay>60</dialerAbandonedDelay>
    <noAnswerDelay>60</noAnswerDelay>
  </retries>
  <skillGroupInfos>
  <skillGroupInfo>
```

```

    <ivrPorts>0</ivrPorts>
    <overflowAgents>0</overflowAgents>
    <recordsToCache>1</recordsToCache>
    <abandonedRoutePoint>12345</abandonedRoutePoint>
    <dialedNumber>123</dialedNumber>
    <ivrRoutePoint>91234</ivrRoutePoint>
    <skillGroup>
      <refURL>/unifiedconfig/config/skillgroup/5004</refURL>
      <name>errorDetailsRouteScript</name>
    </skillGroup>
  </skillGroupInfo>
</skillGroupInfos>
<startDate>2016-01-14</startDate>
<startTime>09:00</startTime>
<timeZone>
  <displayName>(UTC-05:00) Eastern Time (US & Canada)</displayName>
  <refURL>/unifiedconfig/config/timezone/Eastern%20Standard%20Time</refURL>
</timeZone>
<callProgressAnalysis>
  <enabled>true</enabled>
  <record>false</record>
  <minSilencePeriod>608</minSilencePeriod>
  <analysisPeriod>2500</analysisPeriod>
  <minimumValidSpeech>112</minimumValidSpeech>
  <maxTimeAnalysis>3000</maxTimeAnalysis>
  <maxTermToneAnalysis>30000</maxTermToneAnalysis>
</callProgressAnalysis>
</campaign>

```

### Example Create Request

```

<campaign>
  <name>APIOct1</name>
  <description>APIOct1</description>
  <dialingMode>PREVIEWONLY</dialingMode>
  <skillGroupInfos>
    <skillGroupInfo>
      <ivrPorts>0</ivrPorts>
      <overflowAgents>0</overflowAgents>
      <recordsToCache>1</recordsToCache>
      <skillGroup>
        <refURL>/unifiedconfig/config/skillgroup/5001</refURL>
        <name>sgcampaign</name>
      </skillGroup>
    </skillGroupInfo>
  </skillGroupInfos>
  <timeZone>
    <refURL>/unifiedconfig/config/timezone/UTC</refURL>
  </timeZone>
  <callProgressAnalysis>
    <enabled>true</enabled>
    <record>false</record>
    <minSilencePeriod>608</minSilencePeriod>
    <analysisPeriod>2500</analysisPeriod>
    <minimumValidSpeech>112</minimumValidSpeech>
    <maxTimeAnalysis>3000</maxTimeAnalysis>
    <maxTermToneAnalysis>30000</maxTermToneAnalysis>
  </callProgressAnalysis>
</campaign>

```

# Campaign Status API

Use the Campaign Status API to get the real-time status of running Outbound Option campaigns.

## URL

```
https://<server>/unifiedconfig/config/campaign/<campaign-id>/runtimestats
```



---

**Note** You must specify the ID for a campaign that was created using the Outbound Campaign API (see [Outbound Campaign API, on page 90](#)). If you specify the ID for a campaign created using the Outbound Option Campaign tool, the request returns `CceDBDataNotFoundException`.

---

## Operations

- `get`: Returns the runtime status of a campaign.

## Response Parameters

- `abandonDetectCount`: The number of calls abandoned by the dialer.
- `abandonToIvrCount`: The number of calls that were abandoned by the dialer and transferred to IVR.
- `agentClosedCount`: The number of preview and callback calls that were closed by the agent.
- `agentRejectedCount`: The number of preview and callback calls that were rejected by the agent.
- `answeringMachineCount`: The number of calls that detected an answering machine.
- `attemptedCount`: Summary total of the number of calls attempted.
- `busyCount`: The number of calls that detected a busy signal.
- `callBackCount`: The number of callback contacts.
- `cancelledDetectCount`: The number of calls where the dialer canceled a ringing customer call.
- `closedCount`: The number of contacts closed for any reason other than reaching a live customer.
- `customerAbandonDetectCount`: The number of calls where the customer hung up immediately after picking up the phone.
- `customerNotHomeCount`: The number of contacts where the party who answered the phone was not the customer.
- `dateTime`: The date and time when this data was updated last. The format is yyyy-MM-ddTHH:mm:ss (for example, 2016-03-13T04:50:31).
- `faxDetectCount`: The number of calls that detected a fax machine.
- `networkAnsMachineCount`: The number of calls that detected a network answering machine.
- `noAnswerDetectCount`: The number of calls that were not answered.
- `noDialToneDetectCount`: The number of calls that did not detect a dial tone.

- `noRingBackDetectCount`: The number of calls that did not detect a ring back.
- `personalCallbackCount`: The number of callback contacts scheduled.
- `sitToneDetectCount`: The number of calls that detected a special information tone (SIT).
- `talkTimeCount`: The total number of seconds that agents spent talking on the phone since midnight.
- `totalCount`: The total number of records available to dial for the current campaign.
- `totalVoiceCount`: The number of live customers that have been reached for this campaign since the last time the imported dialing list was overwritten.
- `voiceCount`: The number of calls for the day that ended in successful customer contact.
- `wrapupTimeCount`: The number of seconds that agents spent in wrap-up mode since midnight.
- `wrongNumberCount`: The number of contacts where the party who answered the phone indicated that the customer did not live there.

### Example Get Response

```
<runtimeStatus>
  <abandonDetectCount>0</abandonDetectCount>
  <abandonToIvrCount>0</abandonToIvrCount>
  <agentClosedCount>0</agentClosedCount>
  <agentRejectedCount>0</agentRejectedCount>
  <answeringMachineCount>0</answeringMachineCount>
  <attemptedCount>1</attemptedCount>
  <busyCount>0</busyCount>
  <callBackCount>0</callBackCount>
  <cancelledDetectCount>0</cancelledDetectCount>
  <closedCount>0</closedCount>
  <customerAbandonDetectCount>0</customerAbandonDetectCount>
  <customerNotHomeCount>0</customerNotHomeCount>
  <dateTime>2016-01-15T13:43:00</dateTime>
  <faxDetectCount>0</faxDetectCount>
  <networkAnsMachineCount>0</networkAnsMachineCount>
  <noAnswerDetectCount>0</noAnswerDetectCount>
  <noDialToneDetectCount>0</noDialToneDetectCount>
  <noRingBackDetectCount>0</noRingBackDetectCount>
  <personalCallbackCount>0</personalCallbackCount>
  <sitToneDetectCount>0</sitToneDetectCount>
  <talkTimeCount>1</talkTimeCount>
  <totalCount>0</totalCount>
  <totalVoiceCount>1</totalVoiceCount>
  <voiceCount>1</voiceCount>
  <wrapupTimeCount>0</wrapupTimeCount>
  <wrongNumberCount>0</wrongNumberCount>
</runtimeStatus>
```

## Do Not Call API

Use the Do Not Call API to set the Do Not Call (DNC) import rule configuration for Outbound Option so that the campaign dialer doesn't dial the numbers in the DNC list.

The DNC import is automatically scheduled to start when the file is available. After the import is complete, the file is RENAMED or DELETED based on the boolean value for the `renameFileAfterImport` field.



## URL

`https://<server>/unifiedconfig/config/dnc`

## Operations

- **create**: Sets the configuration in the database. Returns the refURL if the configuration is set.
- **delete**: Deletes the specific DNC configuration using the URL `https://<server>/unifiedconfig/config/dnc/<id>`. This does not delete the DNC import file that is present at the location of the filePath.
- **list**: Retrieves a list available DNC import rules.
- **get**: Returns the DNC import configuration from the database using the URL `https://<server>/unifiedconfig/config/dnc/<id>`.
- **update**: Updates the specific DNC import configuration with the new values using the URL `https://<server>/unifiedconfig/config/dnc/<id>`.

## Parameters

- **name**: Name of the DNC import. See [Shared Parameters, on page 8](#).
- **filePath**: Path to Microsoft Windows Distributed File System (DFS) share on the logger or accessible from the logger. Maximum length of 255 characters.
- **overwrite**: Whether the new DNC import overwrites the phone numbers from the previous DNC import. True or false. Default is false.
- **renameFileAfterImport**: Whether to delete the DNC import file after the import is complete. True or false. Default is true. If the parameter is set to true, the DNC file is renamed. If the parameter is set to false, the DNC import file is deleted.

## Search and Sort Parameters

The following table shows the parameters that are searched and the parameters that are sortable.

Search parameters	Sort parameters
<ul style="list-style-type: none"> <li>• name</li> </ul>	<ul style="list-style-type: none"> <li>• name</li> </ul>

See [Search, on page 10](#) and [Sort, on page 11](#).

## Example Get Response

```
<dnc>
  <refURL>/unifiedconfig/config/dnc/unifiedconfig/config/dnc/5001</refURL>
  <name>dnc1</name>
  <filePath>\\CCE-ROGGER-A\C$\Users\boston\Desktop\dnc.txt</filePath>
  <overwrite>>false</overwrite>
  <renameFileAfterImport>>true</renameFileAfterImport>
</dnc>
```

## Create Do Not Call List

When creating a Do\_Not\_Call list file, format it correctly using the following instructions.

### Procedure

- 
- Step 1** Using a text editor, create a text file that contains all the do-not-call phone numbers.
- Step 2** Enter a phone number for each Do Not Call entry on a new line.
- Step 3** Observe the following characteristics for each Do Not Call entry:
- Each phone number can be a maximum of 20 characters long.
  - The Do Not Call table can support up to 60 million entries, but note that the information is also stored in memory in the Campaign Manager process. Unless you set the **Overwrite table** option, each import appends to the table. A single large import or several smaller ones can create a Do Not Call list in memory that consumes all the memory for the process.
  - Each Do Not Call entry uses 16 bytes of memory. So, 60 million entries requires approximately 1 GB of memory on the Logger Side A platform.
- Step 4** Save the text file to the local server.
- 

The following is an example of a Do\_Not\_Call list:

```
2225554444
```

```
2225556666
```

```
2225559999
```

To add a customer to this list, import a Do Not Call list.

The Campaign Manager reads from the Do\_Not\_Call table. Dialing List entries are marked as Do Not Call entries only when the Campaign Manager fetches the Dialing List entry *and only when there is an exact, digit-for-digit match*. This allows Do Not Call imports to happen while a Campaign is running without rebuilding the Dialing List.




---

**Note** If the Dialing List includes a base number plus extension, this entry must match a Do Not Call entry for that same base number and same extension. The dialer will not dial the extension.

---




---

**Note** To clear the Do Not Call list, import a blank file with the Overwrite table option enabled.

---

## Import API

Use the Import API to import customer contact information for an outbound campaign. You can import up to 10,000 records in one create request.

**Note**

- You can queue up to 30 requests. If the queue has 30 requests and you submit another request, the response is HTTP 503 Service Unavailable with the boundary error condition "Request processing queue is at capacity."

If you receive this error, wait until a few requests are processed and submit the next request when the queue has less than 30 requests.

If a particular integration is doing multiple small inserts per second for a campaign and this error appears, it is more efficient to batch up the records into larger imports.

- Avoid performing a bulk job transaction during a maintenance window.
- Only administrators can use the Import API. For this reason, Import API user roles are authorized with the Active Directory, and the local cache is updated every 30 minutes (the interval cannot be modified).

**URL**

```
https://<server>/unifiedconfig/config/campaign/<id>/import
```

**Note**

You must specify the ID for a campaign that was created using the Outbound Campaign API. If you specify the ID for a campaign created using the Outbound Option Campaign tool, the request returns `CceDBDataNotFoundException`.

**Operations**

- **create**: Imports customer contacts for a specific campaign.
- **delete**: Deletes the imported contacts for a specific campaign.

**Note**

The delete operation deletes all imported contacts for the campaign. You cannot delete an individual record.

- **get** (template): Returns a sample CSV template for contacts, which is provided by the API, using the URL `https://<server>/unifiedconfig/config/campaign/import/template`. The response contains the CSV template as a file attachment.
- **get**: Retrieves the details of a single import record using the URL `https://<server>/unifiedconfig/config/campaign/<campaignId>/import/<id>`. The `<id>` is the ID of the imported contact.
- **list**: Retrieves a list of all imported contacts for the campaign.
  - **Query parameters**
    - Summary list: See [list, on page 2](#).

## Parameters

### Response Parameters for get:

- `accountNumber`: The customer's account number.
- `callsMade`: The number of calls made.
- `callStatus`: The call status of the last call placed for this record. Possible values include the following:
  - `active (A)`
  - `callbackRequested (B)`
  - `closed (C)`
  - `dialed (D)`
  - `agentRejected (J)`
  - `maxAttemptsReached (M)`
  - `pending (P)`
  - `retry (R)`
  - `personalCallbackRequested (S)`
  - `unknown (U)`

For more information about these values, see the `CallStatusZone Values` section of the *Outbound Option Guide for Unified Contact Center Enterprise* at <https://www.cisco.com/c/en/us/support/customer-collaboration/unified-contact-center-enterprise/products-user-guide-list.html>.

- `callResultOverall`: The call result from the last call placed for this record.
- `firstName`: The customer's first name.
- `lastName`: The customer's last name.
- `importDate`: The date and time that the record was imported.
- `phone01` through `phone10`: A collection of information about the customer's phones. Each phone contains the following parameters:

- `number`: The phone number.
- `callResult`: The call result from the last call placed for this phone number.

For more information about possible `callResult` values, see the `CallResult Codes and Values` section of the *Outbound Option Guide for Unified Contact Center Enterprise* at <https://www.cisco.com/c/en/us/support/customer-collaboration/unified-contact-center-enterprise/products-user-guide-list.html>.

- `dstObserved`: Whether DST is observed for this phone's location. True or false.
- `gmtOffset`: The number of minutes that the customer's time zone is offset from GMT. When you create import records, you can optionally provide a `TimeZoneBias`. The `TimeZoneBias` parameter represents the way information about time zones is stored in the Windows registry. You can use the following formula to convert `TimeZoneBias` to `gmtOffset`:

```
if timeZoneBias is positive:
```

```

    gmtOffset = 1440 - timeZoneBias (where 1440 is the number of minutes in 24
hours)
else if timeZoneBias is negative:
    gmtOffset = -1 * timeZoneBias
else if timeZoneBias is 0
    gmtOffset = timeZoneBias

```

### Parameters for create:

- **fileContent:** Required. Comma-separated or pipe-separated list of data embedded within a CDATA section.
- **overwriteData:** True or false. If set to true, the existing import data in the database is overwritten by the new import data. If set to false, the new import data is appended to the existing data. Default is false.




---

**Note** You cannot modify or remove existing fields or append a new field to existing data.

---

- **delimiter:** Comma (,) or pipe (|). Default is comma (,).
- **header fields:** The following header fields are allowed:
  - **AccountNumber:** Can contain any characters, including internationalized characters, except the delimiter specified in the input XML. Maximum length of 30 bytes.
  - **FirstName:** Can contain any characters, including internationalized characters, except the delimiter specified in the input XML. Maximum length of 50 characters.
  - **LastName:** Can contain any characters, including internationalized characters, except the delimiter specified in the input XML. Maximum length of 50 characters.
  - **Phone01 through Phone10:** Can contain digits 0-9, pound sign (#), and asterisk (\*). Maximum length of 20 bytes. At least one Phone field is required.
  - **TimeZoneBias:** Specifies the offset of the customer's time zone from UTC in minutes. Integer. Range is from -780 to 720 (-13 to 12 hours from UTC).
  - **DstObserved:** Specifies whether DST is observed for the customer's location. True or false. Default is false.



**Note** If the TimeZoneBias parameter is provided but the DstObserved parameter is not, DstObserved is set to false. If the DstObserved parameter is provided but not TimeZoneBias, a validation error is returned.

If TimeZoneBias is not provided, time zone and Daylight Saving Time information is assigned by matching phone numbers to region prefix strings. If a phone number for a contact does not match a configured region prefix, the default time zone for the campaign is used.

If a customer record contains multiple phone numbers, the value for TimeZoneBias and DstObserved are applied to all of that customer's phone numbers.

You can use the Time Zone API to look up the values for TimeZoneBias and DstObserved for the target time zone. For more information, see [Time Zone API, on page 110](#).

### Search and Sort

The following table shows the parameters that are searched and the parameters that are sortable.

Search parameters	Sort parameters
<ul style="list-style-type: none"> <li>• accountNumber</li> <li>• firstName</li> <li>• lastName</li> </ul>	<ul style="list-style-type: none"> <li>• accountNumber (default)</li> <li>• firstName</li> <li>• lastName</li> </ul>

See [Search, on page 10](#) and [Sort, on page 11](#).

### Example Get Response

```
<importContact>
  <refURL>/unifiedconfig/config/campaign/5000/import/1</refURL>
  <accountNumber>4019</accountNumber>
  <callsMade>1</callsMade>
  <callStatus>pending</callStatus>
  <callResultOverall>0</callResultOverall>
  <firstName>Mir</firstName>
  <lastName>Ali</lastName>
  <importDate>2016-03-28T01:09:40</importDate>
  <phone01>
    <callResult>0</callResult>
    <dstObserved>true</dstObserved>
    <gmtOffset>720</gmtOffset>
    <number>9789360001</number>
  </phone01>
  <phone02>
    <callResult>0</callResult>
    <dstObserved>true</dstObserved>
    <gmtOffset>720</gmtOffset>
    <number>9789360002</number>
  </phone02>
```

```

<phone03>...</phone03>
<phone04>...</phone04>
<phone05>...</phone05>
<phone06>...</phone06>
<phone07>...</phone07>
<phone08>...</phone08>
<phone09>...</phone09>
<phone10>
  <callResult>0</callResult>
  <dstObserved>true</dstObserved>
  <gmtOffset>330</gmtOffset>
  <number>9789360010</number>
</phone10>
</importContact>

```

### Example Create Request

```

<import>
  <fileContent>
    <![CDATA[
      AccountNumber,FirstName,LastName,Phone01,Phone02,TimeZoneBias,DstObserved
      6782, Henry, Martin, 2225554444, 2225556262, 720, false
      3456, Michele, Smith, 2225559999, 2225551234, 540, true
      4569, Walker, Evans, 2225552000, 2225557890, -600, true
    ]]>
  </fileContent>
  <delimiter>,</delimiter>
</import>

```

## Personal Callback API

Use the Personal Callback API to configure your Outbound Option campaign to handle personal callbacks. The Personal Callback feature allows an agent to schedule a callback to a customer for a specific date and time.

### URL

`https://<server>/unifiedconfig/config/personalcallback`

### Operations

- **create**: Creates a single PersonalCallback record and stores it in the BA database.
- **create** (bulk): Creates PersonalCallback records in bulk and stores them in the BA database using the URL `https://<server>/unifiedconfig/config/personalcallback/import`.
- **delete**: Deletes one or more PersonalCallback records from the PersonalCallback list using the URL `https://<server>/unifiedconfig/config/personalcallback/<id>`.
- **get** (template): Retrieves a sample CSV template for contacts, which is provided by the API, using the URL `https://<server>/unifiedconfig/config/personalcallback/template`.
- **get** (record): Retrieves one PersonalCallback record from the database using the URL `https://<server>/unifiedconfig/config/personalcallback/<id>`.
- **list**: Retrieves a list of PersonalCallback records from the database.

- **Query parameters:**

- agentId
- accountNumber
- firstName
- lastName

- **update:** Updates one PersonalCallback record in the database using the URL `https://<server>/unifiedconfig/config/personalcallback/<id>`.

## Parameters

### Parameters for create (single record), get, and update operations:

- **campaign:** A reference to a specific campaign, including the refURL and campaign ID.
- **agent:** A reference to a specific agent, including the refURL and agent ID.
- **campaignId:** Read only. The ID for the campaign.
- **peripheralId:** Read only. ID for the peripheral on which the agent would be available.
- **agentId:** Read only. ID of the agent to whom to connect the call.
- **campaignDn:** The Dialed Number (DN) to use if the original agent is not available.
- **phone:** Required. The phone number to call back. Can contain digits 0 to 9, pound sign (3), and asterisk (\*). Maximum length of 20 bytes.
- **accountNumber:** The customer's account number. Internationalized characters are allowed. Maximum length of 30 bytes.
- **maxAttempts:** Required. The maximum number of times to attempt a call (decrements at each attempt). An attempt is the Dialer's attempt to reserve the agent and call the customer. Because the Dialer places multiple customer call attempts (such as busy, no answer), individual call attempts are not tracked here; only the result at the end of the callback time range. After this parameter is set to 0, no more attempts are made. Must be a positive integer value.
- **callbackDateTime:** Required. The time to attempt the customer callback is normalized to the logger GMT zone. For example, the Campaign Manager is in Boston and the customer is in California. The customer wants to be called back at 3 p.m. The time in this column is 6 p.m. The format for this parameter is yyyy-MM-ddTHH:mm:ss (for example, 2016-03-13T04:50:31).

The following rules apply to the callbackDateTime parameter:

- The callbackDateTime that is used is local to the time zone of the Logger. You need to consider this if the client machine on which you are using this API is in a different time zone than the Logger machine.
- The setting of the callbackDateTime by this API reads the CallbackDateTimeLimit in the registry. For more information, see the Registry Settings section of the *Outbound Option Guide for Unified Contact Center Enterprise* at <https://www.cisco.com/c/en/us/support/customer-collaboration/unified-contact-center-enterprise/products-user-guide-list.html>.



- The Campaign Manager uses the `CallbackDateTimeLimit` registry value to select Personal Callback records to queue to the Dialer.
  - The default `CallbackDateTimeLimit` in the registry is 15 minutes. For create and update operations, you cannot set the `callbackDateTime` to 15 minutes or more before the current time. For example, if it is currently 4:00, you cannot set the `callbackDateTime` to 3:30.
  - For update operations, the new `callbackDateTime` value can only be set if the current `callbackDateTime` is 15 minutes or more after the current Logger time. For example, if the current Logger time is 4:00 and the current `callbackDateTime` is 4:30, the new `callbackDateTime` can be set to 4:10. However, if the current `callbackDateTime` is 4:10, it cannot be set to 4:00.
- `callStatus`: The status of the personal callback. Possible values include the following:
- active (A)
  - callbackRequested (B)
  - closed (C)
  - dialed (D)
  - agentRejected (J)
  - maxAttemptsReached (M)
  - pending (P)
  - retry (R)
  - personalCallbackRequested (S)
  - unknown (U)
  - agentNotAvailable (X)

For more information about these values, see the `CallStatusZone` Values section of the *Outbound Option Guide for Unified Contact Center Enterprise* at <https://www.cisco.com/c/en/us/support/customer-collaboration/unified-contact-center-enterprise/products-user-guide-list.html>.

- `callResult`: Read only. Corresponds to the `CallResult` value in the `Dialer_Detail` table.  
For more information about possible `callResult` values, see the `CallResult` Codes and Values section of the *Outbound Option Guide for Unified Contact Center Enterprise* at <https://www.cisco.com/c/en/us/support/customer-collaboration/unified-contact-center-enterprise/products-user-guide-list.html>.
- `lastName`: The customer's last name. Internationalized characters are allowed. Maximum length of 50 characters.
- `firstName`: The customer's first name. Internationalized characters are allowed. Maximum length of 50 characters.

**Bulk parameters:**

- `fileContent`: Comma-separated or pipe-separated list of data embedded within a CDATA section.
- `overwriteData`: True or false. If set to true, the existing personal callback data in the database is overwritten by the new personal callback data. If set to false, the new personal callback data is appended to the existing data. Default is false.




---

**Note** You cannot modify or remove existing fields or append a new field to existing data.

If overwriteData is set to true, any agent scheduled personal callback records are also overwritten.

---




---

**Note** Avoid performing a bulk job transaction during a maintenance window.

---

- delimiter: Comma (,) or pipe (|). Default is comma (,).

### Bulk fileContent parameters:




---

**Note** The descriptions for these parameters are the same as the descriptions for the parameters for create (single record), get, and update operations. Only the case is different.

---

- CampaignId (must be a valid campaign ID in the database)
- AgentSkillTargetId (must be a valid SkillTargetID in the database)
- CampaignDn
- Phone
- AccountNumber
- MaxAttempts
- CallbackDateTime
- LastName
- FirstName

### Search and Sort Values

The following table shows the parameters that are searched and the parameters that are sortable.

Search parameters	Sort parameters
<ul style="list-style-type: none"> <li>• agentId</li> <li>• accountNumber</li> <li>• firstName</li> <li>• lastName</li> </ul>	<ul style="list-style-type: none"> <li>• agentId</li> <li>• accountNumber</li> <li>• firstName</li> <li>• lastName</li> </ul>

See [Search](#), on page 10 and [Sort](#), on page 11.

### Advanced search parameters

There are several advanced searches you can perform on the Personal Callback API, including agentId, accountNumber, firstName, and lastName. All search terms are case-insensitive.

- **agentId:<ID>** finds all personal callback records where the agent ID contains a specified ID. For example, **agentId:123** returns all records where the agent ID contains the string "123".
- **lastName:<name>** finds all personal callback records where the last name contains the specified name. For example, **lastName:smith** returns all records where the last name includes "smith".
- **firstName:<name>** finds all personal callback records where the firstName contains the specified name. For example, **firstName:John** returns all records where the first name includes "john".
- **accountNumber:<number>** finds all personal callback records where the accountNumber contains the specified number. For example, **accountNumber:456** returns all records where the account number includes "456".

### Example Create Request (Single Record)

```
<personalCallback>
  <campaign>
    <refURL>/unifiedconfig/config/campaign/5000</refURL>
  </campaign>
  <agent>
    <refURL>/unifiedconfig/config/agent/5050</refURL>
  </agent>
  <campaignDn>222222</campaignDn>
  <phone>999333</phone>
  <accountNumber>23334343334</accountNumber>
  <maxAttempts>1</maxAttempts>
  <callbackDateTime>2016-01-15T11:37:00</callbackDateTime>
  <callStatus>pending</callStatus>
  <lastName>Kumar</lastName>
  <firstName>Akshaya</firstName>
</personalCallback>
```

### Example Create Request (Bulk)

```
<personalCallback>
  <fileContent>
    <![CDATA[
      AccountNumber,FirstName,LastName,Phone,AgentSkillTargetId,CampaignId,CampaignDn,
      CallbackDateTime,MaxAttempts
      6782,Henry,Martin,2225554444,1004,5000,2222222221,2016-01-25T05:12:00,1
      3444,Thomas,Edison,2225554555,1004,5000,2222222222,2016-01-25T05:23:00,1
      5444,Tom,Hilfiger,2225554666,1004,5000,2222222223,2016-01-25T05:37:00,1
    ]]>
  </fileContent>
</personalCallback>
```

### Example Get (Record) Response

```
<personalCallback>
  <changeStamp>48</changeStamp>
  <refURL>/unifiedconfig/config/campaign/personalcallback/2</refURL>
  <campaign>
    <refURL>/unifiedconfig/config/campaign/5000</refURL>
  </campaign>
  <agent>
```

```

    <refURL>/unifiedconfig/config/agent/5050</refURL>
  </agent>
  <campaignId>5000</campaignId>
  <peripheralId>5000</peripheralId>
  <agentId>1001</agentId>
  <campaignDn>222222</campaignDn>
  <phone>999333</phone>
  <accountNumber>23334343334</accountNumber>
  <maxAttempts>1</maxAttempts>
  <callbackDateTime>2016-01-15T11:37:00</callbackDateTime>
  <callStatus>pending</callStatus>
  <callResult>0</callResult>
  <lastName>Kumar</lastName>
  <firstName>Akshaya</firstName>
</personalCallback>

```

## Time Zone API

Use the Time Zone API to list all available time zones and to get time zone information for a specified zone. Time zone information is stored in the registry of the Windows operating system.



**Important** Microsoft periodically releases cumulative time zone updates. These updates include worldwide changes to time zone names, bias (the amount of time in minutes that a time zone is offset from Coordinated Universal Time (UTC)), and observance of daylight saving time. These patches update the information in the Windows registry. When these updates are available, apply them to all virtual machines in the deployment that are running a Microsoft Windows operating system.

Use this API with the Outbound Campaign API to set the default time zone for an Outbound Option campaign. An Outbound Option campaign uses the time zone when the location of the customer number being dialed is unknown.

This API is read-only.

### URL

`https://<server>/unifiedconfig/config/timezone`

### Operations

- **list**: Retrieves a list of available time zones. The list is sorted by UTC offset from the International Date Line from west to east.
- **get**: Returns information for a specific time zone using the URL `https://<server>/unifiedconfig/config/timezone/<id>`, where `<id>` is the URL-encoded version of the name parameter.

### Response Parameters

- **name**: The name of the time zone.
- **displayName**: Specific bias and location information about the time zone, such as the offset from UTC and one or more places located within the time zone.

Example: “(UTC+5:30) Chennai, Kolkata, Mumbai, New Delhi”

- **stdName:** The time zone name during standard time.

Example: Malay Peninsula Standard Time

- **dstName:** The time zone name during daylight saving time.

Example: Malay Peninsula Daylight Time

- **dstObserved:** Indicates whether daylight saving time is observed for the time zone. True or false.
- **bias:** The current bias for local time translation on the server (in minutes). That is, the number of minutes to add to the local time to yield UTC.

### Example Get Response

```
<timeZone>
  <refURL>
    /unifiedconfig/config/timezone/Pacific%20Standard%20Time%20%28Mexico%29
  </refURL>
  <name>Pacific Standard Time (Mexico)</name>
  <displayName>(UTC-08:00) Baja California</displayName>
  <stdName>Pacific Standard Time (Mexico)</stdName>
  <dstName>Pacific Daylight Time (Mexico)</dstName>
  <dstObserved>true</dstObserved>
  <bias>480</bias>
</timeZone>
```





## CHAPTER 24

# Precision Queue API

---

- [Precision Queue API, on page 113](#)

## Precision Queue API

Precision queues help direct incoming callers to appropriate agents, as they match specific agent attributes with caller requirements. If a precision queue requires an agent who lives in Boston and who speaks fluent Spanish, then an agent with the attributes **Boston = True** and **Spanish = True** is a good match.

Use the Precision Queue API to list the precision queues currently defined in the database, define new precision queues, and view, edit, and delete existing precision queues.

### URL

`https://<server>/unifiedconfig/config/precisionqueue`

### Operations

- **create**: Creates one precision queue.
- **delete**: Marks one precision queue for deletion, but does not permanently delete it. Deleting a precision queue that is referenced dynamically in a script is allowed. No new calls are queued against it, but the precision queue remains operational until calls are no longer in the queue.
- **get**: Returns one precision queue, using the URL  
`https://<server>/unifiedconfig/config/precisionqueue/<id>`.

- **Query parameters:**

- **agentcount**: Use this query parameter to have the agent count parameter included in the response; for example, `agentcount=true`.
- **attributes**: Use this query parameter to have the attribute parameter included in the response; for example, `attributes=true`.
- **skillgroups**: Use this query parameter to augment the returned precision queue attributes with an id listing of all skillgroups that are associated with the precision queue; for example, `skillgroups=true`.

- **list**: Retrieves a list of precision queues. Query parameters described above for the get operation are also allowed for list.
- **update**: Updates one precision queue.

## Parameters

### Precision queue parameters:

- **refURL**: The refURL of the precision queue. See [Shared Parameters, on page 8](#).
- **name**: The name of the precision queue. See [Shared Parameters, on page 8](#).
- **changeStamp**: See [Shared Parameters, on page 8](#).
- **description**: See [Shared Parameters, on page 8](#).
- **mediaRoutingDomain**: A reference to the media routing domain ([Media Routing Domain API, on page 81](#)) including the name and refURL. See [References, on page 5](#).
  - Defaults to Cisco\_Voice MRD if this parameter is not provided.
  - This reference cannot be updated.
- **bucketInterval**: A reference to a bucket interval ([Bucket Interval API, on page 31](#)), including the refURL and name. See [References, on page 5](#).
- **agentCount**: Returns agent count for the precision queue. Returned only when using the agentcount query parameter.
- **agentOrdering**: Determines the order in which agents receive calls from this queue.
  - 1: LAA (Agent availability time)
  - 2: Most skilled agent
  - 3: Least skilled agent
- **callOrdering**: Determines the order of calls in this precision queue.
  - 1: Top priority in queue. This is the default value.
- **id**: The database id of the precision queue. Read-only field. Used in scripting.
- **attributes**: A collection of attribute names (attribute1, attribute2, and so on) indicating all attributes used in this precision queue. Returned only when the query parameter attributes=true.
- **serviceLevelThreshold**: Maximum time in seconds that a caller should wait before being connected with an agent.
- **serviceLevelType**: This value indicates how the system calculates the service level.
  - 1: Ignore abandoned calls.
  - 2: Abandoned call has negative impact.
  - 3: Abandoned call has positive impact.



- **skillgroups:** A collection of skill groups associated with this precision queue, including the id of each skill group. Returned only when the query parameter `skillgroups=true`.
- **steps:** Required. A collection of steps for this precision queue. You can have 1-10 steps. Returned only for get operation. See the Step parameters below.

**Step parameters:**

- **waitTime:** Time in seconds to wait before proceeding to the next step.
- **considerIf:** A Consider If expression which must be met to execute a particular step. Items used in the expression are case sensitive. You cannot add an expression to the last step.
- **terms:** Required. A collection of terms for this step. Each step can have 1-10 terms. See the Term parameters below.

**Term parameters:**

- **attribute:** A reference to the attribute ([Attribute API, on page 27](#)), including the refURL, name, description, and dataType. Multiple unique attributes can be used across all terms in a precision queue.
- **parenCount:** Denotes a parenthesis before or after this term. A value of 1 means a parenthesis before the current term, and a value of -1 means a parenthesis after the current term. The sum of all parenCount for all terms in a step must be equal to zero, meaning that all parenthesis in the expression are matched. For example, a step to check for agents that have `(sales > 7 or expertSales = true) and english = true` requires 3 terms with the parenCount set to 1 on the first term, -1 on the second term, and 0 on the last term.
- **termRelation:** Indicates the relationship of this term to the preceding term, using the following values:
  - 0: None. Valid only on the first term in a step.
  - 1: AND
  - 2: OR
- **attributeRelation:** Indicates what kind of comparison is done on the attribute, using the following values:
  - 1: Equal
  - 2: Not equal
  - 3: Less than
  - 4: Less than or equal
  - 5: Greater than
  - 6: Greater than or equal
- **value1:** The value that the attribute is tested against. For boolean attributes, this value must be true/false. For proficiency attributes, this value must be 1-10.

**Search and Sort Values**

The following table shows the parameters that are searched and the parameters that are sortable.

Search parameters	Sort parameters
<ul style="list-style-type: none"> <li>• name</li> <li>• description</li> </ul>	<ul style="list-style-type: none"> <li>• name (default)</li> <li>• description</li> </ul>

See [Search, on page 10](#) and [Sort, on page 11](#).

### Example Get Response

```
<precisionQueue>
  <refURL>/unifiedconfig/config/precisionqueue/5002</refURL>
  <changeStamp>4</changeStamp>
  <agentOrdering>1</agentOrdering>
  <callOrdering>1</callOrdering>
  <bucketInterval>
    <refURL>/unifiedconfig/config/bucketinterval/1</refURL>
    <name>Default_Bucket_Intervals</name>
  </bucketInterval>
  <mediaRoutingDomain>
    <name>Cisco_Voice</name>
    <refURL>/unifiedconfig/config/mediaroutingdomain/1</refURL>
  </mediaRoutingDomain>
  <description>This is a practice precision queue</description>
  <name>Practice_Queue</name>
  <serviceLevelThreshold>3</serviceLevelThreshold>
  <serviceLevelType>1</serviceLevelType>
  <steps>
    <step>
      <terms>
        <term>
          <attribute>
            <refURL>/unifiedconfig/config/attribute/5698</refURL>
            <name>test</name>
            <dataType>4</dataType>
          </attribute>
          <attributeRelation>5</attributeRelation>
          <parenCount>0</parenCount>
          <termRelation>0</termRelation>
          <value1>2</value1>
        </term>
      </terms>
      <waitTime>0</waitTime>
    </step>
  </steps>
</precisionQueue>
```



## CHAPTER 25

# Scan API

---

- [Scan API, on page 117](#)

## Scan API

The Scan API forces the validation of the Customer Collaboration Platform external machine status rules.

### URL

```
https://<server>/unifiedconfig/config/status/scan
```

### HTTP method

PUT: Invoke the PUT method to force a scan to start immediately.





## CHAPTER 26

# Single Sign-On Global State API

---

- [Single Sign-On Global State API, on page 119](#)

## Single Sign-On Global State API

Use the Single Sign-On (SSO) Global State API to view or update the global status of SSO.

To retrieve the overall status of setting the SSO state or the status for a single component, see the [Single Sign-On Status API, on page 123](#).

### URL

`https://<server>/unifiedconfig/config/sso/globalstate`

### Operations

- **get**: Returns the current global state of SSO in the database.
- **update**: Updates the global state of SSO in the database.

### Parameters

- **refURL**: The RefURL. See [Shared Parameters, on page 8](#).
- **changeStamp**: See [Shared Parameters, on page 8](#).
- **permissionInfo**: Information about permissions.
  - **canUpdate**: Whether ssoState can be updated. True or false.
  - **role**: The role of the user.
- **state**: Required for update. Valid values are NON\_SSO (SSO is disabled for all users), SSO (SSO is enabled for all users), and HYBRID (mix of enabled and disabled).

### Example Get Response

```
<ssoState>  
  <refURL>/ssostate</refURL>
```

```
<changeStamp>227</changeStamp>
<permissionInfo>
  <canUpdate>true</canUpdate>
  <role>Administrator</role>
</permissionInfo>
<state>SSO</state>
</ssoState>
```



## CHAPTER 27

# Single Sign-On Registration API

---

- [Single Sign-On Registration API, on page 121](#)

## Single Sign-On Registration API

Use the Single Sign-On (SSO) Registration API to register SSO-compatible components with the Cisco Identity Service. These components include AW, Finesse, and Unified Intelligence Center machines.

To retrieve the overall registration status or the status for a single component, see the [Single Sign-On Status API, on page 123](#).

### URL

```
https://<server>/unifiedconfig/config/sso/register
```

### Operations

- **update:** Registers all SSO-compatible components in the Machine Inventory with the Cisco Identity Service, using the URL `https://<server>/unifiedconfig/config/sso/register`. (See [Machine Inventory API, on page 73](#))

### Parameters

None







## CHAPTER 28

# Single Sign-On Status API

- [Single Sign-On Status API, on page 123](#)

## Single Sign-On Status API

Use the Single Sign-On (SSO) Registration API to get the current status of registering components with the Cisco Identity Service (IdS) and setting SSO state on the SSO-compatible components. These components include AW, Finesse, and Unified Intelligence Center machines.

### URL

```
https://<server>/unifiedconfig/config/sso/status
```

### Operations

- **get** component status: Returns the status of registering a specific component with the Cisco IdS and setting SSO state, using the URL `https://<server>/unifiedconfig/config/sso/status/<id>`. The `<id>` is the `machine_id` of the component.
- **list**: Retrieves a list with the overall and individual component statuses of registering SSO-compatible components with the Cisco Identity Service and setting SSO state, using the URL `https://<server>/unifiedconfig/config/sso/status`.

### Parameters

- `globalSsoState`: The current SSO state as set in the AW database. The values are `NON_SSO` (SSO is disabled for all users), `SSO` (SSO is enabled for all users), and `HYBRID` (mix of enabled and disabled).
- `registrationState`: The overall status of registering components with the Cisco IdS. Values are the following:
  - `SUCCEEDED`: All of the components were successfully registered.
  - `FAILED`: Registration failed on one or more components. Error detail is set on each failed component.
  - `PROCESSING`: Registration started and is not complete.
  - `NOT_STARTED`: Registration has not started.
- `modeState`: The overall status of registering components with the Cisco IdS. Values are the following:

- SUCCEEDED: The SSO state was successfully set on all of the components.
  - FAILED: The SSO state failed to be set on one or more components. Error detail is set on each failed component.
  - PROCESSING: The SSO state change has started and is not complete.
  - NOT\_STARTED: The SSO state change has not started.
- idSConfigurationState: Whether the Cisco IdS has been configured and is in service.
    - STATE\_NOT\_CONFIGURED : The Cisco IdS is not been configured.
    - STATE\_IN\_SERVICE : The Cisco IdS is configured and is in service.
    - STATE\_OUT\_OF\_SERVICE : The Cisco IdS is configured and is out of service.
    - STATE\_PARTIAL\_SERVICE: The Cisco IdS is configured and is partially in service.
    - STATE\_UNREACHABLE: The Cisco IdS cannot be reached.
- hasIdsCredentials: Whether the Machine Inventory has the necessary IdS credentials to register components (see [Machine Inventory API, on page 73](#). Values are true or false. The default is false.
  - idsBaseUrl: The base URL for accessing the Identity Service.
  - ssoComponentStatuses: A collection of registration and SSO state status information for all of the individual components. Returned on a list operation.
  - ssoComponentStatus: Registration and SSO state status information for an individual component. Includes the following parameters:
    - registrationState: The status of registering the component with the IdS. See the values for this parameter above.
    - modeState: The status of setting the SSO state for the component. See the values for this parameter above.
    - refURL: The refURL for the component machine. See [Shared Parameters, on page 8](#).
    - name: The name of the component machine.

### Example Get Response

Example URL: `https://<server>/unifiedconfig/config/sso/status/21`

```
<ssoComponentStatus>
  <registrationState>FAILED</registrationState>
  <modeState>NOT_STARTED</modeState>
  <refURL>/unifiedconfig/config/machineinventory/21</refURL>
  <name>FINESSE-A.boston.com</name>
</ssoComponentStatus>
```

### Example List Response

```
<ssoStatus>
  <globalSsoState>HYBRID</globalSsoState>
  <registrationState>FAILED</registrationState>
```

```
<modeState>NOT_STARTED</modeState>
<idSConfigurationState>STATE_IN_SERVICE</idSConfigurationState>
<hasIdsCredentials>true</hasIdsCredentials>
<idsBaseUrl>https://<server>:<serverport></idsBaseUrl>
<ssoComponentStatuses>
  <ssoComponentStatus>
    <registrationState>FAILED</registrationState>
    <modeState>NOT_STARTED</modeState>
    <refURL>/unifiedconfig/config/machineinventory/21</refURL>
    <name>FINESSE-A.boston.com</name>
  </ssoComponentStatus>
  <ssoComponentStatus>
    <registrationState>FAILED</registrationState>
    <modeState>NOT_STARTED</modeState>
    <refURL>/unifiedconfig/config/machineinventory/22</refURL>
    <name>FINESSE-B.boston.com</name>
  </ssoComponentStatus>
  <ssoComponentStatus>
    <registrationState>FAILED</registrationState>
    <modeState>NOT_STARTED</modeState>
    <refURL>/unifiedconfig/config/machineinventory/23</refURL>
    <name>CUIC-A.boston.com</name>
  </ssoComponentStatus>
</ssoComponentStatuses>
</ssoStatus>
```





## CHAPTER 29

# Skill Group API

---

- [Skill Group API, on page 127](#)

## Skill Group API

A skill group is a collection of agents who share a common set of competencies that equip them to handle the same types of requests. Some examples of skill groups are a collection of agents who speak a specific language or who can assist callers with billing questions.

Use the Skill Group API to list, view, or edit existing skill groups.



---

**Note** Access to this API is different for supervisors and administrators. For more information, see [Access, on page 3](#).

---

### URL

```
https://<server>/unifiedconfig/config/skillgroup
```



---

**Note** `unifiedconfig api` does not support skill groups in System PGs

---

### Operations

- **get:** Returns one skill group, using the URL `https://<server>/unifiedconfig/config/skillgroup/<id>`.
- **list:** Retrieves a list of skill groups.
  - **Query Parameters:**
    - **selectedAgentCount:** Use this query parameter to augment skill group information about multiple agents. The `selectedAgentCount` parameter shows the number of specified agents belonging to that skill group. For example, to find out how many of agents 5000, 5001, 5002, and 5003 belong to each of the skill groups in the list, add **`selectedAgentCount=5000,5001,5002,5003`**.



---

**Note** Using `selectedAgentCount` automatically sets the summary list query parameter to **true**.

---

- Summary list: See [list](#), on page 2.

- `update`: Updates one skill group.

## Parameters

- `refURL`: The refURL of the skill group. See [Shared Parameters](#), on page 8.
- `name`: The name of the skill group. See [Shared Parameters](#), on page 8.
- `changeStamp`: See [Shared Parameters](#), on page 8.
- `description`: See [Shared Parameters](#), on page 8.
- `peripheral`: Contains the name and id of the peripheral.
- `mediaRoutingDomain`: A reference to the media routing domain ([Media Routing Domain API](#), on page 81) including the name and refURL. See [References](#), on page 5.
  - Defaults to `Cisco_Voice` MRD if this parameter is not provided.
  - This reference cannot be updated.
- `agents`: A collection of agents assigned to the skill group (See [Agent Call API](#)). References also include `firstName`, `lastName`, `agentId`, and `agentTeam` (which includes the team name and refURL). See [References](#), on page 5.
  - `canRemove`: This parameter only appears for supervisors. It indicates whether or not the supervisor has permission to remove the agent from this skill group. The supervisor can remove the agent from the skill group if the agent belongs to a team of this supervisor.
- `agentsAdded`: A collection of agent references to be added to the skill group, including the refURL of each agent to be added. This parameter is update only, and cannot be used in conjunction with the `agents` parameter. This parameter can be used with the `agentsRemoved` parameter. See [References](#), on page 5.
- `agentsRemoved`: A collection of agent references to be removed from the skill group, including the refURL of each agent to be removed. This parameter is update only, and cannot be used in conjunction with the `agents` parameter. This parameter can be used with the `agentsAdded` parameter. See [References](#), on page 5.
- `agentCount`: Read-only parameter containing the number of agents having the skill.
- `selectedAgentCount`: Read-only field. Indicates the number of specified agents belonging to the skill group. Returned only when using the `selectedAgentCount` query parameter.
- `bucketInterval`: A reference to the bucket interval ([Bucket Interval API](#), on page 31). Includes the name and refURL. See [References](#), on page 5.
- `serviceLevelThreshold`: Maximum time in seconds that a caller should wait before being connected with an agent. Positive integers only, or blank.

- **serviceLevelType:** This value indicates how the system calculates the service level.
  - 1: Ignore Abandoned Calls (default).
  - 2: Abandoned Calls have Negative Impact.
  - 3: Abandoned Calls have Positive Impact.

### Search and Sort Values

The following table shows the parameters that are searched and the parameters that are sortable.

Search parameters	Sort parameters
<ul style="list-style-type: none"> <li>• name</li> <li>• description</li> </ul>	<ul style="list-style-type: none"> <li>• name (default)</li> <li>• description</li> <li>• serviceLevelThreshold</li> <li>• serviceLevelType</li> <li>• peripheralNumber</li> <li>• peripheral.name</li> </ul>

See [Search](#), on page 10 and [Sort](#), on page 11.

For more information on search restrictions, see [Search](#), on page 10.

### Advanced Search Parameters

- **peripherals: (peri1|peri2|peri3, ...)** which returns all SkillGroups that have any of the specified peripherals. Up to ten peripherals can be specified. The peripheral names are fully matched (case-insensitive, no partial matches).

### Example Get Response

```
<skillGroup>
  <refURL>/unifiedconfig/config/skillgroup/(id)</refURL>
  <name>test</name>
  <description>test skill group</description>
  <changeStamp>0</changeStamp>
  <peripheral>
    <id>5001</id>
    <name>CUCM_PG1</name>
  </peripheral>
  <mediaRoutingDomain>
    <name>Cisco_Voice</name>
    <refURL>/unifiedconfig/config/mediaroutingdomain/1</refURL>
  </mediaRoutingDomain>
  <bucketInterval>
    <name>bucketIntervalName</name>
    <refURL>/unifiedconfig/config/bucketinterval/1</refURL>
  </bucketInterval>
  <serviceLevelThreshold>20</serviceLevelThreshold>
  <serviceLevelType>1</serviceLevelType>
  <agents>
    <agent>
```

```
<refURL>/unifiedconfig/config/agent/5000</refURL>
<firstName>Jane</firstName>
<lastName>Doe</lastName>
<userName>username</userName>
<agentId>8007</agentId>
<canRemove>true</canRemove>
</agent>
<agent>
  <refURL>/unifiedconfig/config/agent/5001</refURL>
  <firstName>John</firstName>
  <lastName>Smith</lastName>
  <userName>username2</userName>
  <agentId>8008</agentId>
  <agentTeam>
    <refURL>/unifiedconfig/config/agentteam/5000</refURL>
    <name>someTeam</name>
  </agentTeam>
  <canRemove>>false</canRemove>
</agent>
<agent>...</agent>
<agent>...</agent>
</agents>
<agentCount>4</agentCount>
</skillGroup>
```





# CHAPTER 30

## Status API

---

The Status API retrieves information about the state of rules that collectively determine if the system is working correctly.

The system periodically checks the state of the rules. To force the status to be updated, refer to the [Scan API](#), on page 117.

### URL

```
https://<server>/unifiedconfig/config/status
```

### Operations

- **get**: Returns the status rule results, using the URL `https://<server>/unifiedconfig/config/status`.

### Response Parameters

- **name**: The name of the status. See the **Configuration Rules** and **Operation Rules**.
- **category**: The status category of Configuration or Operation.
- **level**: The severity of the condition. Values include: OK, ERROR, and BLOCKED. The BLOCKED level indicates that the rule has not been processed yet or that the failure of another rule prevents this rule from running.
- **machine**: A collection for the machine ([Machine Inventory API](#), on page 73) including the machine's name, type, and refURL. See [References](#), on page 5.

### Example Get Response

```
<results>
  <statuses>
    <status>
      <name>CUSTOMER_COLLABORATION_PLATFORM_MR_ENABLED</name>
      <category>CONFIGURATION</category>
      <level>BLOCKED</level>
      <machines>
        <machine>
          <refURL>/unifiedconfig/config/
            machineinventory/6110</refURL>
          <machineType>EXTERNAL_CUSTOMER_COLLABORATION_PLATFORM
```

```

        </machineType>
        <name>Machine_2563_00002</name>
    </machine>
</machines>
</status>
<status>
    <name>SERVER_CONNECTION</name>
    <category>OPERATION</category>
    <level>OK</level>
    <machines>
        <machine>
            <refURL>/unifiedconfig/config/
            machineinventory/6110</refURL>
            <machineType>EXTERNAL_CUSTOMER_COLLABORATION_PLATFORM
            </machineType>
            <name>Machine_2563_00002</name>
        </machine>
    </machines>
</status>
<status>
    <name>SERVER_CREDENTIALS</name>
    <category>OPERATION</category>
    <level>OK</level>
    <machines>
        <machine>
            <refURL>/unifiedconfig/config/
            machineinventory/6110</refURL>
            <machineType>EXTERNAL_CUSTOMER_COLLABORATION_PLATFORM
            </machineType>
            <name>Machine_2563_00002</name>
        </machine>
    </machines>
</status>
</statuses>
</results>

```

- [Configuration Rules, on page 132](#)
- [Operation Rules, on page 133](#)

## Configuration Rules

### Common Rules for All Machines

These rules show the potential configuration errors and warnings for all machines.

**Table 1: Common Rules**

Rule	Description
CAN_RESOLVE_ADDRESS_TO_FQDN	Machine address must be resolvable to a fully qualified domain name (FQDN).

### Unified CCE AW, Unified Intelligence Center, CUIC-LD-IdS, and Finesse Machines

These rules show the potential configuration errors and warnings for Unified CCE AW, Unified Intelligence Center, CUIC-LD-IdS, and Finesse machines.

**Table 2: Unified CCE AW, Unified Intelligence Center, CUIC-LD-IdS, and Finesse Rules**

Rule	Description
SSO_COMPONENT_STATUS_MATCHES_GLOBAL	The global SSO status must be the same as component SSO status.
SSO_VALID_IDS_REFERENCE	If single sign-on is enabled, this machine must be associated with a valid Cisco Identity Service.

**Table 3: Unified CCE AW Rules**

Rule	Description
TASK_ROUTING_APP_PATHS_EXIST	Each Peripheral Gateway with a Communications Manager PIM must have an associated Task Routing Application Path.

### Customer Collaboration Platform Machines

These rules show the potential configuration errors and warnings for Customer Collaboration Platform machines.

**Table 4: Customer Collaboration Platform Rules**

Rule	Description
SOCIAL_MINER_MR_ENABLED	Multichannel routing must be enabled on Customer Collaboration Platform.

### Cloud Connect Machines

These rules show the potential configuration errors and warnings for all of the machines, ESX hosts, and Gateways. Each section has a rule table that applies to all machines listed in that category, as well as a rule table for each type of machine in that category.

These rules show the potential configuration errors and warnings for Cloud Connect machines.

**Table 5: Cloud Connect Rules**

Rule	Description
CLOUD_CONNECT_STATUS	Shows the sync status of Cloud Connect Machine.

## Operation Rules

### Common Operation Rules

These rules show the potential operation errors and warnings for Unified CCE, Unified CM, Unified CVP, Gateways, Unified Intelligence Center, Finesse, and Enterprise Chat and Email. Each section has a rule table

that applies to all machines listed in that category, as well as a rule table for each type of machine in that category.

These rules show the potential operation errors and warnings for the following machines:

- All Unified CCE components
- Unified Intelligence Center
- CUIC-LD-IdS
- Finesse
- Live Data
- Identity Service
- Customer Collaboration Platform

**Table 6: Common Rules**

Rule	Description
SERVER_CONNECTION	<p>The Diagnostic Portal, AXL, REST, or SOAP service on this machine must be in service. The status you see varies according to the product type, as follows:</p> <ul style="list-style-type: none"> <li>• Unified CCE: The Cisco ICM Diagnostic Framework service on the Principal AW must be reachable on the network.</li> <li>• CUIC-LD-IdS: The SOAP service on the Publisher must be reachable on the network.</li> <li>• Finesse: The SOAP service on the Primary Finesse machine must be reachable on the network.</li> <li>• IdS: The REST service on the Primary Identity Server must be reachable on the network</li> <li>• Customer Collaboration Platform : The service must be reachable on the network.</li> </ul>

Rule	Description
SERVER_CREDENTIALS	<p>The inventory's credentials for the machine must be valid. The status you see varies according to the product type, as follows:</p> <ul style="list-style-type: none"> <li>• Unified CCE: The Diagnostic Framework credentials entered for the Principal AW must be valid for all CCE components in the solution.</li> <li>• CUIE-LD-IdS: The Unified Intelligence Center Administration credentials entered for the Publisher must be valid</li> <li>• Finesse: The Finesse Administration credentials entered for the Primary Finesse machine must be valid.</li> <li>• IdS: The Identity Service Administration credentials entered for the Primary Identity Server must be valid</li> <li>• Customer Collaboration Platform : The service credentials must be valid.</li> </ul> <p><b>Note</b> This rule does not apply to a standalone Live Data machine.</p>

### Cloud Connect Machines

These rules show the potential operational errors and warnings for Cloud Connector machines.

**Table 7: Cloud Connect Rules**

Rule	Description
CLOUD_CONNECTOR_TYPE	Cloud connect is either publisher or subscriber.
CONTACT_CENTER_AI_GLOBAL_CONFIG_NOT_FOUND	The Contact Center AI configuration that is associated as a Global configuration is not available in the Control Hub.

