

## X.509v3 Certificates for SSH Authentication

- X.509v3 Certificates for SSH Authentication, on page 1
- Information About X.509v3 Certificates for SSH Authentication, on page 2
- How to Configure X.509v3 Certificates for SSH Authentication, on page 2
- Configuration Examples for X.509v3 Certificates for SSH Authentication, on page 6
- Feature History for X.509v3 Certificates for SSH Authentication, on page 6

## X.509v3 Certificates for SSH Authentication

The X.509v3 Certificates for SSH Authentication feature uses the X.509v3 digital certificates in server and user authentication at the secure shell (SSH) server side.

This module describes how to configure server and user certificate profiles for a digital certificate.

### **Prerequisites for X.509v3 Certificates for SSH Authentication**

• The X.509v3 Certificates for SSH Authentication feature introduces the **ip ssh server algorithm authentication** command to replace the **ip ssh server authenticate user** command. If you use the **ip ssh server authenticate user** command, the following deprecation message is displayed.

Warning: SSH command accepted but this CLI will be deprecated soon. Please move to new CLI "ip ssh server algorithm authentication". Please configure "default ip ssh server authenticate user" to make CLI ineffective.

• Use the **default ip ssh server authenticate user** command to remove the **ip ssh server authenticate user** command from effect. The IOS secure shell (SSH) server then starts using the **ip ssh server algorithm authentication** command.

### Restrictions for X.509v3 Certificates for SSH Authentication

- The X.509v3 Certificates for SSH Authentication feature implementation is applicable only on the IOS secure shell (SSH) server side.
- IOS SSH server supports only the x509v3-ssh-rsa algorithm based certificate for server and user authentication on the IOS SSH server side.

## Information About X.509v3 Certificates for SSH Authentication

The following section provides information about digital certificates, and server and user authentication.

## **Digital Certificates**

The validity of the authentication depends upon the strength of the linkage between the public signing key and the identity of the signer. Digital certificates in the X.509v3 format (RFC5280) are used to provide identity management. A chain of signatures by a trusted root certification authority and its intermediate certificate authorities binds a given public signing key to a given digital identity.

Public key infrastructure (PKI) trustpoint helps manage the digital certificates. The association between the certificate and the trustpoint helps track the certificate. The trustpoint contains information about the certificate authority (CA), different identity parameters, and the digital certificate. Multiple trustpoints can be created to associate with different certificates.

## Server and User Authentication using X.509v3

For server authentication, the IOS secure shell (SSH) server sends its own certificate to the SSH client for verification. This server certificate is associated with the trustpoint configured in the server certificate profile (ssh-server-cert-profile-server configuration mode).

For user authentication, the SSH client sends the user's certificate to the IOS SSH server for verification. The SSH server validates the incoming user certificate using public key infrastructure (PKI) trustpoints configured in the server certificate profile (ssh-server-cert-profile-user configuration mode).

By default, certificate-based authentication is enabled for server and user at the IOS SSH server end.

## **How to Configure X.509v3 Certificates for SSH Authentication**

The following section provides information about how to configure X.509v3 Certificates for SSH Authentication.

## Configuring IOS SSH Server to Use Digital Certificates for Server Authentication

To configure IOS SSH server to use digital certificates for server authentication, perform this procedure:

#### **Procedure**

	Command or Action	Purpose
Step 1	enable	Enables privileged EXEC mode.
	Example:	Enter your password if prompted.
	Device> enable	
Step 2	configure terminal	Enters global configuration mode.
	Example:	

	Command or Action	Purpose	
	Device# configure terminal		
Step 3	ip ssh server algorithm hostkey {x509v3-ssh-rsa [ssh-rsa]   ssh-rsa [x509v3-ssh-rsa]}	configured algorithm is negotiated with the secure shell (SSH) client.	
	Example:		
	Device(config) # ip ssh server algorithm hostkey x509v3-ssh-rsa	Note The IOS SSH server must have at least one configured host key algorithm:	
		• ssh-rsa – public key based authentication	
		• x509v3-ssh-rsa – certificate-based authentication	
Step 4	ip ssh server certificate profile	Configures server certificate profile and user certificate	
	Example:	profile and enters SSH certificate profile configuration	
	Device (config) # ip ssh server certificate profile	mode.	
Step 5	server	Configures server certificate profile and enters SSH server certificate profile server configuration mode.	
	Example:	certificate profile server configuration mode.	
	Device(ssh-server-cert-profile)# server		
Step 6	trustpoint sign PKI-trustpoint-name	Attaches the public key infrastructure (PKI) trustpoint to	
	Example:	the server certificate profile. The SSH server uses the certificate associated with this PKI trustpoint for serve authentication.	
	Device(ssh-server-cert-profile-server)# trustpoint		
	sign trust1	authentication.	
Step 7	ocsp-response include	(Optional) Sends the Online Certificate Status Protoco	
	Example:	(OCSP) response or OCSP stapling along with the server	
	Device(ssh-server-cert-profile-server)#	certificate.	
	ocsp-response include	Note By default the "no" form of this command is configured and no OCSP response is sent along with the server certificate.	
Step 8	end	Exits SSH server certificate profile server configuration	
	Example:	mode and enters privileged EXEC mode.	
	Device(ssh-server-cert-profile-server)# end		

# **Configuring IOS SSH Server to Verify User's Digital Certificate for User Authentication**

To configure IOS SSH Server to use digital certificates for user authentication, perform this procedure:

#### **Procedure**

	Command or Action	Purpose	
Step 1	enable	Enables p	privileged EXEC mode.
	Example:	Enter your password if prompted.	
	Device> enable		
Step 2	configure terminal	Enters glo	obal configuration mode.
	Example:		
	Device# configure terminal		
Step 3	ip ssh server algorithm authentication {publickey   keyboard   password}	Defines the order of user authentication algorithms. Only the configured algorithm is negotiated with the secure shel (SSH) client.	
	Example:		
	Device(config)# ip ssh server algorithm authentication publickey	Note	The IOS SSH server must have at least one configured user authentication algorithm.
		Note	To use the certificate method for user authentication, the <b>publickey</b> keyword must be configured.
		Note	The ip ssh server algorithm authentication command replaces the ip ssh server authenticate user command.
Step 4	ip ssh server algorithm publickey {x509v3-ssh-rsa [ssh-rsa]   ssh-rsa [x509v3-ssh-rsa]}	configure	he order of public key algorithms. Only the dalgorithm is accepted by the SSH client for use
	Example:	authentica	ation.
	Device(config)# ip ssh server algorithm publickey x509v3-ssh-rsa	Note	The IOS SSH client must have at least one configured public key algorithm:
			• ssh-rsa – public-key-based authentication
			• x509v3-ssh-rsa – certificate-based authentication
Step 5	ip ssh server certificate profile	Configures server certificate profile and user certificate profile and enters SSH certificate profile configuration	
	Example:		
	Device(config)# ip ssh server certificate profile	mode.	
Step 6	user		es user certificate profile and enters SSH server
	Example:	certificate	e profile user configuration mode.
	Device(ssh-server-cert-profile)# user		
Step 7	trustpoint verify PKI-trustpoint-name	Configure	es the public key infrastructure (PKI) trustpoint
	Example:	that is use	ed to verify the incoming user certificate.

	Command or Action	Purpose
	Device(ssh-server-cert-profile-user)# trustpoint verify trust2	Note Configure multiple trustpoints by executing the same command multiple times. A maximum of 10 trustpoints can be configured.
Step 8	ocsp-response required  Example:	(Optional) Mandates the presence of the Online Certificate Status Protocol (OCSP) response with the incoming user certificate.
	Device(ssh-server-cert-profile-user)# ocsp-response required	Note By default the "no" form of this command is configured and the user certificate is accepted without an OCSP response.
Step 9	<pre>end Example: Devicessh-server-cert-profile-user)# end</pre>	Exits SSH server certificate profile user configuration mode and enters privileged EXEC mode.

# **Verifying Configuration for Server and User Authentication Using Digital Certificates**

To verify configuration for server and user Authentication using digital certificates, perform this procedure:

#### **Procedure**

	Command or Action	Purpose	
Step 1	enable	Enables privileged EXEC mode.	
	Example:	Enter your password if prompted.	
	Device> enable		
Step 2	show ip ssh	Displays the currently configured authentication method	
	Example:	To confirm the use of certificate-based authentication, ensure that the x509v3-ssh-rsa algorithm is the configured	
	Device# show ip ssh	host key algorithm.	
	SSH Enabled - version 1.99 Authentication methods:publickey, keyboard-interactive, password Authentication Publickey Algorithms:x509v3-ssh-rsa, ssh-rsa Hostkey Algorithms:x509v3-ssh-rsa, ssh-rsa Authentication timeout: 120 secs; Authentication retries: 3 Minimum expected Diffie Hellman key size: 1024 bits		

# Configuration Examples for X.509v3 Certificates for SSH Authentication

The following section provides examples for user and server authentication using digital certificates.

## **Example: Configuring IOS SSH Server to Use Digital Certificates for Server Authentication**

This example shows how to configure IOS SSH Server to Use Digital Certificates for Server Authentication.

```
Device> enable
Device# configure terminal
Device(config)# ip ssh server algorithm hostkey x509v3-ssh-rsa
Device(config)# ip ssh server certificate profile
Device(ssh-server-cert-profile)# server
Device(ssh-server-cert-profile-server)# trustpoint sign trust1
Device(ssh-server-cert-profile-server)# exit
```

## **Example: Configuring IOS SSH Server to Verify User's Digital Certificate for User Authentication**

This example shows how to configure IOS SSH server to verify user's digital certificate for user authentication.

```
Device> enable

Device# configure terminal

Device(config)# ip ssh server algorithm authentication publickey

Device(config)# ip ssh server algorithm publickey x509v3-ssh-rsa

Device(config)# ip ssh server certificate profile

Device(ssh-server-cert-profile)# user

Device(ssh-server-cert-profile-user)# trustpoint verify trust2

Device(ssh-server-cert-profile-user)# end
```

## Feature History for X.509v3 Certificates for SSH Authentication

This table provides release and related information for features explained in this module.

These features are available on all releases subsequent to the one they were introduced in, unless noted otherwise.

Release	Feature	Feature Information
Cisco IOS XE Fuji 16.9.2	X.509v3 Certificates for SSH Authentication	The X.509v3 Certificates for SSH Authentication feature uses the X.509v3 digital certificates in server and user authentication at the SSH server side.

Use Cisco Feature Navigator to find information about platform and software image support. To access Cisco Feature Navigator, go to http://www.cisco.com/go/cfn.

Feature History for X.509v3 Certificates for SSH Authentication