



ACS QoS-Group-of-Ruledefs Configuration Mode Commands

The ACS QoS-Group-of-Ruledefs Configuration Mode is used to configure groups of rule definitions (ruledefs).

Command Modes

Exec > ACS Configuration > QoS-Group-of-Ruledefs Configuration

active-charging service *service_name* > **qos-group-of-ruledefs** *group_name*

Entering the above command sequence results in the following prompt:

```
[local] host_name(config-qos-group-of-ruledefs) #
```



Important

The commands or keywords/variables that are available are dependent on platform type, product version, and installed license(s).

- [add-group-of-ruledef, on page 1](#)
- [add-ruledef, on page 2](#)
- [end, on page 3](#)
- [exit, on page 3](#)

add-group-of-ruledef

This command allows you to add or remove groups-of-ruledefs from a qos-group-of-ruledefs.

Product

ACS

Privilege

Security Administrator, Administrator

Command Modes

Exec > ACS Configuration > QoS-Group-of-Ruledefs Configuration

active-charging service *service_name* > **qos-group-of-ruledefs** *group_name*

Entering the above command sequence results in the following prompt:

```
[local] host_name(config-qos-group-of-ruledefs) #
```

Syntax Description

[no] **add-group-of-ruledef** *group_of_ruledef_name*

no

If added previously, removes the specified group-of-ruledef from the current qos-group-of-ruledefs.

group_of_ruledef_name

Specifies name of the group-of-ruledef to add/remove from the current qos-group-of-ruledefs.

group_of_ruledef_name must be the name of an ACS group-of-ruledef, and must be an alphanumeric string of 1 through 63 characters.

Usage Guidelines

Use this command to add/remove a group-of-ruledefs from a qos-group-of-ruledefs.

Example

The following command adds the group-of-ruledef named *grpruledef1* to the current qos-group-of-ruledefs:

```
add-group-of-ruledef grpruledef1
```

add-ruledef

This command allows you to add or remove ruledefs from a qos-group-of-ruledefs.

Product

ACS

Privilege

Security Administrator, Administrator

Command Modes

Exec > ACS Configuration > QoS-Group-of-Ruledefs Configuration

active-charging service *service_name* > **qos-group-of-ruledefs** *group_name*

Entering the above command sequence results in the following prompt:

```
[local]host_name(config-qos-group-of-ruledefs)#
```

Syntax Description

[**no**] **add-ruledef** *ruledef_name*

no

If added previously, removes the specified ruledef from the current qos-group-of-ruledefs.

ruledef_name

Specifies name of the ruledef to add/remove from the current qos-group-of-ruledefs.

ruledef_name must be the name of an ACS ruledef, and must be an alpha and/or numeric string of 1 through 63 characters.

Usage Guidelines

Use this command to add/remove ruledefs from a qos-group-of-ruledefs.

**Warning**

Deletion or addition of the same rule name must be done with some amount of time lag.

Example

The following command adds the ruledef *ruledef23* to the current qos-group-of-ruledefs:

```
add-ruledef ruledef23
```

end

Exits the current configuration mode and returns to the Exec mode.

Product	All
Privilege	Security Administrator, Administrator
Syntax Description	end
Usage Guidelines	Use this command to return to the Exec mode.

exit

Exits the current mode and returns to the parent configuration mode.

Product	All
Privilege	Security Administrator, Administrator
Syntax Description	exit
Usage Guidelines	Use this command to return to the parent configuration mode.

■ exit