



Install Cisco Jabber

Review the options for installation and learn about different methods for installing Cisco Jabber. Understand the requirements for successful deployments before you start the installation procedure.

- [Methods of Installation, on page 1](#)
- [Use the Command Line, on page 2](#)
- [Run the MSI Manually, on page 3](#)
- [Create a Custom Installer, on page 4](#)
- [Deploy with Group Policy, on page 7](#)
- [Command Line Arguments, on page 9](#)
- [Installer Properties, on page 20](#)
- [Supported Languages, on page 21](#)
- [Cisco Media Services Interface, on page 21](#)
- [Uninstall Cisco Jabber for Windows, on page 23](#)

Methods of Installation

Cisco Jabber for Windows provides an MSI installation package. You must be logged in as an administrator to complete installation. You can use this installation package in the following ways:

Use the Command Line

Specify arguments in a command line window to set installation properties.

Choose this option if you plan to install multiple instances.

Run the MSI Manually

Run the MSI manually on the file system of the client workstation and then specify connection properties when you start the client.

Choose this option if you plan to install a single instance for testing or evaluation purposes.

Create a Custom Installer

Open the default installation package, specify the required installation properties, and then save a custom installation package.

Choose this option if you plan to distribute an installation package with the same installation properties.

Deploy with Group Policy

Install the client on multiple computers in the same domain.

Use the Command Line

Specify installation arguments in a command line window.

Procedure

- Step 1** Open a command line window.
- Step 2** Enter the following command:
- ```
msiexec.exe /i CiscoJabberSetup.msi
```
- Step 3** Specify command line arguments as parameter=value pairs.
- ```
msiexec.exe /i CiscoJabberSetup.msi argument=value
```
- Step 4** Run the command to install Cisco Jabber for Windows.
-

Example Installation Commands

Review examples of commands to install Cisco Jabber for Windows.

Cisco Unified Communications Manager, Release 9.x

```
msiexec.exe /i CiscoJabberSetup.msi /quiet CLEAR=1
```

Where:

- CLEAR=1 — Deletes any existing bootstrap file.
- /quiet — Specifies a silent installation.

Cisco Unified Communications Manager, Release 8.x in Default Mode

```
msiexec.exe /i CiscoJabberSetup.msi /quiet CLEAR=1 AUTHENTICATOR=CUP CUP_ADDRESS=1.2.3.4
```

Where:

- CLEAR=1 — Deletes any existing bootstrap file.
- AUTHENTICATOR=CUP — Sets Cisco Unified Presence as the authenticator.
- CUP_ADDRESS=1.2.3.4 — Sets 1.2.3.4 as the IP address of the presence server.
- /quiet — Specifies a silent installation.

Cisco Unified Communications Manager, Release 8.x in Phone Mode

If you are integrating with UDS when you are installing in phone mode, you must first define the `<PresenceDomain>Domain address of your Presence server</PresenceDomain>` parameter.

```
msiexec.exe /i CiscoJabberSetup.msi /quiet CLEAR=1 PRODUCT_MODE=Phone_Mode AUTHENTICATOR=CUCM  
TFTP=1.2.3.4 CTI=5.6.7.8
```

Where:

`CLEAR=1` — Deletes any existing bootstrap file.
`PRODUCT_MODE=Phone_Mode` — Sets the client to phone mode.
`AUTHENTICATOR=CUCM` — Sets Cisco Unified Communications Manager as the authenticator.
`TFTP=1.2.3.4` — Sets 1.2.3.4 as the IP address of the TFTP server that hosts the client configuration.
`CTI=5.6.7.8` — Sets 5.6.7.8 as the IP address of the CTI server.
`/quiet` — Specifies a silent installation.

Cisco WebEx Messenger Service

```
msiexec.exe /i CiscoJabberSetup.msi /quiet CLEAR=1 AUTHENTICATOR=WEBEX
```

Where:

`CLEAR=1` — Deletes any existing bootstrap file.
`AUTHENTICATOR=WEBEX` — Sets the Cisco WebEx Messenger service as the authenticator.
`/quiet` — Specifies a silent installation.

Cisco WebEx Messenger Service with SSO

```
msiexec.exe /i CiscoJabberSetup.msi /quiet CLEAR=1 AUTHENTICATOR=WEBEX  
SSO_ORG_DOMAIN=example.com
```

Where:

`CLEAR=1` — Deletes any existing bootstrap file.
`AUTHENTICATOR=WEBEX` — Sets the Cisco WebEx Messenger service as the authenticator.
`SSO_ORG_DOMAIN=example.com` — Sets `example.com` as the single sign-on (SSO) domain.
`/quiet` — Specifies a silent installation.

Run the MSI Manually

You can run the installation program manually to install a single instance of the client and specify connection settings in the Advanced settings window.

Procedure

- Step 1** Launch `CiscoJabberSetup.msi`.
The installation program opens a window to guide you through the installation process.
 - Step 2** Follow the steps to complete the installation process.
 - Step 3** Start Cisco Jabber for Windows.
 - Step 4** Select **Manual setup and sign in**.
The Advanced settings window opens.
 - Step 5** Specify values for the connection settings properties.
 - Step 6** Select **Save**.
-

Create a Custom Installer

You can transform the default installation package to create a custom installer.



Note You use Microsoft Orca to create custom installers. Microsoft Orca is available as part of the Microsoft Windows SDK for Windows 7 and .NET Framework 4.

Download and install Microsoft Windows SDK for Windows 7 and .NET Framework 4 from the [Microsoft website](#).

Procedure

	Command or Action	Purpose
Step 1	Get the Default Transform File, on page 4	You must have the default transform file to modify the installation package with Microsoft Orca.
Step 2	Create Custom Transform Files, on page 5	Transform files contain installation properties that you apply to the installer.
Step 3	Transform the Installer, on page 5	Apply a transform file to customize the installer.

Related Topics

[Microsoft Windows SDK for Windows 7 and .NET Framework 4](#)

Get the Default Transform File

You must have the default transform file to modify the installation package with Microsoft Orca.

Procedure

- Step 1** Download the Cisco Jabber administration package from [Software Download page](#).
- Step 2** Copy `CiscoJabberProperties.msi` from the Cisco Jabber administration package to your file system.

What to do next

[Create Custom Transform Files, on page 5](#)

Related Topics

[Software Downloads](#)

Create Custom Transform Files

To create a custom installer, you use a transform file. Transform files contain installation properties that you apply to the installer.

The default transform file lets you specify values for properties when you transform the installer. You should use the default transform file if you are creating one custom installer.

You can optionally create custom transform files. You specify values for properties in a custom transform file and then apply it to the installer.

Create custom transform files if you require more than one custom installer with different property values. For example, create one transform file that sets the default language to French and another transform file that sets the default language to Spanish. You can then apply each transform file to the installation package separately. The result is that you create two installers, one for each language.

Before you begin

[Get the Default Transform File, on page 4](#)

Procedure

- Step 1** Start Microsoft Orca.
 - Step 2** Open `CiscoJabberSetup.msi` and then apply `CiscoJabberProperties.msi`.
 - Step 3** Specify values for the appropriate installer properties.
 - Step 4** Generate and save the transform file.
 - a) Select **Transform > Generate Transform**.
 - b) Select a location on your file system to save the transform file.
 - c) Specify a name for the transform file and select **Save**.
-

The transform file you created is saved as `file_name.mst`. You can apply this transform file to modify the properties of `CiscoJabberSetup.msi`.

What to do next

[Transform the Installer, on page 5](#)

Transform the Installer

Apply a transform file to customize the installer.



Note

Applying transform files will alter the digital signature of `CiscoJabberSetup.msi`. Attempts to modify or rename `CiscoJabberSetup.msi` will remove the signature entirely.

Before you begin

[Create Custom Transform Files, on page 5](#)

Procedure

Step 1 Start Microsoft Orca.

Step 2 Open `CiscoJabberSetup.msi` in Microsoft Orca.

- a) Select **File > Open**.
- b) Browse to the location of `CiscoJabberSetup.msi` on your file system.
- c) Select `CiscoJabberSetup.msi` and then select **Open**.

The installation package opens in Microsoft Orca. The list of tables for the installer opens in the **Tables** pane.

Step 3 Required: Remove all language codes except for 1033 (English).

Restriction You must remove all language codes from the custom installer except for 1033 (English).

Microsoft Orca does not retain any language files in custom installers except for the default, which is 1033. If you do not remove all language codes from the custom installer, you cannot run the installer on any operating system where the language is other than English.

- a) Select **View > Summary Information**.
The **Edit Summary Information** window displays.
- b) Locate the **Languages** field.
- c) Delete all language codes except for 1033.
- d) Select **OK**.

English is set as the language for your custom installer.

Step 4 Apply a transform file.

- a) Select **Transform > Apply Transform**.
- b) Browse to the location of the transform file on your file system.
- c) Select the transform file and then select **Open**.

Step 5 Select **Property** from the list of tables in the **Tables** pane.

The list of properties for `CiscoJabberSetup.msi` opens in the right panel of the application window.

Step 6 Specify values for the properties you require.

Tip Set the value of the CLEAR property to 1 to override any existing bootstrap file from previous installations. If you do not override existing bootstrap files, the values you set in the custom installer do not take effect.

Step 7 Remove any properties that you do not require.

It is essential to remove any properties that are not being set, otherwise the properties being set will not take effect. Remove each property that is not needed one at a time.

- a) Right-click the property you want to remove.
- b) Select **Drop Row**.
- c) Select **OK** when Microsoft Orca prompts you to continue.

Step 8 Required: Enable your custom installer to save embedded streams.

- a) Select **Tools > Options**.
- b) Select the **Database** tab.
- c) Select **Copy embedded streams during 'Save As'**.
- d) Select **Apply** and then **OK**.

Step 9 Save your custom installer.

- a) Select **File > Save Transformed As**.
- b) Select a location on your file system to save the installer.
- c) Specify a name for the installer and then select **Save**.

Related Topics

[Installer Properties](#), on page 20

Deploy with Group Policy

Install Cisco Jabber for Windows with Group Policy using the Microsoft Group Policy Management Console (GPMC) on Microsoft Windows Server.



Note To install Cisco Jabber for Windows with Group Policy, all computers or users to which you plan to deploy Cisco Jabber for Windows must be in the same domain.

Procedure

	Command or Action	Purpose
Step 1	Set a Language Code, on page 7	You must use this procedure and set the Language field to 1033 only if the MSI is to be modified by Orca in any way.
Step 2	Deploy the Client with Group Policy, on page 8	Deploy Cisco Jabber for Windows with Group Policy.

Set a Language Code

Altering the installation language is not necessary in Group Policy deployment scenarios where the exact MSI file provided by Cisco will be used. The installation language will be determined from the Windows User Locale (Format) in these situations. You must use this procedure and set the Language field to 1033 only if the MSI is to be modified by Orca in any way.

Procedure

Step 1 Start Microsoft Orca.

Microsoft Orca is available as part of the Microsoft Windows SDK for Windows 7 and .NET Framework 4 that you can download from the Microsoft website.

- Step 2** Open `CiscoJabberSetup.msi`.
- Select **File > Open**.
 - Browse to the location of `CiscoJabberSetup.msi` on your file system.
 - Select `CiscoJabberSetup.msi` and then select **Open**.
- Step 3** Select **View > Summary Information**.
- Step 4** Locate the **Languages** field.
- Step 5** Set the **Languages** field to 1033.
- Step 6** Select **OK**.
- Step 7** Required: Enable your custom installer to save embedded streams.
- Select **Tools > Options**.
 - Select the **Database** tab.
 - Select **Copy embedded streams during 'Save As'**.
 - Select **Apply** and then **OK**.
- Step 8** Save your custom installer.
- Select **File > Save Transformed As**.
 - Select a location on your file system to save the installer.
 - Specify a name for the installer and then select **Save**.

What to do next

[Deploy the Client with Group Policy, on page 8](#)

Related Topics

[Supported Languages, on page 21](#)

Deploy the Client with Group Policy

Complete the steps in this task to deploy Cisco Jabber for Windows with Group Policy.

Before you begin

[Set a Language Code, on page 7](#)

Procedure

- Step 1** Copy the installation package to a software distribution point for deployment.
- All computers or users to which you plan to deploy Cisco Jabber for Windows must be able to access the installation package on the distribution point.
- Step 2** Select **Start > Run** and then enter the following command:
- ```
GPMC.msc
```



The **Group Policy Management** console opens.

**Step 3**

Create a new group policy object.

- a) Right-click on the appropriate domain in the left pane.
- b) Select **Create a GPO in this Domain, and Link it here**.

The **New GPO** window opens.

- c) Enter a name for the group policy object in the **Name** field.
- d) Leave the default value or select an appropriate option from the **Source Starter GPO** drop-down list and then select **OK**.

The new group policy displays in the list of group policies for the domain.

**Step 4**

Set the scope of your deployment.

- a) Select the group policy object under the domain in the left pane.

The group policy object displays in the right pane.

- b) Select **Add** in the **Security Filtering** section of the **Scope** tab.

The **Select User, Computer, or Group** window opens.

- c) Specify the computers and users to which you want to deploy Cisco Jabber for Windows.

**Step 5**

Specify the installation package.

- a) Right-click the group policy object in the left pane and then select **Edit**.

The **Group Policy Management Editor** opens.

- b) Select **Computer Configuration** and then select **Policies > Software Settings**.
- c) Right-click **Software Installation** and then select **New > Package**.
- d) Enter the location of the installation package next to **File Name**; for example, `\\server\software_distribution`.

**Important** You must enter a Uniform Naming Convention (UNC) path as the location of the installation package. If you do not enter a UNC path, Group Policy cannot deploy Cisco Jabber for Windows.

- e) Select the installation package and then select **Open**.
- f) In the **Deploy Software** dialog box, select **Assigned** and then **OK**.

---

Group Policy installs Cisco Jabber for Windows on each computer the next time each computer starts.

## Command Line Arguments

Review the command line arguments you can specify when you install Cisco Jabber for Windows.

### Override Argument

The following table describes the parameter you must specify to override any existing bootstrap files from previous installations:

| Argument | Value | Description                                                                                                                                                                                                                                                     |
|----------|-------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| CLEAR    | 1     | Specifies if the client overrides any existing bootstrap file from previous installations.<br><br>The client saves the arguments and values you set during installation to a bootstrap file. The client then loads settings from the bootstrap file at startup. |

If you specify CLEAR, the following occurs during installation:

1. The client deletes any existing bootstrap file.
2. The client creates a new bootstrap file.

If you do not specify CLEAR, the client checks for existing bootstrap files during installation.

- If no bootstrap file exists, the client creates a bootstrap file during installation.
- If a bootstrap file exists, the client does not override that bootstrap file and preserves the existing settings.



**Note** If you are reinstalling Cisco Jabber for Windows, you should consider the following:

- The client does not preserve settings from existing bootstrap files. If you specify CLEAR, you must also specify all other installation arguments as appropriate.
- The client does not save your installation arguments to an existing bootstrap file. If you want to change the values for installation arguments, or specify additional installation arguments, you must specify CLEAR to override the existing settings.

To override existing bootstrap files, specify CLEAR in the command line as follows:

```
msiexec.exe /i CiscoJabberSetup.msi CLEAR=1
```

## Mode Type Argument

The following table describes the command line argument with which you specify the product mode:

| Argument     | Value      | Description                                                                                                                                                                                                                                                                            |
|--------------|------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| PRODUCT_MODE | Phone_Mode | Specifies the product mode for the client. You can set the following value: <ul style="list-style-type: none"> <li>• Phone_Mode — Cisco Unified Communications Manager is the authenticator.</li> </ul> Choose this value to provision users with audio devices as base functionality. |

## When to Set the Product Mode

In phone mode deployments Cisco Unified Communications Manager is the authenticator. When the client gets the authenticator, it determines the product mode is phone mode. However, because the client always starts in the default product mode on the initial launch, users must restart the client to enter phone mode after sign in.

- Cisco Unified Communications Manager, Release 9.x and Later — You should not set `PRODUCT_MODE` during installation. The client gets the authenticator from the service profile. After the user signs in, the client requires a restart to enter phone mode.
- Cisco Unified Communications Manager, Release 8.x — You can specify phone mode during installation if you set Cisco Unified Communications Manager as the authenticator. The client reads the bootstrap file on the initial launch and determines it should start in phone mode. The client then gets Cisco Unified Communications Manager as the authenticator from the bootstrap file or manual settings. After the user signs in, the client does not require a restart.

## Change Product Modes

To change the product mode, you must change the authenticator for the client. The client can then determine the product mode from the authenticator.

The method for changing from one product mode to another after installation, depends on your deployment.



---

**Note** In all deployments, the user can manually set the authenticator in the Advanced settings window.

In this case, you must instruct the user to change the authenticator in the Advanced settings window to change the product mode. You cannot override the manual settings, even if you uninstall and then reinstall the client.

---

### Change Product Modes with Cisco Unified Communications Manager Version 9.x and Later

To change product modes with Cisco Unified Communications Manager version 9.x and later, you change the authenticator in the service profile.

#### Procedure

---

**Step 1** Change the authenticator in the service profiles for the appropriate users.

##### Change Default Mode > Phone Mode

Do not provision users with an IM and Presence service.

If the service profile does not contain an IM and presence service configuration, the authenticator is Cisco Unified Communications Manager.

##### Change Phone Mode > Default Mode

Provision users with an IM and Presence service.

If you set the value of the **Product type** field in the IM and Presence profile to:

- **Unified CM (IM and Presence)** the authenticator is Cisco Unified Communications Manager IM and Presence Service.

- Webex (**IM and Presence**) the authenticator is the Cisco Webex Messenger service.

**Step 2** Instruct users to sign out and then sign in again.

When users sign in to the client, it retrieves the changes in the service profile and signs the user in to the authenticator. The client then determines the product mode and prompts the user to restart the client.

---

After the user restarts the client, the product mode change is complete.

## Change Product Modes with Cisco Unified Communications Manager Version 8.x

To change product modes with Cisco Unified Communications Manager version 8.x, you must reinstall Cisco Jabber for Windows to change the authenticator.

### Change Default Mode > Phone Mode

Set the following arguments, at a minimum:

- CLEAR=1 to delete any existing bootstrap file.
- AUTHENTICATOR=CUCM to set the authenticator to Cisco Unified Communications Manager.
- PRODUCT\_MODE=Phone\_Mode to set phone mode as the product mode.

### Change Phone Mode > Default Mode

Set the following arguments, at a minimum:

- CLEAR=1 to delete any existing bootstrap file.
- AUTHENTICATOR= one of the following:
  - CUP to set the authenticator to Cisco Unified Presence or Cisco Unified Communications Manager.
  - WEBEX to set the authenticator to the Cisco WebEx Messenger service.

## Authentication Arguments

The following table describe the command line arguments you can set to specify the source of authentication:

| Argument      | Value                          | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
|---------------|--------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| AUTHENTICATOR | CUP<br>CUCM<br>Webex           | <p>Specifies the source of authentication for the client. This value is used if Service Discovery fails. Set one of the following as the value:</p> <ul style="list-style-type: none"> <li>• CUP—Cisco Unified Communications Manager IM and Presence Service. On-premises deployments in the default product mode. The default product mode can be either full UC or IM only.</li> <li>• CUCM—Cisco Unified Communications Manager. On-premises deployments in phone mode.</li> <li>• Webex—Cisco Webex Messenger Service. Cloud-based or hybrid cloud-based deployments.</li> </ul> <p>In on-premises deployments with Cisco Unified Communications Manager version 9.x and later, you should deploy the <code>_cisco-uds</code> SRV record. The client can then automatically determine the authenticator.</p> |
| CUP_ADDRESS   | IP address<br>Hostname<br>FQDN | <p>Specifies the address of Cisco Unified Communications Manager IM and Presence Service. Set one of the following as the value:</p> <ul style="list-style-type: none"> <li>• Hostname (<i>hostname</i>)</li> <li>• IP address (<i>123.45.254.1</i>)</li> <li>• FQDN (<i>hostname.domain.com</i>)</li> </ul>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
| TFTP          | IP address<br>Hostname<br>FQDN | <p>Specifies the address of your TFTP server. Set one of the following as the value:</p> <ul style="list-style-type: none"> <li>• Hostname (<i>hostname</i>)</li> <li>• IP address (<i>123.45.254.1</i>)</li> <li>• FQDN (<i>hostname.domain.com</i>)</li> </ul> <p>You should specify this argument if you set Cisco Unified Communications Manager as the authenticator.</p> <p>If you deploy:</p> <ul style="list-style-type: none"> <li>• In phone mode—you should specify the address of the TFTP server that hosts the client configuration.</li> <li>• In default mode—you can specify the address of the Cisco Unified Communications Manager TFTP service that hosts the device configuration.</li> </ul>                                                                                                |

| Argument        | Value                          | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
|-----------------|--------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| CTI             | IP address<br>Hostname<br>FQDN | <p>Sets the address of your CTI server.</p> <p>Specify this argument if:</p> <ul style="list-style-type: none"> <li>You set Cisco Unified Communications Manager as the authenticator.</li> <li>Users have desk phone devices and require a CTI server.</li> </ul>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
| CCMCIP          | IP address<br>Hostname<br>FQDN | <p>Sets the address of your CCMCIP server.</p> <p>Specify this argument if:</p> <ul style="list-style-type: none"> <li>You set Cisco Unified Communications Manager as the authenticator.</li> <li>The address of your CCMCIP server is not the same as the TFTP server address.</li> </ul> <p>The client can locate the CCMCIP server with the TFTP server address if both addresses are the same.</p> <p>Cisco Unified Communications Manager release 9.x and earlier—If you enable Cisco Extension Mobility, the <code>Cisco Extension Mobility</code> service must be activated on the Cisco Unified Communications Manager nodes that are used for CCMCIP. For information about Cisco Extension Mobility, see the <i>Feature and Services</i> guide for your <a href="#">Cisco Unified Communications Manager</a> release.</p> |
| SERVICES_DOMAIN | Domain                         | <p>Sets the value of the domain where the DNS SRV records for Service Discovery reside.</p> <p>This argument can be set to a domain where no DNS SRV records reside if you want the client to use installer settings or manual configuration for this information. If this argument is not specified and Service Discovery fails, the user will be prompted for services domain information.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                     |

| Argument              | Value                                                                                                    | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |
|-----------------------|----------------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| VOICE_SERVICES_DOMAIN | Domain                                                                                                   | <p>In Hybrid Deployments the domain required to discover Webex via CAS lookup may be a different domain than where the DNS records are deployed. If this is the case then set the SERVICES_DOMAIN to be the domain used for Webex discovery (or let the user enter an email address) and set the VOICE_SERVICES_DOMAIN to be the domain where DNS records are deployed. If this setting is specified, the client will use the value of VOICE_SERVICES_DOMAIN to lookup the following DNS records for the purposes of Service Discovery and Edge Detection:</p> <ul style="list-style-type: none"> <li>• <code>_cisco-uds</code></li> <li>• <code>_cuplogin</code></li> <li>• <code>_collab-edge</code></li> </ul> <p>This setting is optional and if not specified, the DNS records are queried on the Services Domain which is obtained from the SERVICES_DOMAIN, email address input by the user, or cached user configuration.</p> |
| EXCLUDED_SERVICES     | One or more of: <ul style="list-style-type: none"> <li>• CUP</li> <li>• Webex</li> <li>• CUCM</li> </ul> | <p>Lists the services that you want Jabber to exclude from Service Discovery. For example, you may have done a trial with Webex which means that your company domain is registered on Webex, but you do not want Jabber users to authenticate using Webex. You want Jabber to authenticate with an on-premises CUP CUCM server. In this case set:</p> <ul style="list-style-type: none"> <li>• <code>EXCLUDED_SERVICES=WEBEX</code></li> </ul> <p>Possible values are CUP, CUCM, Webex</p> <p>To exclude more than one service, use comma separated values. For example, to exclude CUP and CUCM, specify: <b><code>EXCLUDED_SERVICES=CUP, CUCM</code></b>. To exclude all services, specify:<br/><b><code>EXCLUDED_SERVICES=CUP, CUCM, WEBEX</code></b></p> <p>If you exclude all services, you need to use manual configuration or bootstrap configuration to configure the Jabber client.</p>                                      |

## TFTP Server Address

Cisco Jabber for Windows retrieves two different configuration files from the TFTP server:

- Client configuration files that you create.
- Device configuration files that reside on the Cisco Unified Communications Manager TFTP service when you provision users with devices.

To minimize effort, you should host your client configuration files on the Cisco Unified Communications Manager TFTP service. You then have only one TFTP server address for all configuration files and can specify that address as required.

You can, however, host your client configuration on a different TFTP server to the one that contains the device configuration. In this case, you have two different TFTP server addresses, one address for the TFTP server that hosts device configuration and another address for the TFTP server that hosts client configuration files.

### Default Deployments

This section describes how you should handle two different TFTP server addresses in deployments that have a presence server.

You should do the following:

1. Specify the address of the TFTP server that hosts the client configuration on the presence server.
2. During installation, specify the address of the Cisco Unified Communications Manager TFTP service with the TFTP argument.

When the client starts for the first time, it:

1. Retrieves the address of the Cisco Unified Communications Manager TFTP service from the bootstrap file.
2. Gets device configuration from the Cisco Unified Communications Manager TFTP service.
3. Connects to the presence server.
4. Retrieves the address of the TFTP service that hosts the client configuration from the presence server.
5. Gets client configuration from the TFTP server.

### Phone Mode Deployments

This section describes how you should handle two different TFTP server addresses in phone mode deployments.

You should do the following:

1. During installation, specify the address of the TFTP server that hosts the client configuration with the TFTP argument.
2. Specify the address of the TFTP server that hosts the device configuration in your client configuration file with the following parameter: TftpServer1.
3. Host the client configuration file on the TFTP server.

When the client starts for the first time, it:

1. Retrieves the address of the TFTP server from the bootstrap file.
2. Gets client configuration from the TFTP server.
3. Retrieves the address of the Cisco Unified Communications Manager TFTP service from the client configuration.
4. Gets device configuration from the Cisco Unified Communications Manager TFTP service.



## Common Installation Arguments

The following table describes command line arguments that are common to all deployments:

| Argument            | Value           | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
|---------------------|-----------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| LANGUAGE            | LCID in decimal | <p>Defines the Locale ID (LCID), in decimal, of the language that Cisco Jabber for Windows uses. The value must be an LCID in decimal that corresponds to a supported language.</p> <p>For example, you can specify one of the following:</p> <ul style="list-style-type: none"> <li>• 1033 specifies English.</li> <li>• 1036 specifies French.</li> </ul> <p>See the <i>LCID for Languages</i> topic for a full list of the languages that you can specify.</p> <p>This argument is optional.</p> <p>If you do not specify a value, Cisco Jabber for Windows uses the regional language for the current user as the default.</p> <p>From Release 11.1(1) onwards, if you do not specify a value, Cisco Jabber for Windows checks the value for the UseSystemLanguage parameter. If the UseSystemLanguage parameter is set to true, the same language is used as for the operating system. If the UseSystemLanguage parameter is to set to false or not defined, then the client uses the regional language for the current user as the default.</p> <p>The regional language is set at <b>Control Panel &gt; Region and Language &gt; Change the date, time, or number format &gt; Formats tab &gt; Format dropdown.</b></p> |
| FORGOT_PASSWORD_URL | URL             | <p>Specifies the URL where users can reset lost or forgotten passwords.</p> <p>This argument is optional but recommended.</p> <p><b>Note</b> In cloud-based deployments, you can specify a forgot password URL using the Cisco WebEx Administration Tool. However, the client cannot retrieve that forgot password URL until users sign in.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |

| Argument          | Value         | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |
|-------------------|---------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| AUTOMATIC_SIGN_IN | true<br>false | <p>Applies to Release 11.1(1) onwards.</p> <p>Specifies whether the <b>Sign me in when Cisco Jabber starts</b> check box is checked when the user installs the client.</p> <ul style="list-style-type: none"> <li>• true—The <b>Sign me in when Cisco Jabber starts</b> check box is checked when the user installs the client.</li> <li>• false (default)—The <b>Sign me in when Cisco Jabber starts</b> check box is not checked when the user installs the client.</li> </ul>                                                                                                                                                                                                                                                                                                                           |
| TFTP_FILE_NAME    | Filename      | <p>Specifies the unique name of a group configuration file.</p> <p>You can specify either an unqualified or fully qualified filename as the value. The filename you specify as the value for this argument takes priority over any other configuration file on your TFTP server.</p> <p>This argument is optional.</p> <p><b>Remember</b> You can specify group configuration files in the <b>Cisco Support Field</b> on the CSF device configuration on Cisco Unified Communications Manager.</p>                                                                                                                                                                                                                                                                                                         |
| LOGIN_RESOURCE    | WBX<br>MUT    | <p>Controls user sign in to multiple client instances.</p> <p>By default, users can sign in to multiple instances of Cisco Jabber at the same time. Set one of the following values to change the default behavior:</p> <ul style="list-style-type: none"> <li>• WBX—Users can sign in to one instance of Cisco Jabber for Windows at a time.<br/>Cisco Jabber for Windows appends the <code>wbxconnect</code> suffix to the user's JID. Users cannot sign in to any other Cisco Jabber client that uses the <code>wbxconnect</code> suffix.</li> <li>• MUT—Users can sign in to one instance of Cisco Jabber for Windows at a time, but can sign in to other Cisco Jabber clients at the same time.<br/>Each instance of Cisco Jabber for Windows appends the user's JID with a unique suffix.</li> </ul> |

| Argument          | Value                                 | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
|-------------------|---------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| LOG_DIRECTORY     | Absolute path on the local filesystem | <p>Defines the directory where the client writes log files.</p> <p>Use quotation marks to escape space characters in the path, as in the following example:</p> <pre>"C:\my_directory\Log Directory"</pre> <p>The path you specify must not contain Windows invalid characters.</p> <p>The default value is<br/>%USER_PROFILE%\AppData\Local\Cisco\Unified Communications\Jabber\CSF\Logs</p>                                                                                                                                                                                                                                                                                             |
| CLICK2X           | DISABLE                               | <p>Disables click-to-x functionality with Cisco Jabber.</p> <p>If you specify this argument during installation, the client does not register as a handler for click-to-x functionality with the operating system. This argument prevents the client from writing to the Microsoft Windows registry during installation.</p> <p>You must re-install the client and omit this argument to enable click-to-x functionality with the client after installation.</p>                                                                                                                                                                                                                          |
| Telemetry_Enabled | true<br>false                         | <p>Specifies whether analytics data is gathered. The default value is true.</p> <p>To improve your experience and product performance, Cisco Jabber may collect and send non-personally identifiable usage and performance data to Cisco. The aggregated data is used by Cisco to understand trends in how Jabber clients are being used and how they are performing.</p> <p>Full details on what analytics data Cisco Jabber does and does not collect can be found in the Cisco Jabber Supplement to Cisco's On-Line Privacy Policy at <a href="http://www.cisco.com/web/siteassets/legal/privacy_02Jun10.html">http://www.cisco.com/web/siteassets/legal/privacy_02Jun10.html</a>.</p> |

## SSO Arguments

This section describes the command line arguments you can use to deploy Cisco Jabber for Windows with single sign on (SSO) capabilities.

### Cloud-Based SSO Arguments

The arguments in the following table apply to cloud-based deployments only:

| Argument       | Value       | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
|----------------|-------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| SSO_ORG_DOMAIN | Domain name | <p>Specifies the domain name for the Cisco WebEx Org that contains the URL for the SSO service.</p> <p>Cisco Jabber for Windows uses this argument to retrieve the URL of the SSO service from the Org. When Cisco Jabber for Windows gets the SSO service URL, it can request login tokens to authenticate with Cisco WebEx Messenger.</p> <p><b>Note</b> You specify the URL for the SSO service as the value of the Customer SSO Service Login URL in the Cisco WebEx Administration Tool.</p> |

## Installer Properties

The following are the properties you can modify in a custom installer:

- CLEAR
- PRODUCT\_MODE
- AUTHENTICATOR
- CUP\_ADDRESS
- TFTP
- CTI
- CCMCIP
- LANGUAGE
- TFTP\_FILE\_NAME
- FORGOT\_PASSWORD\_URL
- SSO\_ORG\_DOMAIN
- LOGIN\_RESOURCE
- LOG\_DIRECTORY
- CLICK2X
- SERVICES\_DOMAIN

These properties correspond to the installation arguments and have the same values.

## Supported Languages

Cisco Jabber for Windows uses the regional language for the current user as the default. The regional language is set at **Control Panel > Region and Language > Change the date, time, or number format > Formats tab > Format dropdown**.

The following table lists the languages that Cisco Jabber for Windows supports.

|           |                       |                  |
|-----------|-----------------------|------------------|
| Arabic    | French                | Romanian         |
| Bulgarian | Hebrew                | Russian          |
| Catalan   | Hungarian             | Serbian          |
| Croatian  | Italian               | Slovak           |
| Czech     | Japanese              | Slovenian        |
| Danish    | Korean                | Swedish          |
| German    | Norwegian             | Thai             |
| Greek     | Dutch                 | Turkish          |
| English   | Polish                | Chinese - China  |
| Spanish   | Portuguese - Brazil   | Chinese - Taiwan |
| Finnish   | Portuguese - Portugal |                  |



**Note** Cisco Jabber for Windows does not support Locale IDs for all sub-languages. For example, if you specify French - Canada, Cisco Jabber for Windows uses French - France.

See the following documentation for more information about Locale IDs:

- *Microsoft Windows Locale Code Identifier (LCID) Reference*
- *Locale IDs Assigned by Microsoft*

### Related Topics

- [Microsoft Windows Locale Code Identifier \(LCID\) Reference](#)
- [Locale IDs Assigned by Microsoft](#)

## Cisco Media Services Interface

Cisco Jabber for Windows supports Cisco Media Services Interface version 4.1.2 for Microsoft Windows 7 and later.

Cisco Jabber for Mac supports Cisco Media Services Interface version 4.0.2 or later.

## Traffic Marking

Cisco Media Services Interface provides a service that works with Cisco Prime Collaboration Manager and Cisco Medianet-enabled routers to ensure that Cisco Jabber can send audio media and video media on your network with minimum latency or packet loss.

Before Cisco Jabber sends audio media or video media, it checks for Cisco Media Services Interface.

- If the service exists on the computer, Cisco Jabber provides flow information to Cisco Media Services Interface.

The service then signals the network so that routers classify the flow and provide priority to the Cisco Jabber traffic.

- If the service does not exist, Cisco Jabber does not use it and sends audio media and video media as normal.



---

**Note** Cisco Jabber checks for Cisco Media Services Interface for each audio call or video call.

---

## Desk Phone Video Capabilities

You must install Cisco Media Services Interface to enable desk phone video capabilities. Cisco Media Services Interface provides a driver that enables Cisco Jabber for Windows to do the following:

- Discover the desk phone device.
- Establish and maintain a connection to the desk phone device using the CAST protocol.

## Prepare Your Network

To install Cisco Media Service Interface for traffic marking, you must prepare your network.

### Procedure

---

- Step 1** Install Cisco Prime Collaboration manager.
- Step 2** Install routers or switches enabled for Cisco Medianet where appropriate.
- Step 3** Configure your network to handle the metadata attributes that Cisco Media Service Interface applies to applications.

Not all devices on your network must support Cisco Medianet.

The first hop should prioritize traffic based on the metadata attributes from Cisco Media Service Interface. As the traffic traverses the network, all other devices should also prioritize that traffic unless you configure policies on those devices to handle the traffic differently.

---

## Install Cisco Media Services Interface

### Procedure

---

- Step 1** Download the Cisco Media Services Interface installation program from the download site on [cisco.com](http://cisco.com).

- Step 2** Install Cisco Media Services Interface on each computer on which you install Cisco Jabber. See the appropriate Cisco Medianet documentation for installing Cisco Media Services Interface.

---

**Related Topics**

- [Download software](#)
- [Medianet Knowledge Base Portal](#)

## Uninstall Cisco Jabber for Windows

You can uninstall Cisco Jabber for Windows using either the command line or the Microsoft Windows control panel. This document describes how to uninstall Cisco Jabber for Windows using the command line.

### Use the Installer

If the installer is available on the file system, use it to remove Cisco Jabber for Windows.

---

**Procedure**

- Step 1** Open a command line window.
- Step 2** Enter the following command:

```
msiexec.exe /x path_to_CiscoJabberSetup.msi
```

For example,

```
msiexec.exe /x C:\Windows\Installer\CiscoJabberSetup.msi /quiet
```

Where `/quiet` specifies a silent uninstall.

---

The command removes Cisco Jabber for Windows from the computer.

### Use the Product Code

If the installer is not available on the file system, use the product code to remove Cisco Jabber for Windows.

---

**Procedure**

- Step 1** Find the product code.
- Open the Microsoft Windows registry editor.
  - Locate the following registry key: `HKEY_CLASSES_ROOT\Installer\Products`
  - Select **Edit > Find**.
  - Enter Cisco Jabber in the **Find what** text box in the **Find** window and select **Find Next**.
  - Find the value of the **ProductIcon** key.

The product code is the value of the **ProductIcon** key, for example,  
C:\Windows\Installer\{*product\_code*}\ARPPRODUCTICON.exe.

**Note** The product code changes with each version of Cisco Jabber for Windows.

**Step 2** Open a command line window.

**Step 3** Enter the following command:

```
msiexec.exe /x product_code
```

For example,

```
msiexec.exe /x 45992224-D2DE-49BB-B085-6524845321C7 /quiet
```

Where `/quiet` specifies a silent uninstall.

---

The command removes Cisco Jabber for Windows from the computer.