



Cisco Unified Border Element SIP Support Configuration Guide, Cisco IOS Release 12.4T

Americas Headquarters

Cisco Systems, Inc.
170 West Tasman Drive
San Jose, CA 95134-1706
USA
<http://www.cisco.com>
Tel: 408 526-4000
800 553-NETS (6387)
Fax: 408 527-0883

THE SPECIFICATIONS AND INFORMATION REGARDING THE PRODUCTS IN THIS MANUAL ARE SUBJECT TO CHANGE WITHOUT NOTICE. ALL STATEMENTS, INFORMATION, AND RECOMMENDATIONS IN THIS MANUAL ARE BELIEVED TO BE ACCURATE BUT ARE PRESENTED WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED. USERS MUST TAKE FULL RESPONSIBILITY FOR THEIR APPLICATION OF ANY PRODUCTS.

THE SOFTWARE LICENSE AND LIMITED WARRANTY FOR THE ACCOMPANYING PRODUCT ARE SET FORTH IN THE INFORMATION PACKET THAT SHIPPED WITH THE PRODUCT AND ARE INCORPORATED HEREIN BY THIS REFERENCE. IF YOU ARE UNABLE TO LOCATE THE SOFTWARE LICENSE OR LIMITED WARRANTY, CONTACT YOUR CISCO REPRESENTATIVE FOR A COPY.

The Cisco implementation of TCP header compression is an adaptation of a program developed by the University of California, Berkeley (UCB) as part of UCB's public domain version of the UNIX operating system. All rights reserved. Copyright © 1981, Regents of the University of California.

NOTWITHSTANDING ANY OTHER WARRANTY HEREIN, ALL DOCUMENT FILES AND SOFTWARE OF THESE SUPPLIERS ARE PROVIDED "AS IS" WITH ALL FAULTS. CISCO AND THE ABOVE-NAMED SUPPLIERS DISCLAIM ALL WARRANTIES, EXPRESSED OR IMPLIED, INCLUDING, WITHOUT LIMITATION, THOSE OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT OR ARISING FROM A COURSE OF DEALING, USAGE, OR TRADE PRACTICE.

IN NO EVENT SHALL CISCO OR ITS SUPPLIERS BE LIABLE FOR ANY INDIRECT, SPECIAL, CONSEQUENTIAL, OR INCIDENTAL DAMAGES, INCLUDING, WITHOUT LIMITATION, LOST PROFITS OR LOSS OR DAMAGE TO DATA ARISING OUT OF THE USE OR INABILITY TO USE THIS MANUAL, EVEN IF CISCO OR ITS SUPPLIERS HAVE BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: www.cisco.com/go/trademarks. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.

© 2011 Cisco Systems, Inc. All rights reserved.



CONTENTS

Cisco Unified Border Element SIP Support 1

Finding Feature Information 1

Cisco Unified Border Element SIP Support Features 1

SIP Core SIP Technology Enhancements 3

Finding Feature Information 5

Simultaneous Cancel and 2xx Class Response 6

Prerequisites for SIP Core SIP Technology Enhancements 6

Restrictions for SIP Core SIP Technology Enhancements 6

How to Configure SIP Core SIP Technology Enhancements 6

Monitoring 487 Sent for BYE Requests 7

Monitoring 3xx Redirection Responses 8

Monitoring the Deletion of 303 and 411 Cause Codes 10

Examples 10

show sip-ua statistics Command 11

show sip-ua map 12

Configuration Examples for SIP Core SIP Technology Enhancements 13

SIP Core SIP Technology Enhancements Example 13

Feature Information for SIP Core SIP Technology Enhancements 14

Reporting End-of-Call Statistics in SIP BYE Message 17

Finding Feature Information 18

Prerequisites for Reporting End-of-Call Statistics in SIP BYE Message 18

Restrictions for Reporting End-of-Call Statistics in SIP BYE Message 18

Disabling Reporting End-of-Call Statistics in SIP BYE Message 19

Defining SIP Profile Rules to Remove a Header 19

Disabling Reporting End-of-Call Statistics in SIP BYE Message at the Global Level 20

Disabling Reporting End-of-Call Statistics in SIP BYE Message at the Dial Peer Level 21

Feature Information for Reporting End-of-Call Statistics in SIP BYE Message 23

Configurable Hostname in Locally Generated SIP Headers 25

Finding Feature Information 25

Prerequisites for Configurable Hostname in Locally Generated SIP Headers	25
Restrictions for Configurable Hostname in Locally Generated SIP Headers	26
How to Configure the Hostname in Locally Generated SIP Headers	26
Configuring Hostname in Locally Generated SIP Headers at the Global Level	26
Configuring Hostname in Locally Generated SIP Headers at the Dial-Peer-Specific Level	27
Verifying the Hostname in Locally Generated SIP Headers	29
Feature Information for Configurable Hostname in Locally Generated SIP Headers	34
SIP Parameter Modification	37
Finding Feature Information	39
Example	39
Feature Information for Configuring SIP Parameter Modification	40
SIP Session Timer Support	43
Finding Feature Information	43
Prerequisites for SIP Session Timer Support	43
Information About SIP Session Timer Support	44
How to Configure SIP Session Timer Support	45
Prerequisites	45
Restrictions	46
Configuring SIP Session Timer Support	46
Troubleshooting Tips	47
Feature Information for SIP Session Timer Support	48
SIP-to-SIP Basic Functionality for Session Border Controller	51
Finding Feature Information	51
Prerequisites for SIP-to-SIP Basic Functionality for Session Border Controller	52
Feature Information for SIP-to-SIP Basic Functionality for Session Border Controller	52
SIP-to-SIP Supplementary Services for Session Border Controller	55
Finding Feature Information	55
Prerequisites for SIP-to-SIP Supplementary Services for Session Border Controller	56
How to Configure SIP-to-SIP Supplementary Services for Session Border Controller	56
Feature Information for SIP-to-SIP Supplementary Services for Session Border Controller	56
Session Refresh with Reinvites	59
Finding Feature Information	61
Feature Information for Session Refresh with Reinvites	61
Configuring Cisco UBE Out-of-dialog OPTIONS Ping for Specified SIP Servers or Endpoints	63
Finding Feature Information	65

Troubleshooting Tips	65
Feature Information for Cisco UBE Out-of-dialog OPTIONS Ping for Specified SIP Servers or Endpoints	66
Configuring an Error Response Code upon an Out-of-Dialog OPTIONS Ping Failure	69
Finding Feature Information	69
Prerequisites for Configuring an Error Response Code upon an Out-of-Dialog OPTIONS Ping Failure	70
Restrictions for Configuring an Error Response Code upon an Out-of-Dialog OPTIONS Ping Failure	70
Configuring an Error Response Code upon an Out-of-Dialog OPTIONS Ping Failure at the Global Level	70
Configuring an Error Response Code upon an Out-of-Dialog OPTIONS Ping Failure at the Dial Peer Level	72
Troubleshooting Tips	73
Feature Information for Configuring an Error Response Code upon an Out-of-Dialog OPTIONS Ping Failure	74
SIP INFO Method for DTMF Tone Generation	77
Finding Feature Information	77
Prerequisites for SIP INFO Method for DTMF Tone Generation	77
Information About SIP INFO Method for DTMF Tone Generation	78
How to Review SIP INFO Messages	78
Prerequisites	78
Restrictions	78
Configuring for SIP INFO Method for DTMF Tone Generation	79
Troubleshooting Tips	79
Feature Information for SIP INFO Method for DTMF Tone Generation	80
SIP Enhanced 180 Provisional Response Handling	83
Finding Feature Information	83
Prerequisites SIP Enhanced 180 Provisional Response Handling	83
Information About SIP Enhanced 180 Provisional Response Handling	84
How to Disable the SIP Enhanced 180 Provisional Response Handling Feature	84
Disabling Early Media Cut-Through	84
Verifying SIP Enhanced 180 Provisional Response Handling	85
Configuration Examples for SIP - Enhanced 180 Provisional Response Handling	86
show running-config Command	86
show sip-ua status Command	86

show logging Command	87
Feature Information for SIP Enhanced 180 Provisional Response Handling	89
Configuring SIP 181 Call is Being Forwarded Message	91
Finding Feature Information	91
Prerequisites for SIP 181 Call is Being Forwarded Message	91
Configuring SIP 181 Call is Being Forwarded Message Globally	92
Configuring SIP 181 Call is Being Forwarded Message at the Dial-Peer Level	93
Configuring Mapping of SIP Provisional Response Messages Globally	94
Configuring Mapping of SIP Provisional Response Messages at the Dial-Peer Level	95
Feature Information for Configuring SIP 181 Call is Being Forwarded Message	97
Expires Timer Reset on Receiving or Sending SIP 183 Message	99
Finding Feature Information	99
Prerequisites for Expires Timer Reset on Receiving or Sending SIP 183 Message	99
How to Configure Expires Timer Reset on Receiving or Sending SIP 183 Message	100
Configuring Reset of Expires Timer Globally	100
Configuring Reset of Expires Timer at the Dial-Peer Level	101
Feature Information for Configuring Support for Expires Timer Reset on Receiving or Sending SIP 183 Message	102
SIP UPDATE Message per RFC 3311	105
Finding Feature Information	105
Prerequisites for SIP UPDATE Message per RFC 3311	105
Restrictions	106
Feature Information for the SIP UPDATE Message per RFC 3311	106
Support for PAID PPID Privacy PCPID and PAURI Headers on the Cisco Unified Border Element	109
Finding Feature Information	117
Prerequisites for Support for PAID PPID Privacy PCPID and PAURI Headers on the Cisco UBE	117
Restrictions for Support for PAID PPID Privacy PCPID and PAURI Headers on the Cisco UBE	117
Configuring P-Header and Random-Contact Support on the Cisco Unified Border Element	118
Configuring P-Header Translation on a Cisco Unified Border Element	118
Configuring P-Header Translation on an Individual Dial Peer	119
Configuring P-Called-Party-Id Support on a Cisco Unified Border Element	120
Configuring P-Called-Party-Id Support on an Individual Dial Peer	122
Configuring Privacy Support on a Cisco Unified Border Element	123
Configuring Privacy Support on an Individual Dial Peer	125

Configuring Random-Contact Support on a Cisco Unified Border Element	126
Configuring Random-Contact Support for an Individual Dial Peer	128
Feature Information for PAID PPID Privacy PCPID and PAURI Headers on the Cisco Unified Border Element	129
Configurable Pass-through of SIP INVITE Parameters	133
Finding Feature Information	133
Prerequisites for Configurable Pass-through of SIP INVITE Parameters	133
Restrictions for Configurable Pass-through of SIP INVITE Parameters	134
Information About Configurable Pass-through of SIP INVITE Parameters	134
How to Configure Configurable Pass-through of SIP INVITE Parameters	134
Configuring Configurable Pass-through of SIP INVITE Parameters at the Global Level	135
Configuring Configurable Pass-through of SIP INVITE Parameters at the Dial Peer Level	136
Feature Information for Configurable Pass-through of SIP INVITE Parameters	137
Conditional Header Manipulation of SIP Headers	141
Finding Feature Information	141
Prerequisites for Conditional Header Manipulation of SIP Headers	141
Restrictions	142
Passing an Unsupported Parameter Present in a Mandatory Header from One Call Leg to Another of Cisco UBE	142
Copying Contents from One Header to Another in an Outgoing SIP Message	143
Copying Contents from One SIP Header to Another in an Outgoing Message	143
Copying Contents from Peer Header to a SIP Header in an Outgoing Message	144
Feature Information for Support for Conditional Header Manipulation of SIP Headers	146
Transparent Tunneling of QSIG and Q.931	149
Finding Feature Information	149
Prerequisites for Transparent Tunneling of QSIG and Q.931	150
Restrictions for Transparent Tunneling of QSIG and Q.931	150
Information About Transparent Tunneling of QSIG or Q.931	150
Use of the QSIG or Q.931 Protocols	150
Purpose of Tunneling QSIG or Q.931 over SIP	151
Encapsulation of QSIG in SIP Messaging	151
Mapping of QSIG Message Elements to SIP Message Elements	153
How to Transparently Tunnel QSIG over SIP	153
Configuring Signaling Forward Settings for a Gateway	154
Signaling Forward Settings for a Gateway	154
Configuring Signaling Forward Settings for an Interface	155

Signaling Forward Settings for an Interface	155
Configuration Examples for Transparent Tunneling of QSIG	157
Tunneling QSIG Raw Messages over SIP Example	157
Tunneling QSIG Messages Unconditionally over SIP Example	158
Tunneling QSIG Raw Messages over SIP on an Interface Example	158
Tunneling QSIG Messages Unconditionally over SIP on an Interface Example	159
Feature Information for Transparent Tunneling of QSIG and Q.931	159
SIP Diversion Header Enhancements	163
Finding Feature Information	163
Prerequisites for SIP Diversion Header Enhancements	163
Information about SIP Diversion Header Enhancements	164
How to Configure SIP Diversion Header Enhancements	164
Feature Information for SIP Diversion Header Enhancements	165
SIP History INFO	169
Finding Feature Information	169
Prerequisites	169
Configuring SIP History INFO	169
Feature Information for SIP History-info Header	170
SIP Ability to Send a SIP Registration Message on a Border Element	173
Finding Feature Information	174
Feature Information for Sending a SIP Registration Message from a Cisco Unified Border Element	175
Configurable SIP Parameters via DHCP	177
Finding Feature Information	177
Prerequisites for Configurable SIP Parameters via DHCP	177
Restrictions for Configurable SIP Parameters via DHCP	178
Information About Configurable SIP Parameters via DHCP	178
How to Configure SIP Parameters via DHCP	181
Configuring the DHCP Client	181
Configuring the DHCP Client Example	183
Enabling the SIP Configuration	183
Enabling the SIP Configuration Example	185
Troubleshooting Tips	185
Configuring a SIP Outbound Proxy Server	185
Configuring a SIP Outbound Proxy Server in Voice Service VoIP Configuration Mode	186

Configuring a SIP Outbound Proxy Server in Voice Service VoIP Configuration Mode Example	187
Configuring a SIP Outbound Proxy Server and Session Target in Dial Peer Configuration Mode Example	187
Configuring a SIP Outbound Proxy Server in Dial Peer Configuration Mode Example	189
Feature Information for Configurable SIP Parameters via DHCP	189
Multiple Registrars on SIP Trunks	191
Finding Feature Information	191
Prerequisites for Multiple Registrars on SIP Trunks	191
Restrictions for Multiple Registrars on SIP Trunks	192
Configuring Multiple Registrars on SIP Trunks Feature	192
Feature Information for the Multiple Registrars on SIP Trunks Feature	192
Additional References	195
Related Documents	195
Standards	196
MIBs	196
RFCs	197
Technical Assistance	198
Glossary	199



Cisco Unified Border Element SIP Support

This Cisco Unified Border Element is a special Cisco IOS software image that provides a network-to-network interface point for billing, security, call admission control, quality of service, and signaling interworking. This chapter describes basic gateway functionality, software images, topology, and summarizes supported features.



Note

Cisco Product Authorization Key (PAK)--A Product Authorization Key (PAK) is required to configure some of the features described in this guide. Before you start the configuration process, please register your products and activate your PAK at the following URL <http://www.cisco.com/go/license> .

- [Finding Feature Information, page 1](#)
- [Cisco Unified Border Element SIP Support Features, page 1](#)

Finding Feature Information

Your software release may not support all the features documented in this module. For the latest feature information and caveats, see the release notes for your platform and software release. To find information about the features documented in this module, and to see a list of the releases in which each feature is supported, see the Feature Information Table at the end of this document.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Cisco Unified Border Element SIP Support Features

This chapter contains the following configuration topics:

Cisco UBE Prerequisites and Restrictions

- Prerequisites for Cisco Unified Border Element
- Restrictions for Cisco Unified Border Element

Basic SIP Set-up

- SIP--Core SIP Technology Enhancements

SIP Parameter Settings

- SIP--Configurable Hostname in Locally Generated SIP Headers
- SIP Parameter Modification
- SIP--Session Timer Support

SIP Protocol Handling and Supplementary Services

- SIP-to-SIP Basic Functionality for Session Border Controller
- SIP-to-SIP Extended Feature Functionality for Session Border Controllers
- SIP-to-SIP Supplementary Services for Session Border Controller
- Cisco UBE Support for generating Out-of-dialog SIP OPTIONS Ping messages to monitor SIP Servers
- SIP--INFO Method for DTMF Tone Generation
- SIP--Enhanced 180 Provisional Response Handling
- Configuring Support for SIP 181 Call is Being Forwarded Message
- Support for Expires Timer Reset on Receiving or Sending SIP 183 Message
- Support for PAID, PPID, Privacy, PCPID, and PAURI Headers on the Cisco UBE
- Configuring Selective Filtering of Outgoing Provisional Response on the Cisco UBE
- Cisco Unified Border Element Support for Configurable Pass-through of SIP INVITE Parameters
- Transparent Tunneling of QSIG and Q.931 over SIP TDM Gateway and SIP-SIP Cisco Unified Border Element
- SIP Diversion Header Enhancements

SIP Registration and Authentication

- SIP--Ability to Send a SIP Registration Message on a Border Element
- Support for Multiple Registrars on SIP Trunks

SIP Normalization

- SIP Parameter Modification

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: www.cisco.com/go/trademarks. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.



SIP Core SIP Technology Enhancements

The SIP: Core SIP Technology Enhancements feature updates Cisco SIP VoIP gateways with the latest changes in RFC 2543-bis-04. All changes are compatible with older RFC versions. Compliance to RFC 2543-bis-04 adds enhanced SIP support and ensures smooth interoperability and compatibility with multiple vendors.

The enhanced areas are as follows:

SIP URL Comparison

When a URL is received, the URLs are compared for equality. URL comparison can be done between two From SIP URLs, or it can be done between two To SIP URLs. For two URLs to be equal, the user, password, host, and port parameters must match. The order of the parameters does not to match.

The SIP: Core SIP Technology Enhancements feature changes the parameters allowed in SIP URLs. The maddr parameter and the transport parameter are not allowed in Cisco SIP gateway implementations. The user-param parameter is now the parameter for comparison.

If a compared parameter is omitted or not present, it is matched on the basis of its default value. The table below shows a list of SIP URL compared parameters and their default values.

Table 1 **SIP URL Parameter Comparison**

SIP URL Compared Parameter	Default
host	mandatory
password	--
port	5060
user	--
user-param	ip

The following is an example of equivalent URLs:

Original URL:

sip:36602@172.18.193.120

Equivalent URLs:

sip:36602@172.18.193.120:

sip:36602@172.18.193.120;tag=499270-A62;pname=pvalue

sip:36602@172.18.193.120;user=ip

sip:36602@172.18.193.120:5060

487 Sent for BYE Requests

RFC 2543-bis-04 requires that a user agent server (UAS) that receives a BYE request first send a response to any pending requests for that call before disconnecting. The SIP: Core SIP Technology Enhancements feature recommends that after receiving a BYE request the UAS respond with a 487 (Request Cancelled) status message.

3xx Redirection Responses

The processing of 3xx redirection responses was updated in the SIP: Core SIP Technology Enhancements feature as follows:

- The Uniform Resource Identifier (URI) of the redirected INVITE is updated to contain the new contact information provided by the 3xx redirect message.
- The transmitted CSeq number found in the CSeq header is increased by one. The new INVITE includes the updated CSeq.
- The To, From, and Call ID headers that identify the call leg remain the same. The same Call ID gives consistency when capturing billing history.
- The user agent client (UAC) retries the request at the new address given by the 3xx Contact header field.

See the [Examples, page 10](#) for a sample call flow that shows the updated CSeq numbers.

DNS SRV Query Procedure

When a Request URI or the session target in the dial peer contains a fully qualified domain name (FQDN), the UAC needs to determine the protocol, port, and IP address of the endpoint before it forwards the request. SIP on Cisco gateways uses a Domain Name System Server (DNS SRV) query to determine the protocol, port, and IP address of the user endpoint.

Before the SIP: Core SIP Technology Enhancements feature, the DNS query procedure did not take into account the destination port.

CANCEL Request Route Header

The SIP: Core SIP Technology Enhancements feature does not allow a CANCEL message sent by a UAC on an initial INVITE request to have a Route header. Route headers cannot appear in a CANCEL message because they take the same path as INVITE requests, and INVITE requests cannot contain Route headers.

Interpret User Parameters

Telephone-subscriber or user parameters in an incoming INVITE message may contain extra characters to incorporate space, control characters, quotation marks, hash marks, and other characters. The SIP: Core SIP Technology Enhancements feature allows the telephone-subscriber or user parameter to be interpreted before dial-peer matching is done. For example, the telephone number in an incoming INVITE message may appear as:

-%32%32%32

Although 222 is a valid telephone number, it requires interpretation. If the interpretation is not done, the call attempt fails when the user parameter is matched with the dial-peer destination pattern.

user=phone Parameter

A SIP URL identifies a user's address, whose appearance is similar to that of an e-mail address. The form of the user's address is *user@host* where *user* is the user identification and *host* is either a domain name or a numeric network address. For example, the request line of an outgoing INVITE request might appear as:

```
INVITE sip:5550002@companyb.com
```

With the SIP: Core SIP Technology Enhancements feature, the *user=phone* parameter formerly required in a SIP URL is no longer necessary. However, if an incoming SIP message has a SIP URL with *user=phone*, *user=phone* is parsed and used in the subsequent messages of the transaction.

303 and 411 SIP Cause Codes

The SIP: Core SIP Technology Enhancements feature obsoletes the SIP cause codes 303 *Redirection: See Other* and 411 *Client Error: Length required*.

Flexibility of Content-Type Header

The SIP: Core SIP Technology Enhancements feature allows the Content-Type header, which specifies the media type of the message body, to have an empty Session Description Protocol (SDP) body.

Optional SDP s= Line

The SIP: Core SIP Technology Enhancements feature accepts the "s=" line in SDP as optional. The "s=" line describes the reason or subject for SDP information. Cisco SIP gateways can create messages with an "s=" line in SDP bodies and can accept messages that have no "s=" line.

Allow Header Addition to INVITEs and 2xx Responses

The SIP: Core SIP Technology Enhancements feature enables the use of the Allow header in an initial or re-INVITE request or in any 2xx class response to an INVITE. The Allow header lists the set of methods supported by the user agent that is generating the message. Because it advertises what methods should be invoked on the user agent sending the message, it avoids congesting the message traffic unnecessarily. The Allow header can contain any or all of the following: INVITE, OPTIONS, BYE, CANCEL, ACK, PRACK, COMET, REFER, NOTIFY, INFO, SUBSCRIBE.

- [Finding Feature Information, page 5](#)
- [Simultaneous Cancel and 2xx Class Response, page 6](#)
- [Prerequisites for SIP Core SIP Technology Enhancements, page 6](#)
- [Restrictions for SIP Core SIP Technology Enhancements, page 6](#)
- [How to Configure SIP Core SIP Technology Enhancements, page 6](#)
- [Configuration Examples for SIP Core SIP Technology Enhancements, page 13](#)
- [Feature Information for SIP Core SIP Technology Enhancements, page 14](#)

Finding Feature Information

Your software release may not support all the features documented in this module. For the latest feature information and caveats, see the release notes for your platform and software release. To find information about the features documented in this module, and to see a list of the releases in which each feature is supported, see the Feature Information Table at the end of this document.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Simultaneous Cancel and 2xx Class Response

According to RFC 2543-bis-04, if the UAC desires to end the call before a response is received to an INVITE, the UAC sends a CANCEL. However, if the CANCEL and a 2xx class response to the INVITE "pass on the wire", the UAC also receives a 2xx to the INVITE. The SIP: Core SIP Technology Enhancements feature ensures that when the two messages pass, the UAC terminate the call by sending a BYE request.

Prerequisites for SIP Core SIP Technology Enhancements

- Ensure that your Cisco router has the minimum memory requirements necessary for voice capabilities.
- Establish a working IP network.
- Configure VoIP.

Cisco Unified Border Element

- Cisco IOS Release 12.2(13)T or a later release must be installed and running on your Cisco Unified Border Element.

Cisco Unified Border Element (Enterprise)

- Cisco IOS XE Release 2.5 or a later release must be installed and running on your Cisco ASR 1000 Series Router.

Restrictions for SIP Core SIP Technology Enhancements

- Via handling for TCP was not implemented in the Cisco SIP: Core SIP Technology Enhancements feature.

How to Configure SIP Core SIP Technology Enhancements

The SIP: Core SIP Technology Enhancements features are all enabled by default, and no special configurations is necessary. However, several of these features can be monitored through the use of various commands. See the following sections for monitoring tasks for the SIP: Core SIP Technology Enhancements feature. Each task in the list is optional:

- [Monitoring 487 Sent for BYE Requests, page 7](#)
- [Monitoring 3xx Redirection Responses, page 8](#)
- [Monitoring the Deletion of 303 and 411 Cause Codes, page 10](#)
- [Examples, page 10](#)
- [show sip-ua statistics Command, page 11](#)
- [show sip-ua map, page 12](#)

Monitoring 487 Sent for BYE Requests

When a UAS responds with a 487 after receiving a BYE request, the *Client Error: Request Cancelled* counter increments in the **show sip-ua statistics** command.

SUMMARY STEPS

1. enable
2. show sip-ua statistics

DETAILED STEPS

Command or Action	Purpose
Step 1 enable Example: Router> enable	Enables such as privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2 show sip-ua statistics Example: Router# show sip-ua statistics	(Optional) Displays response, traffic, and retry statistics for the SIP user agent (UA).

Example

The following sample output from the **show sip-ua statistics** command with the *Client Error: Request Cancelled* counter incremented:

```
Router# show sip-ua statistics
SIP Response Statistics (Inbound/Outbound)
  Informational:
    Trying 0/0, Ringing 0/0,
    Forwarded 0/0, Queued 0/0,
    SessionProgress 0/0
  Success:
    OkInvite 0/0, OkBye 0/0,
    OkCancel 0/0, OkOptions 0/0,
    OkPrack 0/0, OkPreconditionMet 0/0,
    OKSubscribe 0/0, OkNotify 0/0,
    202Accepted 0/0
  Redirection (Inbound only):
    MultipleChoice 0, MovedPermanently 0,
    MovedTemporarily 0, UseProxy 0,
    AlternateService 0
  Client Error:
    BadRequest 0/0, Unauthorized 0/0,
    PaymentRequired 0/0, Forbidden 0/0,
    NotFound 0/0, MethodNotAllowed 0/0,
    NotAcceptable 0/0, ProxyAuthReqd 0/0,
    ReqTimeout 0/0, Conflict 0/0, Gone 0/0,
    ReqEntityTooLarge 0/0, ReqURITooLarge 0/0,
    UnsupportedMediaType 0/0, BadExtension 0/0,
    TempNotAvailable 0/0, CallLegNonExistent 0/0,
    LoopDetected 0/0, TooManyHops 0/0,
    AddrIncomplete 0/0, Ambiguous 0/0,
    BusyHere 0/0, RequestCancel 0/1
```

```

    NotAcceptableMedia 0/0, BadEvent 0/0
  Server Error:
    InternalError 0/0, NotImplemented 0/0,
    BadGateway 0/0, ServiceUnavail 0/0,
    GatewayTimeout 0/0, BadSipVer 0/0,
    PreCondFailure 0/0
  Global Failure:
    BusyEverywhere 0/0, Decline 0/0,
    NotExistAnywhere 0/0, NotAcceptable 0/0
SIP Total Traffic Statistics (Inbound/Outbound)
  Invite 0/0, Ack 0/0, Bye 0/0,
  Cancel 0/0, Options 0/0,
  Prack 0/0, Comet 0/0,
  Subscribe 0/0, Notify 0/0,
  Refer 0/0
  Retry Statistics
    Invite 0, Bye 0, Cancel 0, Response 0,
    Prack 0, Comet 0, Reliablelxx 0, Notify 0
SDP application statistics:
  Parses: 0, Builds 0
  Invalid token order: 0, Invalid param: 0
  Not SDP desc: 0, No resource: 0

```

Monitoring 3xx Redirection Responses

The processing for 3xx redirection responses was updated in the SIP: Core SIP Technology Enhancements feature. The new implementation can be monitored with the **debug ccsip messages** command.

SUMMARY STEPS

1. **enable**
2. **debug ccsip message**

DETAILED STEPS

Command or Action	Purpose
Step 1 enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2 debug ccsip message Example: Router# debug ccsip message	Displays all SIP Service Provider Interface (SPI) message tracing. <ul style="list-style-type: none"> • Use this command to enable traces for SIP messages exchanged between the SIP user agent client (UAC) and the access server.

Example

The following is **debug ccsip message** output from an originating gateway. The output shows message transactions including the new INVITE message for the redirected address. The output has been updated as follows:

- The URI of the redirected INVITE is updated to contain new contact information provided by the 3xx redirect message.

- The transmitted CSeq number found in the CSeq header is increased by one. The new INVITE includes the updated CSeq.
- The To, From, and Call ID headers that identify the call leg remain the same.
- The UAC retries the request at the new address given by the 3xx Contact header field.

```

Sent:
INVITE sip:3111100@64.102.17.80:5060; SIP/2.0
Via: SIP/2.0/UDP 172.18.193.98:5060
From: "36601" <sip:36601@172.18.193.98> //This header remains consistent throughout the
call.
To: <sip:3111100@64.102.17.80> //This header remains consistent throughout the call.
Date: Mon, 01 Mar 2002 00:50:50 GMT
Call-ID: A22F0DC8-14F511CC-80329792-19DC655A@172.18.193.98 // Header remains consistent.
Cisco-Guid: 2682312529-351605196-2150668178-433874266
User-Agent: Cisco-SIPGateway/IOS-12.x
CSeq: 101 INVITE
Max-Forwards: 6
Timestamp: 730947050
Contact: <sip:36601@172.18.193.98:5060>
Expires: 180
Content-Type: application/sdp
Content-Length: 160
v=0
o=CiscoSystemsSIP-GW-UserAgent 2378 4662 IN IP4 172.18.193.98
s=SIP Call
c=IN IP4 172.18.193.98
t=0 0
m=audio 19202 RTP/AVP 18
a=rtpmap:18 G729/8000
Received:
SIP/2.0 302 Moved Temporarily
Via: SIP/2.0/UDP 172.18.193.98:5060
From: "36601" <sip:36601@172.18.193.98> //This header remains consistent throughout the
call.
To: <sip:3111100@64.102.17.80> //This header remains consistent throughout the call.
Date: Mon, 01 Mar 2002 00:50:50 GMT
Call-ID: A22F0DC8-14F511CC-80329792-19DC655A@172.18.193.98 //Header remains consistent.
Cisco-Guid: 2682312529-351605196-2150668178-433874266
User-Agent: Cisco-SIPGateway/IOS-12.x
CSeq: 101 INVITE
Contact: Anonymous <sip:36602@172.18.193.120 //Provides Request URI with the new contact
address.
Contact: Anonymous <sip:36601@172.18.193.98>
Sent:
ACK sip:3111100@64.102.17.80:5060; SIP/2.0
Via: SIP/2.0/UDP 172.18.193.98:5060
From: "36601" <sip:36601@172.18.193.98> //This header remains consistent throughout the
call.
To: <sip:3111100@64.102.17.80> //This header remains consistent throughout the call.
Date: Mon, 01 Mar 2002 00:50:50 GMT
Call-ID: A22F0DC8-14F511CC-80329792-19DC655A@172.18.193.98 // Header remains consistent.
Max-Forwards: 6
Content-Length: 0
CSeq: 101 ACK
Sent:
INVITE sip:36602@172.18.193.120:5060 SIP/2.0 //URI updated with new contact/redirect
address.
Via: SIP/2.0/UDP 172.18.193.98:5060
From: "36601" <sip:36601@172.18.193.98> //This header remains consistent throughout the
call.
To: <sip:3111100@64.102.17.80> //This header remains consistent throughout the call.
Date: Mon, 01 Mar 2002 00:50:50 GMT
Call-ID: A22F0DC8-14F511CC-80329792-19DC655A@172.18.193.98 // Header remains consistent.
Cisco-Guid: 2682312529-351605196-2150668178-433874266
User-Agent: Cisco-SIPGateway/IOS-12.x
CSeq: 102 INVITE //Transmitted CSeq is increased by one.
Max-Forwards: 6
Timestamp: 730947050
Contact: <sip:36601@172.18.193.98:5060>
Expires: 180
Content-Type: application/sdp

```

```

Content-Length: 159
v=0
o=CiscoSystemsSIP-GW-UserAgent 5957 524 IN IP4 172.18.193.98
s=SIP Call
c=IN IP4 172.18.193.98
t=0 0
m=audio 17018 RTP/AVP 18
a=rtpmap:18 G729/8000

```

Monitoring the Deletion of 303 and 411 Cause Codes

The processing for Monitoring the Deletion of 303 and 411 Cause Codes was updated in the SIP: Core SIP Technology Enhancements feature. The new implementation can be monitored with the **show sip-ua statistics** and **show sip-ua map** commands.

SUMMARY STEPS

1. **enable**
2. **show sip-ua statistics**
3. **show sip-ua map**

DETAILED STEPS

	Command or Action	Purpose
Step 1	enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2	show sip-ua statistics Example: Router# show sip-ua statistics	Displays response, traffic, and retry statistics for the SIP UA. <ul style="list-style-type: none"> • Can be used to verify the deletion of the 303 and 411 cause codes.
Step 3	show sip-ua map Example: Router# show sip-ua map	Displays the mapping table of PSTN cause codes and their corresponding SIP error status codes or the mapping table of SIP-to-PSTN codes. <ul style="list-style-type: none"> • Can be used to verify the deletion of 411 cause codes.

Examples

The following examples provide different ways to monitor the deletion of the 303 and 411 cause codes.

- [show sip-ua statistics Command, page 11 command](#)
- [show sip-ua map, page 12 command](#)

show sip-ua statistics Command

The following is sample output of the **show sip-ua statistics** command that includes the *SeeOther* (303) and *LengthRequired* (411) fields is from the Cisco IOS version before the SIP: Core SIP Technology Enhancements feature:

```
Router# show sip-ua statistics
SIP Response Statistics (Inbound/Outbound)
  Informational:
    Trying 0/4, Ringing 0/0,
    Forwarded 0/0, Queued 0/0,
    SessionProgress 0/5
  Success:
    OkInvite 0/2, OkBye 1/1,
    OkCancel 0/2, OkOptions 0/0,
    OkPrack 0/0, OkPreconditionMet 0/0,
    OkNotify 0/0, 202Accepted 0/0
  Redirection (Inbound only):
    MultipleChoice 0, MovedPermanently 0,
MovedTemporarily 0, SeeOther 0,
    UseProxy 0, AlternateService 0
  Client Error:
    BadRequest 0/0, Unauthorized 0/0,
    PaymentRequired 0/0, Forbidden 0/0,
    NotFound 0/0, MethodNotAllowed 0/0,
    NotAcceptable 0/0, ProxyAuthReqd 0/0,
    ReqTimeout 0/0, Conflict 0/0, Gone 0/0,
    LengthRequired 0/0, ReqEntityTooLarge 0/0,
    ReqURITooLarge 0/0, UnsupportedMediaType 0/0,
    BadExtension 0/0, TempNotAvailable 0/0,
    CallLegNonExistent 0/0, LoopDetected 0/0,
    TooManyHops 0/0, AddrIncomplete 0/0,
    Ambiguous 0/0, BusyHere 0/0
    RequestCancel 0/2, NotAcceptableMedia 0/0
  Server Error:
    InternalError 0/0, NotImplemented 0/0,
    BadGateway 0/0, ServiceUnavail 0/0,
    GatewayTimeout 0/0, BadSipVer 0/0,
    PreCondFailure 0/0
  Global Failure:
    BusyEverywhere 0/0, Decline 0/0,
    NotExistAnywhere 0/0, NotAcceptable 0/0
SIP Total Traffic Statistics (Inbound/Outbound)
  Invite 5/0, Ack 4/0, Bye 1/1,
  Cancel 2/0, Options 0/0,
  Prack 0/0, Comet 0/0,
  Notify 0/0, Refer 0/0
Retry Statistics
  Invite 0, Bye 0, Cancel 0, Response 0,
  Prack 0, Comet 0, Reliablelxx 0, Notify 0
```

The following is sample output of the **show sip-ua statistics** command from a Cisco IOS version after implementing the SIP: Core SIP Technology Enhancements feature and shows that the *SeeOther* and *LengthRequired* fields are now omitted is from fields:

```
Router# show sip-ua statistics
SIP Response Statistics (Inbound/Outbound)
  Informational:
    Trying 0/0, Ringing 0/0,
    Forwarded 0/0, Queued 0/0,
    SessionProgress 0/0
  Success:
    OkInvite 0/0, OkBye 0/0,
    OkCancel 0/0, OkOptions 0/0,
    OkPrack 0/0, OkPreconditionMet 0/0,
    OKSubscribe 0/0, OkNotify 0/0,
    202Accepted 0/0
  Redirection (Inbound only):
```

```

    MultipleChoice 0, MovedPermanently 0,
    MovedTemporarily 0, UseProxy 0,
    AlternateService 0
Client Error:
    BadRequest 0/0, Unauthorized 0/0,
    PaymentRequired 0/0, Forbidden 0/0,
    NotFound 0/0, MethodNotAllowed 0/0,
    NotAcceptable 0/0, ProxyAuthReqd 0/0,
    ReqTimeout 0/0, Conflict 0/0, Gone 0/0,
    ReqEntityTooLarge 0/0, ReqURITooLarge 0/0,
    UnsupportedMediaType 0/0, BadExtension 0/0,
    TempNotAvailable 0/0, CallLegNonExistent 0/0,
    LoopDetected 0/0, TooManyHops 0/0,
AddrIncomplete 0/0, Ambiguous 0/0,
    BusyHere 0/0, RequestCancel 0/0
    NotAcceptableMedia 0/0, BadEvent 0/0
Server Error:
    InternalError 0/0, NotImplemented 0/0,
    BadGateway 0/0, ServiceUnavail 0/0,
    GatewayTimeout 0/0, BadSipVer 0/0,
    PreCondFailure 0/0
Global Failure:
    BusyEverywhere 0/0, Decline 0/0,
    NotExistAnywhere 0/0, NotAcceptable 0/0
SIP Total Traffic Statistics (Inbound/Outbound)
    Invite 0/0, Ack 0/0, Bye 0/0,
    Cancel 0/0, Options 0/0,
    Prack 0/0, Comet 0/0,
    Subscribe 0/0, Notify 0/0,
    Refer 0/0
Retry Statistics
    Invite 0, Bye 0, Cancel 0, Response 0,
    Prack 0, Comet 0, Reliablelxx 0, Notify 0
SDP application statistics:
    Parses: 0, Builds 0
    Invalid token order: 0, Invalid param: 0
    Not SDP desc: 0, No resource: 0

```

show sip-ua map

The following example is sample output from the **show sip-ua map** command and shows that SIP cause code 411 is omitted from the group of cause codes.

```

Router# show sip-ua map sip-pstn
SIP-Status   Configured   Default
             PSTN-Cause   PSTN-Cause
400          127         127
401          57         57
402          21         21
403          57         57
404          1          1
405          127        127
406          127        127
407          21         21
408          102        102
409          41         41
410          1          1
413          127        127
414          127        127
415          79         79
420          127        127
480          18         18
481          127        127
482          127        127
483          127        1

```

Configuration Examples for SIP Core SIP Technology Enhancements

This section provides a general SIP configuration example:

- [SIP Core SIP Technology Enhancements Example, page 13](#)
- [SIP Core SIP Technology Enhancements Example, page 13](#)

SIP Core SIP Technology Enhancements Example

This example contains output from the **show running-config** command.

```
Router# show running-config
Building configuration...
Current configuration : 2791 bytes
!
version 12.2
service config
no service single-slot-reload-enable
no service pad
service timestamps debug uptime
service timestamps log uptime
no service password-encryption
service internal
service udp-small-servers
!
interface FastEthernet2/0
ip address 172.18.200.24 255.255.255.0
duplex auto
no shut
speed 10
ip rsvp bandwidth 7500 7500
!
voice-port 1/1/1
no supervisory disconnect lcfo
!
dial-peer voice 1 pots
application session
destination-pattern 5550111
port 1/1/1
!
dial-peer voice 3 voip
application session
destination-pattern 5550112
session protocol sipv2
session target ipv4:172.18.200.36
codec g711ulaw
!
dial-peer voice 4 voip
application session
destination-pattern 5550133
session protocol sipv2
session target ipv4:172.18.200.33
codec g711ulaw
!
gateway
!
sip-ua
  retry invite 1
  retry bye 1
!
line con 0
line aux 0
line vty 0 4
```

```
login
!
end
```

Feature Information for SIP Core SIP Technology Enhancements

The following table provides release information about the feature or features described in this module. This table lists only the software release that introduced support for a given feature in a given software release train. Unless noted otherwise, subsequent releases of that software release train also support that feature.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

ISR Feature History Information.

Table 2 Feature Information for SIP: Core SIP Technology Enhancements

Feature Name	Releases	Feature Information
SIP: Core SIP Technology Enhancements	12.2(13)T 12.2(15)T	Compliance to RFC 2543-bis-04 adds enhanced SIP support and ensures smooth interoperability and compatibility with multiple vendors. The following commands were modified: debug ccsip messages , show sip-ua map , show sip-ua statistics ,and.

ASR Feature History Information.

Table 3 Feature Information for SIP: Core SIP Technology Enhancements

Feature Name	Releases	Feature Information
SIP: Core SIP Technology Enhancements	Cisco IOS XE Release 2.5	Compliance to RFC 2543-bis-04 adds enhanced SIP support and ensures smooth interoperability and compatibility with multiple vendors. The following commands were modified: debug ccsip messages , show sip-ua map , show sip-ua statistics ,and.

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: www.cisco.com/go/trademarks. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.



Reporting End-of-Call Statistics in SIP BYE Message

The Reporting End-of-Call Statistics in Session Initiation Protocol (SIP) BYE Message feature enables you to send call statistics to a remote end when a call terminates. The call statistics are sent as a new header in the BYE message or in the 200 OK message (response to BYE message). The statistics include Real-time Transport Protocol (RTP) packets sent or received, total bytes sent or received, total number of packets that are lost, delay jitter, round-trip delay, and call duration.

This feature enables Cisco Unified Border Element (Cisco UBE) to use the call statistics to update the call data records in Cisco Unified Communications Manager (Cisco UCM) or Cisco Unified Communications Manager Express (Cisco UCME).

The Support for Reporting End-of-Call Statistics in SIP BYE Message feature is enabled by default on Cisco UBE.

A new header P-RTP-Stat is added to the BYE and 200 OK messages. The format of P-RTP-Stat is as follows:

P-RTP-Stat: PS=<Packets Sent>, OS=<Octets Sent>, PR=<Packets Recd>, OR=<Octets Recd>, PL=<Packets Lost>, JI=<Jitter>, LA=<Round Trip Delay in ms>, DU=<Call Duration in seconds>

The table below describes the P-RTP-Stat header.

Table 4 P-RTP-Stat Header Fields

Field	Description	Range of Values
PS	Packets Sent	0 to 4294967295
OS	Octets Sent	0 to 4294967295
PR	Packets Received	0 to 4294967295
OR	Octets Received	0 to 4294967295
PL	Packets Lost	0 to 4294967295
JI	Jitter	0 to 4294967295
LA	Round Trip Delay, in milliseconds (ms)	-2147483648 to +2147483647
DU	Call Duration, in seconds	0 to 4294967295

- [Finding Feature Information, page 18](#)

- [Prerequisites for Reporting End-of-Call Statistics in SIP BYE Message, page 18](#)
- [Restrictions for Reporting End-of-Call Statistics in SIP BYE Message, page 18](#)
- [Disabling Reporting End-of-Call Statistics in SIP BYE Message, page 19](#)
- [Feature Information for Reporting End-of-Call Statistics in SIP BYE Message, page 23](#)

Finding Feature Information

Your software release may not support all the features documented in this module. For the latest feature information and caveats, see the release notes for your platform and software release. To find information about the features documented in this module, and to see a list of the releases in which each feature is supported, see the Feature Information Table at the end of this document.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Prerequisites for Reporting End-of-Call Statistics in SIP BYE Message

Cisco Unified Border Element

- Cisco IOS Release 15.1(3)T or a later release must be installed and running on your Cisco Unified Border Element.

Cisco Unified Border Element (Enterprise)

- Cisco IOS XE Release 3.3S or a later release must be installed and running on your Cisco ASR 1000 Series Router.

Restrictions for Reporting End-of-Call Statistics in SIP BYE Message

- If the **media flow-around** command is configured, the call statistics are not sent for a 200 OK message.
- If the **media flow-around** command is configured, the call statistics are passed through the Cisco UBE for a BYE message.
- The values are not validated when the incoming statistics are passed to the endpoints. Hence, in some cases the values may be invalid.
- The value of round-trip delay is valid only if the remote end supports Real-Time Control Protocol (RTCP).

Disabling Reporting End-of-Call Statistics in SIP BYE Message

The Support for Reporting End-of-Call Statistics in SIP BYE Message feature is enabled by default on the Cisco UBE. That is, the P-RTP-Stat header is added to the list of headers that can be processed through the SIP profiles. You must apply SIP profile rules to remove the header from the mandatory header list.

- [Defining SIP Profile Rules to Remove a Header, page 19](#)
- [Disabling Reporting End-of-Call Statistics in SIP BYE Message at the Global Level, page 20](#)
- [Disabling Reporting End-of-Call Statistics in SIP BYE Message at the Dial Peer Level, page 21](#)

Defining SIP Profile Rules to Remove a Header

Perform this task to define SIP profile rules to remove a header.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **voice class sip-profiles *tag***
4. **request bye sip-header p-rtp-stat remove**
5. **response 200 sip-header p-rtp-stat remove**
6. **exit**

DETAILED STEPS

Command or Action	Purpose
Step 1 enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2 configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3 voice class sip-profiles <i>tag</i> Example: Router(config)# voice class sip-profiles 100	Configures SIP profiles for a voice class and enters voice class configuration mode.

Command or Action	Purpose
Step 4 request bye sip-header p-rtp-stat remove Example: <pre>Router(config-class)# request bye sip-header p-rtp-stat remove</pre>	Removes the P-RTP-Stat SIP header from the BYE message.
Step 5 response 200 sip-header p-rtp-stat remove Example: <pre>Router(config-class)# response 200 sip-header p-rtp-stat remove</pre>	Removes the P-RTP-Stat SIP header from the 200 OK message.
Step 6 exit Example: <pre>Router(config-class)# exit</pre>	Exits voice class configuration mode.

Disabling Reporting End-of-Call Statistics in SIP BYE Message at the Global Level

Perform this task to disable the Support for Reporting End-of-Call Statistics in SIP BYE Message feature at the global level.

The Support for Reporting End-of-Call Statistics in SIP BYE Message feature is enabled by default on Cisco UBE. Hence, to disable the feature, you must modify the SIP profiles to remove the P-RTP-Stat SIP header from the request and the response messages and then configure the modified SIP profile on the Cisco UBE.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **voice service voip**
4. **sip**
5. **sip-profiles *tag***
6. **exit**

DETAILED STEPS

Command or Action	Purpose
Step 1 <code>enable</code> Example: <pre>Router> enable</pre>	Enables privileged EXEC mode. <ul style="list-style-type: none"> Enter your password if prompted.
Step 2 <code>configure terminal</code> Example: <pre>Router# configure terminal</pre>	Enters global configuration mode.
Step 3 <code>voice service voip</code> Example: <pre>Router(config)# voice service voip</pre>	Specifies VoIP as the voice encapsulation method and enters voice-service configuration mode.
Step 4 <code>sip</code> Example: <pre>Router(conf-voi-serv)# sip</pre>	Enters service SIP configuration mode.
Step 5 <code>sip-profiles tag</code> Example: <pre>Router(conf-serv-sip)# sip-profiles 100</pre>	Disables the Support for Reporting End-of-Call Statistics in SIP BYE Message feature at the global level.
Step 6 <code>exit</code> Example: <pre>Router(config-class)# exit</pre>	Exits service SIP configuration mode.

Disabling Reporting End-of-Call Statistics in SIP BYE Message at the Dial Peer Level

Perform this task to disable the Support for Reporting End-of-Call Statistics in SIP BYE Message feature at the dial peer level.

The Support for Reporting End-of-Call Statistics in SIP BYE Message feature is enabled by default. Hence, to disable the feature, you must modify the SIP profiles to remove the P-RTP-Stat SIP header from the request and the response messages and then configure the modified SIP profile on the Cisco UBE.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **dial-peer voice *tag* voip**
4. **voice-class sip profiles *tag***
5. **exit**

DETAILED STEPS

Command or Action	Purpose
Step 1 enable Example: <pre>Router> enable</pre>	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2 configure terminal Example: <pre>Router# configure terminal</pre>	Enters global configuration mode.
Step 3 dial-peer voice <i>tag</i> voip Example: <pre>Router(config)# dial-peer voice 100 voip</pre>	Defines a dial peer to specify the method of voice encapsulation and enters dial peer configuration mode.
Step 4 voice-class sip profiles <i>tag</i> Example: <pre>Router(config-dial-peer)# voice-class sip profiles 100</pre>	Disables the Support for Reporting End-of-Call Statistics in SIP BYE Message feature at the dial peer level.
Step 5 exit Example: <pre>Router(config-dial-peer)# exit</pre>	Exits dial-peer configuration mode.

Feature Information for Reporting End-of-Call Statistics in SIP BYE Message

The following table provides release information about the feature or features described in this module. This table lists only the software release that introduced support for a given feature in a given software release train. Unless noted otherwise, subsequent releases of that software release train also support that feature.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required. Feature History Table entry for the Cisco Unified Border Element.

Table 5 Feature Information for Reporting End-of-Call Statistics in SIP BYE Message

Feature Name	Releases	Feature Information
Reporting End-of-Call Statistics in SIP BYE Message	15.1(3)T	Allows users to send call statistics to remote ends when a call terminates. These statistics are sent as a new header in a BYE message or in the 200 OK message. The following commands were introduced or modified: request , response .

Feature History Table entry for the Cisco Unified Border Element (Enterprise) .

Table 6 Feature Information for Reporting End-of-Call Statistics in SIP BYE Message

Feature Name	Releases	Feature Information
Reporting End-of-Call Statistics in SIP BYE Message	Cisco IOS XE Release 3.3S	Allows users to send call statistics to remote ends when a call terminates. These statistics are sent as a new header in a BYE message or in the 200 OK message. The following commands were introduced or modified: request , response .

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: www.cisco.com/go/trademarks. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.



Configurable Hostname in Locally Generated SIP Headers

This feature allows you to configure the hostname for use in locally generated SIP headers in either of two configuration modes.

- [Finding Feature Information, page 25](#)
- [Prerequisites for Configurable Hostname in Locally Generated SIP Headers, page 25](#)
- [Restrictions for Configurable Hostname in Locally Generated SIP Headers, page 26](#)
- [How to Configure the Hostname in Locally Generated SIP Headers, page 26](#)
- [Feature Information for Configurable Hostname in Locally Generated SIP Headers, page 34](#)

Finding Feature Information

Your software release may not support all the features documented in this module. For the latest feature information and caveats, see the release notes for your platform and software release. To find information about the features documented in this module, and to see a list of the releases in which each feature is supported, see the Feature Information Table at the end of this document.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Prerequisites for Configurable Hostname in Locally Generated SIP Headers

Cisco Unified Border Element

- Cisco IOS Release 12.4(2)T or a later release must be installed and running on your Cisco Unified Border Element.

Cisco Unified Border Element (Enterprise)

- Cisco IOS XE Release 2.5 or a later release must be installed and running on your Cisco ASR 1000 Series Router.

Restrictions for Configurable Hostname in Locally Generated SIP Headers

- Dial-peer-specific configuration takes precedence over more general gateway-wide configuration.

How to Configure the Hostname in Locally Generated SIP Headers

- [Configuring Hostname in Locally Generated SIP Headers at the Global Level](#), page 26
- [Configuring Hostname in Locally Generated SIP Headers at the Dial-Peer-Specific Level](#), page 27
- [Verifying the Hostname in Locally Generated SIP Headers](#), page 29

Configuring Hostname in Locally Generated SIP Headers at the Global Level

To configure the local hostname in global configuration mode for use in locally generated URLs, complete the task in this section.



Note

Dial-peer-specific configuration takes precedence over more general gateway-wide configuration.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **voice service voip**
4. **sip**
5. **localhost dns:** *local-host-name-string*
6. **exit**

DETAILED STEPS

	Command or Action	Purpose
Step 1	enable	Enables privileged EXEC mode.
	Example:	<ul style="list-style-type: none"> • Enter your password if prompted.
	Router> enable	

Command or Action	Purpose
<p>Step 2 <code>configure terminal</code></p> <p>Example:</p> <pre>Router# configure terminal</pre>	Enters global configuration mode.
<p>Step 3 <code>voice service voip</code></p> <p>Example:</p> <pre>Router(config)# voice service voip</pre>	(Required) Enters the voice-service VoIP configuration mode
<p>Step 4 <code>sip</code></p> <p>Example:</p> <pre>Router(config-voi-serv)# sip</pre>	(Required) Enters the SIP configuration mode.
<p>Step 5 <code>localhost dns: local-host-name-string</code></p> <p>Example:</p> <pre>Router(conf-serv-sip)# localhost dns:host_one</pre>	<p>(Optional) Globally configures the gateway to substitute a DNS hostname or domain as the localhost name in place of the physical IP address in the From, Call-ID, and Remote-Party-ID headers in outgoing messages:</p> <ul style="list-style-type: none"> • dns: <i>local-host-name-string</i> --Alphanumeric value representing the DNS domain (consisting of the domain name with or without a specific hostname) in place of the physical IP address that is used in the host portion of the From, Call-ID, and Remote-Party-ID headers in outgoing messages. • This value can be the hostname and the domain separated by a period (dns: <i>hostname.domain</i>) or just the domain name (dns: <i>domain</i>). In both case, the dns: delimiter must be included as the first four characters.
<p>Step 6 <code>exit</code></p> <p>Example:</p> <pre>Router(conf-serv-sip)# exit</pre>	Exits the current configuration mode.

Configuring Hostname in Locally Generated SIP Headers at the Dial-Peer-Specific Level

To configure the local hostname in dial-peer-specific configuration mode for use in locally generated URLs, complete the task in this section.



Note This configuration takes precedence over global configuration.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **dial-peer voice tag voip**
4. **voice-class sip localhost dns: [hostname .]domain [preferred]**
5. **exit**

DETAILED STEPS

Command or Action	Purpose
<p>Step 1 enable</p> <p>Example:</p> <pre>Router> enable</pre>	<p>Enables privileged EXEC mode.</p> <ul style="list-style-type: none"> • Enter your password if prompted.
<p>Step 2 configure terminal</p> <p>Example:</p> <pre>Router# configure terminal</pre>	<p>Enters global configuration mode.</p>
<p>Step 3 dial-peer voice tag voip</p> <p>Example:</p> <pre>Router# dial-peer voice 100 voip</pre>	<p>(Required) Enters dial-peer configuration mode for the specified dial peer.</p>
<p>Step 4 voice-class sip localhost dns: [hostname .]domain [preferred]</p> <p>Example:</p> <pre>Router(config-dial-peer)# voice-class sip localhost dns:example.com</pre>	<p>(Optional) Configures individual dial peers to override global settings on the gateway and substitute a DNS hostname or domain as the localhost name in place of the physical IP address in the From, Call-ID, and Remote-Party-ID headers in outgoing messages:</p> <ul style="list-style-type: none"> • dns: <i>local-host-name-string</i> --Alphanumeric value representing the DNS domain (consisting of the domain name with or without a specific hostname) in place of the physical IP address that is used in the host portion of the From, Call-ID, and Remote-Party-ID headers in outgoing messages. • This value can be the hostname and the domain separated by a period (dns: <i>hostname.domain</i>) or just the domain name (dns: <i>domain</i>). In both case, the dns: delimiter must be included as the first four characters.

Command or Action	Purpose
Step 5 <code>exit</code> Example: <code>Router(config-dial-peer)# exit</code>	Exits the current configuration mode.

Verifying the Hostname in Locally Generated SIP Headers

To verify the hostname in locally generated SIP headers for global or dial-peer-specific configuration, use the following **show** commands:

- **show call active voice**
- **show call history voice**

SUMMARY STEPS

1. Use the **show call active voice** command to display output when the local hostname is enabled:
2. Use the **show call history voice** to display output when the local hostname is enabled:

DETAILED STEPS

Step 1 Use the **show call active voice** command to display output when the local hostname is enabled:

Example:

```
Router# show call active voice
Telephony call-legs:1
SIP call-legs:1
H323 call-legs:0
Call agent controlled call-legs:0
Multicast call-legs:0
Total call-legs:2
  GENERIC:
SetupTime=126640 ms
Index=1
PeerAddress=9001
PeerSubAddress=
PeerId=100
PeerIfIndex=6
LogicalIfIndex=4
ConnectTime=130300 ms
CallDuration=00:00:47 sec
CallState=4
CallOrigin=2
ChargedUnits=0
InfoType=speech
TransmitPackets=2431
TransmitBytes=48620
ReceivePackets=2431
ReceiveBytes=48620
TELE:
ConnectionId=[0xA0DC41CF 0x115511D9 0x8002EC82 0xAB4FD5BE]
IncomingConnectionId=[0xA0DC41CF 0x115511D9 0x8002EC82 0xAB4FD5BE]
CallID=1
TxDuration=48620 ms
```

```

VoiceTxDuration=48620 ms
FaxTxDuration=0 ms
CoderTypeRate=g729r8
NoiseLevel=-61
ACOMLevel=3
OutSignalLevel=-35
InSignalLevel=-30
InfoActivity=2
ERLLevel=3
SessionTarget=
ImgPages=0
CallerName=
CallerIDBlocked=False
OriginalCallingNumber=
OriginalCallingOctet=0x0
OriginalCalledNumber=
OriginalCalledOctet=0x80
OriginalRedirectCalledNumber=
OriginalRedirectCalledOctet=0x0
TranslatedCallingNumber=9001
TranslatedCallingOctet=0x0
TranslatedCalledNumber=
TranslatedCalledOctet=0x80
TranslatedRedirectCalledNumber=
TranslatedRedirectCalledOctet=0x0
GwCollectedCalledNumber=9002
GENERIC:
SetupTime=128980 ms
Index=1
PeerAddress=9002
PeerSubAddress=
PeerId=3301
PeerIfIndex=7
LogicalIfIndex=0
ConnectTime=130300 ms
CallDuration=00:00:50 sec
CallState=4
CallOrigin=1
ChargedUnits=0
InfoType=speech
TransmitPackets=2587
TransmitBytes=51740
ReceivePackets=2587
ReceiveBytes=51740
VOIP:
ConnectionId[0xA0DC41CF 0x115511D9 0x8002EC82 0xAB4FD5BE]
IncomingConnectionId[0xA0DC41CF 0x115511D9 0x8002EC82 0xAB4FD5BE]
CallID=2
RemoteIPAddress=172.18.193.87
RemoteUDPPort=17602
RemoteSignallingIPAddress=172.18.193.87
RemoteSignallingPort=5060
RemoteMediaIPAddress=172.18.193.87
RemoteMediaPort=17602
RoundTripDelay=2 ms
SelectedQoS=best-effort
tx_DtmfRelay=inband-voice
FastConnect=FALSE
AnnexE=FALSE
Separate H245 Connection=FALSE
H245 Tunneling=FALSE
SessionProtocol=sipv2
ProtocolCallId=A240B4DC-115511D9-8005EC82-AB4FD5BE@pip.example.com
SessionTarget=172.18.193.87
OnTimeRvPayout=48620
GapFillWithSilence=0 ms
GapFillWithPrediction=0 ms
GapFillWithInterpolation=0 ms
GapFillWithRedundancy=0 ms
HiWaterPayoutDelay=70 ms
LoWaterPayoutDelay=69 ms
TxPakNumber=2434

```



```
TxSignalPak=0
TxComfortNoisePak=0
TxDuration=48680
TxVoiceDuration=48680
RxPakNumber=2434
RxSignalPak=0
RxDuration=0
TxVoiceDuration=48670
VoiceRxDuration=48620
RxOutOfSeq=0
RxLatePak=0
RxEarlyPak=0
PlayDelayCurrent=69
PlayDelayMin=69
PlayDelayMax=70
PlayDelayClockOffset=43547
PlayDelayJitter=0
PlayErrPredictive=0
PlayErrInterpolative=0
PlayErrSilence=0
PlayErrBufferOverflow=0
PlayErrRetroactive=0
PlayErrTalkspurt=0
OutSignalLevel=-35
InSignalLevel=-30
LevelTxPowerMean=0
LevelRxPowerMean=-302
LevelBgNoise=0
ERLLevel=3
ACOMLevel=3
ErrRxDrop=0
ErrTxDrop=0
ErrTxControl=0
ErrRxControl=0
ReceiveDelay=69 ms
LostPackets=0
EarlyPackets=0
LatePackets=0
SRTP = off
VAD = enabled
CoderTypeRate=g729r8
CodecBytes=20
Media Setting=flow-around
CallerName=
CallerIDBlocked=False
OriginalCallingNumber=9001
OriginalCallingOctet=0x0
OriginalCalledNumber=9002
OriginalCalledOctet=0x80
OriginalRedirectCalledNumber=
OriginalRedirectCalledOctet=0x0
TranslatedCallingNumber=9001
TranslatedCallingOctet=0x0
TranslatedCalledNumber=9002
TranslatedCalledOctet=0x80
TranslatedRedirectCalledNumber=
TranslatedRedirectCalledOctet=0x0
GwCollectedCalledNumber=9002
GwOutpulsedCalledNumber=9002
GwOutpulsedCalledOctet3=0x80
GwOutpulsedCallingNumber=9001
GwOutpulsedCallingOctet3=0x0
GwOutpulsedCallingOctet3a=0x0
MediaInactiveDetected=no
MediaInactiveTimestamp=
MediaControlReceived=
Username=
LocalHostname=pip.example.com ! LocalHostname field
Telephony call-legs:1
SIP call-legs:1
H323 call-legs:0
Call agent controlled call-legs:0
```

```
Multicast call-legs:0
Total call-legs:2
```

Step 2 Use the **show call history voice** to display output when the local hostname is enabled:

Example:

```
Router# show call history voice
Telephony call-legs:1
SIP call-legs:1
H323 call-legs:0
Call agent controlled call-legs:0
Total call-legs:2
GENERIC:
SetupTime=128980 ms
Index=1
PeerAddress=9002
PeerSubAddress=
PeerId=3301
PeerIfIndex=7
LogicalIfIndex=0
DisconnectCause=10
DisconnectText=normal call clearing (16)
ConnectTime=130300 ms
DisconnectTime=329120 ms
CallDuration=00:03:18 sec
CallOrigin=1
ReleaseSource=4
ChargedUnits=0
InfoType=speech
TransmitPackets=9981
TransmitBytes=199601
ReceivePackets=9987
ReceiveBytes=199692
VOIP:
ConnectionId[0xA0DC41CF 0x115511D9 0x8002EC82 0xAB4FD5BE]
IncomingConnectionId[0xA0DC41CF 0x115511D9 0x8002EC82 0xAB4FD5BE]
CallID=2
RemoteIPAddress=172.18.193.87
RemoteUDPPort=17602
RemoteSignallingIPAddress=172.18.193.87
RemoteSignallingPort=5060
RemoteMediaIPAddress=172.18.193.87
RemoteMediaPort=17602
SRTP = off
RoundTripDelay=1 ms
SelectedQoS=best-effort
tx_DtmfRelay=inband-voice
FastConnect=FALSE
AnnexE=FALSE
Separate H245 Connection=FALSE
H245 Tunneling=FALSE
SessionProtocol=sipv2
ProtocolCallId=A240B4DC-115511D9-8005EC82-AB4FD5BE@pip.example.com
SessionTarget=172.18.193.87
OnTimeRvPayout=195880
GapFillWithSilence=0 ms
GapFillWithPrediction=0 ms
GapFillWithInterpolation=0 ms
GapFillWithRedundancy=0 ms
HiWaterPayoutDelay=70 ms
LoWaterPayoutDelay=69 ms
ReceiveDelay=69 ms
LostPackets=0
EarlyPackets=0
LatePackets=0
VAD = enabled
CoderTypeRate=g729r8
CodecBytes=20
cvVoIPCallHistoryIcpif=2
```

```
MediaSetting=flow-around
CallerName=
CallerIDBlocked=False
OriginalCallingNumber=9001
OriginalCallingOctet=0x0
OriginalCalledNumber=9002
OriginalCalledOctet=0x80
OriginalRedirectCalledNumber=
OriginalRedirectCalledOctet=0x0
TranslatedCallingNumber=9001
TranslatedCallingOctet=0x0
TranslatedCalledNumber=9002
TranslatedCalledOctet=0x80
TranslatedRedirectCalledNumber=
TranslatedRedirectCalledOctet=0x0
GwCollectedCalledNumber=9002
GwOutpulsedCalledNumber=9002
GwOutpulsedCalledOctet3=0x80
GwOutpulsedCallingNumber=9001
GwOutpulsedCallingOctet3=0x0
GwOutpulsedCallingOctet3a=0x0
MediaInactiveDetected=no
MediaInactiveTimestamp=
MediaControlReceived=
LocalHostname=pip.example.com ! LocalHostname field
Username=
GENERIC:
SetupTime=126640 ms
Index=2
PeerAddress=9001
PeerSubAddress=
PeerId=100
PeerIfIndex=6
LogicalIfIndex=4
DisconnectCause=10
DisconnectText=normal call clearing (16)
ConnectTime=130300 ms
DisconnectTime=330080 ms
CallDuration=00:03:19 sec
CallOrigin=2
ReleaseSource=4
ChargedUnits=0
InfoType=speech
TransmitPackets=9987
TransmitBytes=199692
ReceivePackets=9981
ReceiveBytes=199601
TELE:
ConnectionId=[0xA0DC41CF 0x115511D9 0x8002EC82 0xAB4FD5BE]
IncomingConnectionId=[0xA0DC41CF 0x115511D9 0x8002EC82 0xAB4FD5BE]
CallID=1
TxDuration=195940 ms
VoiceTxDuration=195940 ms
FaxTxDuration=0 ms
CoderTypeRate=g729r8
NoiseLevel=-73
ACOMLevel=4
SessionTarget=
ImgPages=0
CallerName=
CallerIDBlocked=False
OriginalCallingNumber=
OriginalCallingOctet=0x0
OriginalCalledNumber=
OriginalCalledOctet=0x80
OriginalRedirectCalledNumber=
OriginalRedirectCalledOctet=0x0
TranslatedCallingNumber=9001
TranslatedCallingOctet=0x0
TranslatedCalledNumber=
TranslatedCalledOctet=0x80
TranslatedRedirectCalledNumber=
```

```
TranslatedRedirectCalledOctet=0x0
GwCollectedCalledNumber=9002
```

Feature Information for Configurable Hostname in Locally Generated SIP Headers

The following table provides release information about the feature or features described in this module. This table lists only the software release that introduced support for a given feature in a given software release train. Unless noted otherwise, subsequent releases of that software release train also support that feature.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

ISR Feature History Information.

Table 7 Feature Information for Configurable Hostname in Locally Generated SIP Headers

Feature Name	Releases	Feature Information
Configurable Hostname in Locally Generated SIP Header	12.4(2)T	This feature allows you to configure the hostname in locally generated SIP headers in global and dial-peer-specific configuration modes. The following commands were introduced or modified: localhost dns and voice-class sip localhost dns

ASR Feature History Information.

Table 8 Feature Information for Configurable Hostname in Locally Generated SIP Headers

Feature Name	Releases	Feature Information
Configurable Hostname in Locally Generated SIP Header	Cisco IOS XE Release 2.5	This feature allows you to configure the hostname in locally generated SIP headers in global and dial-peer-specific configuration modes. The following commands were introduced or modified: localhost dns and voice-class sip localhost dns

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: www.cisco.com/go/trademarks. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.



SIP Parameter Modification

Cisco Unified Border Element

- Cisco IOS Release 12.4(15)XZ or a later release must be installed and running on your Cisco Unified Border Element.

Cisco Unified Border Element (Enterprise)

- Cisco IOS XE Release 2.5 or a later release must be installed and running on your Cisco ASR 1000 Series Router.



Note

- This feature applies to outgoing SIP messages.
- This feature is disabled by default.
- Removal of mandatory headers is not supported.
- This feature allows removal of entire MIME bodies from SIP messages. Addition of MIME bodies is not supported.

The SIP Parameter modification feature allow customers to add, remove, or modify the SIP parameters in the SIP messages going out of a border element. The SIP message is generated from the standard signaling stack, but runs the message through a parser which can add, delete or modify specific parameters. This allows interoperability with additional third party devices that require specific SIP message formats. All SIP methods and responses are supported, profiles can be added either in dial-peer level or global level. Basic Regular Expression support would be provided for modification of header values. SDP parameters can also be added, removed or modified.

This feature is applicable only for outgoing SIP messages. Changes to the messages are applied just before they are sent out, and the SIP SPI code does not remember the changes. Because there are no restrictions on the changes that can be applied, users must be careful when configuring this feature - for example, the call might fail if a regular expression to change the To tag value is configured.

In releases prior to Cisco IOS Release 15.1(3)S1, outgoing SIP messages used to have non-token characters in server and user-agent SIP headers. In Cisco IOS Release 15.1(3)S1 and later releases, server and user-agent SIP headers have only token characters. Token characters can be a alphanumeric character, hyphen (-), dot (.), exclamation mark (!), percent (%), asterisk (*), underscore (_), plus sign (+), grave (`), apostrophe ('), or a tilde (~).

The **all** keyword is used to apply rules on all requests and responses.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **voice service *number voip***
4. **voice-class sip-profiles *group-number***
5. **response *option sip-header option* ADD word CR**
6. **exit**
7. **end**

DETAILED STEPS

	Command or Action	Purpose
Step 1	enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2	configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3	voice service <i>number voip</i> Example: Router(config)# voice service 1 voip	Enters VoIP voice-service configuration mode.
Step 4	voice-class sip-profiles <i>group-number</i> Example: Router(config)# voice-class sip profiles 42	Establishes individual sip profiles defined by a group-number. Valid group-numbers are from 1 to 1000.
Step 5	response <i>option sip-header option</i> ADD word CR Example: Router(config)# request INVITE sip-header supported remove	Add, change, or delete any SIP or SDP header in voice class or sip-profile submenu.

	Command or Action	Purpose
Step 6	exit Example: Router(config-dial-peer)# exit	Exits the current mode.
Step 7	end Example: Router(config-voi-srv)# end	Returns to privileged EXEC mode.

- [Finding Feature Information, page 39](#)
- [Example, page 39](#)
- [Feature Information for Configuring SIP Parameter Modification, page 40](#)

Finding Feature Information

Your software release may not support all the features documented in this module. For the latest feature information and caveats, see the release notes for your platform and software release. To find information about the features documented in this module, and to see a list of the releases in which each feature is supported, see the Feature Information Table at the end of this document.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Example

```

!
!
!
voice service voip
allow-connections sip to sip
redirect ip2ip
sip
early-offer forced
midcall-signaling passthru
sip-profiles 1
!
!
!
voice class sip-profiles 1
request INVITE sip-header Supported remove
request INVITE sip-header Min-SE remove
request INVITE sip-header Session-Expires remove
request INVITE sip-header Unsupported modify "Unsupported:" "timer"
!
!
!

```

Feature Information for Configuring SIP Parameter Modification

The following table provides release information about the feature or features described in this module. This table lists only the software release that introduced support for a given feature in a given software release train. Unless noted otherwise, subsequent releases of that software release train also support that feature.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Feature History Table entry for the Cisco Unified Border Element.

Table 9 Feature Information for Configuring SIP Parameter Modification

Feature Name	Releases	Feature Information
SIP Parameter Modification	12.4(15)XZ 12.4(20)T	Allows users to change the standard SIP messages sent from the Cisco SIP stack for better interworking with different SIP entities. This feature introduces or modifies the following commands: voice class sip-profiles , voice-class sip profiles

Feature History Table entry for the Cisco Unified Border Element (Enterprise) .

Table 10 Feature Information for Configuring SIP Parameter Modification

Feature Name	Releases	Feature Information
SIP Parameter Modification	Cisco IOS XE Release 2.5	Allows users to change the standard SIP messages sent from the Cisco SIP stack for better interworking with different SIP entities. This feature introduces or modifies the following commands: voice class sip-profiles , voice-class sip profiles

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: www.cisco.com/go/trademarks. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.



SIP Session Timer Support

The SIP Session Timer Support feature adds the capability to periodically refresh Session Initiation Protocol (SIP) sessions by sending repeated INVITE requests. The repeated INVITE requests, or re-INVITEs, are sent during an active call leg to allow user agents (UAs) or proxies to determine the status of a SIP session. Without this keepalive mechanism, proxies that remember incoming and outgoing requests (stateful proxies) may continue to retain the call state needlessly. If a UA fails to send a BYE message at the end of a session or if the BYE message is lost because of network problems, a stateful proxy does not know that the session has ended. The re-INVITES ensure that active sessions stay active and completed sessions are terminated.

- [Finding Feature Information, page 43](#)
- [Prerequisites for SIP Session Timer Support, page 43](#)
- [Information About SIP Session Timer Support, page 44](#)
- [How to Configure SIP Session Timer Support, page 45](#)
- [Troubleshooting Tips, page 47](#)
- [Feature Information for SIP Session Timer Support, page 48](#)

Finding Feature Information

Your software release may not support all the features documented in this module. For the latest feature information and caveats, see the release notes for your platform and software release. To find information about the features documented in this module, and to see a list of the releases in which each feature is supported, see the Feature Information Table at the end of this document.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Prerequisites for SIP Session Timer Support

Cisco Unified Border Element

- Cisco IOS Release 12.2(8)T or a later release must be installed and running on your Cisco Unified Border Element.

Cisco Unified Border Element (Enterprise)

- Cisco IOS XE Release 2.5 or a later release must be installed and running on your Cisco ASR 1000 Series Router..

Information About SIP Session Timer Support

To configure the Session Timer feature, you should understand the following concepts:

Interoperability and Compatibility

- **Interoperability**--This feature provides a periodic refresh of SIP sessions. The periodic refresh allows user agents and proxies to monitor the status of a SIP session, preventing hung network resources from pausing indefinitely when network failures occur.
- **Compatibility**--Only one of the two user agent or proxy participants in a call needs to implement the SIP Session Timer Support feature. This feature is easily compatible with older SIP networks. The SIP Session Timer Support feature also adds two new general headers that are used to negotiate the value of the refresh interval.

Role of the User Agents

The initial INVITE request establishes the duration of the session and may include a Session-Expires header and a Min-SE header. These headers indicate the session timer value required by the user agent client (UAC). A receiving user agent server (UAS) or proxy can lower the session timer value, but not lower than the value of the Min-SE header. If the session timer duration is lower than the configured minimum, the proxy or UAS can also send out a 422 response message. If the UAS or proxy finds that the session timer value is acceptable, it copies the Session-Expires header into the 2xx class response.

A UAS or proxy can insert a Session-Expires header in the INVITE if the UAC did not include one. Thus a UAC can receive a Session-Expires header in a response even if none was present in the request.

In the 2xx response, the *refresher* parameter in the Session-Expires header indicates who performs the re-INVITES. For example, if the parameter contains the value *UAC*, the UAC performs the refreshes. For compatibility issues, only one of the two user agents needs to support the session timer feature, and in that case, the UA that supports the feature performs the refreshes. The other UA interprets the refreshes as repetitive INVITES and ignores them.

Re-INVITES are processed identically to INVITE requests, but go out in predetermined session intervals. Re-INVITES carry the new session expiration time. The UA responsible for generating re-INVITE requests sends a re-INVITE out before the session expires. If there is no response, the UA sends a BYE request to terminate the call before session expiration. If a re-INVITE is not sent before the session expiration, either the UAC or the UAS can send a BYE.

If the 2xx response does not contain a Session-Expires header, there is no session expiration and re-INVITES do not need to be sent.

Session-Expires Header

The Session-Expires header conveys the session interval for a SIP call. It is placed in an INVITE request and is allowed in any 2xx class response to an INVITE. Its presence indicates that the UAC wants to use the session timer for this call. Unlike the SIP-Expires header, it can contain only a delta-time, which is the current time, plus the session interval from the response.

For example, if a UAS generates a 200 OK response to a re-INVITE that contained a Session-Expires header with a value of 1800 seconds (30 minutes), the UAS computes the session expiration as 30 minutes after the time when the 200 OK response was sent. For each proxy, the session expiration is 30 minutes after the time when the 2xx was received or sent. For the UAC, the expiration time is 30 minutes after the receipt of the final response.

The recommended value for the Session-Expires header is 1800 seconds.

The syntax of the Session-Expires header is:

```
Session-Expires = ("Session-Expires" |
"x"
) ":" delta-seconds
                [refresher]
refresher       = ";" "refresher" "=" "UAS" | "UAC"
```

The *refresher* parameter is optional in the initial INVITE, although the UAC can set it to *UAC* to indicate that it will do the refreshes. The 200 OK response must have the refresher parameter set.

Min-SE Header

Because of the processing load of INVITE requests you can configure a minimum timer value that the proxy, UAC, and UAS can accept. The proxy, UAC, and UAS. The **min-se** command sets the minimum timer, and it is conveyed in the Min-SE header in the initial INVITE request.

When making a call, the presence of the Min-SE header informs the UAS and any proxies of the minimum value that the UAC accepts for the session timer duration, in seconds. The default value is 1800 seconds (30 minutes). By not reducing the session timer below the value set, the UAS and proxies prevent the UAC from having to reject a call with a 422 error. Once set, the **min-se** command value affects all calls originated by the router. If the Min-SE header is not present, the UA accepts any value.

The syntax of the Min-SE header is:

```
Min-SE = "Min-SE" ":" delta-seconds
```

422 Response Message

If the value of the Session-Expires header is too small, the UAS or proxy rejects the call with a 422 *Session Timer Too Small* response message. With the 422 response message, the proxy or UAS includes a Min-SE header indicating the minimum session value it can accept. The UAC may then retry the call with a larger session timer value.

If a 422 response message is received after an INVITE request, the UAC can retry the INVITE.

Supported and Require Headers

The presence of the *timer* argument in the Supported header indicates that the UA supports the SIP session timer. The presence of the *timer* argument in the Require header indicates that the opposite UA must support the SIP session timer for the call to be successful.

How to Configure SIP Session Timer Support

- [Prerequisites](#), page 45
- [Restrictions](#), page 46
- [Configuring SIP Session Timer Support](#), page 46

Prerequisites

- Ensure that the gateway has voice functionality that is configurable for SIP.
- Establish a working IP network.

- Configure VoIP--Information about configuring VoIP in a SIP environment can be found here: http://www.cisco.com/en/US/tech/tk652/tk701/tech_configuration_guides_list.html .

Restrictions

- Cisco SIP gateways cannot initiate the use of SIP session timers, but do fully support session timers if another UA requests it.
- The Min-SE value can be set only by using the **min-se** command in the configuration gateway. It cannot be set using the CISCO-SIP-UA-MIB.

Configuring SIP Session Timer Support

To configure the SIP: Session Timer Support feature, complete this task.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **voice service voip**
4. **sip**
5. **min-se** *seconds*
6. **min-se** *exit*
7. **min-se** *show sip-ua min-se*

DETAILED STEPS

	Command or Action	Purpose
Step 1	enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2	configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3	voice service voip Example: Router(config)# voice service voip	Enters voice service VoIP configuration mode.

Command or Action	Purpose
Step 4 sip Example: Router(conf-voi-serv)# sip	Enters SIP configuration mode.
Step 5 min-se <i>seconds</i> Example: Router(conf-serv-sip)# min-se 600	Sets the minimum session expires header value, in seconds, for all calls. <ul style="list-style-type: none"> Range is 90 to 86,400 (one day). The default value is 1800 (30 minutes).
Step 6 min-se <i>exit</i> Example: Router(conf-serv-sip)# exit	Exits the current configuration mode.
Step 7 min-se show sip-ua min-se Example: Router(config)# show sip-ua min-se	Verifies the value of the Min-SE header.

Example

This example contains partial output from the **show running-config** command. It shows that the Min-SE value has been changed from its default value.

```
!
voice service voip
  sip
    min-se 950
!
```

Troubleshooting Tips

To troubleshoot this feature, perform the following steps:

- 1 Make sure that you can make a voice call.
- 2 Use the **debug ccsip all** command to enable all SIP debugging capabilities, or use one of the following SIP **debug** commands:
- 3 **debug ccsip calls**
- 4 **debug ccsip error**
- 5 **debug ccsip events**
- 6 **debug ccsip messages**
- 7 **debug ccsip states**

Feature Information for SIP Session Timer Support

The following table provides release information about the feature or features described in this module. This table lists only the software release that introduced support for a given feature in a given software release train. Unless noted otherwise, subsequent releases of that software release train also support that feature.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

ISR feature history entry.

Table 11 Feature Information for SIP - Session Timer Support

Feature Name	Releases	Feature Information
SIP - Session Timer Support	12.2(8)YN 12.2(15)T 12.2(11)YV 12.2(11)T 12.3(2)T	The SIP Session Timer Support feature adds the capability to periodically refresh Session Initiation Protocol (SIP) sessions by sending repeated INVITE requests. The repeated INVITE requests, or re-INVITEs, are sent during an active call leg to allow user agents (UAs) or proxies to determine the status of a SIP session. The following commands were introduced or modified: min-se (SIP) and show sip-ua min-se .

ASR feature history entry.

Table 12 **Feature Information for SIP - Session Timer Support**

Feature Name	Releases	Feature Information
SIP - Session Timer Support	Cisco XE Release 2.5	<p>The SIP Session Timer Support feature adds the capability to periodically refresh Session Initiation Protocol (SIP) sessions by sending repeated INVITE requests. The repeated INVITE requests, or re-INVITEs, are sent during an active call leg to allow user agents (UAs) or proxies to determine the status of a SIP session.</p> <p>The following commands were introduced or modified: min-se (SIP) and show sip-ua min-se.</p>

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: www.cisco.com/go/trademarks. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.



SIP-to-SIP Basic Functionality for Session Border Controller

The SIP-to-SIP Basic Functionality for Session Border Controller (SBC) for Cisco Unified Border Element (Cisco UBE) feature provides termination and re-origination of both signaling and media between VoIP and video networks using SIP signaling in conformance with RFC 3261. The SIP-to-SIP protocol interworking capabilities of the Cisco UBE support the following:

- Basic voice calls (Supported audio codecs include: G.711, G.729, G.728, G.726, G.723, G.722, AAC_LD, iLBC. Video codecs: H.263, and H.264)
- Codec transcoding
- Calling/called name and number
- Dual-Tone Multifrequency (DTMF) relay interworking
 - SIP RFC 2833 <-> SIP RFC 2833
 - SIP Notify <-> SIP Notify
- Interworking between SIP early-media and SIP early-media signaling
- Interworking between SIP delayed-media and SIP delayed-media signaling
- RADIUS call-accounting records
- Resource Reservation Protocol (RSVP) synchronized with call signaling
- SIP-SIP Video calls
- Tool Command Language Interactive Voice Response (TCL IVR) 2.0 for SIP, including media playout and digit collection (RFC 2833 DTMF relay)
- T.38 fax relay and Cisco fax relay
- UDP and TCP transport
- [Finding Feature Information, page 51](#)
- [Prerequisites for SIP-to-SIP Basic Functionality for Session Border Controller, page 52](#)
- [Feature Information for SIP-to-SIP Basic Functionality for Session Border Controller, page 52](#)

Finding Feature Information

Your software release may not support all the features documented in this module. For the latest feature information and caveats, see the release notes for your platform and software release. To find information about the features documented in this module, and to see a list of the releases in which each feature is supported, see the Feature Information Table at the end of this document.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Prerequisites for SIP-to-SIP Basic Functionality for Session Border Controller

Cisco Unified Border Element

- Cisco IOS Release 12.4(4)T or a later release must be installed and running on your Cisco Unified Border Element.

Cisco Unified Border Element (Enterprise)

- Cisco IOS XE Release 3.1S or a later release must be installed and running on your Cisco ASR 1000 Series Router.

Feature Information for SIP-to-SIP Basic Functionality for Session Border Controller

The following table provides release information about the feature or features described in this module. This table lists only the software release that introduced support for a given feature in a given software release train. Unless noted otherwise, subsequent releases of that software release train also support that feature.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

ISR Feature History Information

Table 13 Feature Information for Configuring SIP-to-SIP Supplementary Features

Feature Name	Releases	Feature Information
SIP-to-SIP Basic Functionality for Session Border Controller	12.4(4)T	<p>The SIP-to-SIP Basic Functionality for Session Border Controller (SBC) for Cisco Unified Border Element (Cisco UBE) feature provides termination and re-origination of both signaling and media between VoIP and video networks using SIP signaling in conformance with RFC 3261.</p> <p>This feature uses no new or modified commands.</p>

ASR Feature History Information

Table 14 **Feature Information for Configuring SIP-to-SIP Supplementary Features**

Feature Name	Releases	Feature Information
SIP-to-SIP Basic Functionality for Session Border Controller	Cisco IOS XE Release 3.1S, Cisco IOS XE Release 3.3S	<p>The SIP-to-SIP Basic Functionality for Session Border Controller (SBC) for Cisco Unified Border Element (Cisco UBE) feature provides termination and re-origination of both signaling and media between VoIP and video networks using SIP signaling in conformance with RFC 3261.</p> <p>This feature uses no new or modified commands.</p>

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: www.cisco.com/go/trademarks. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.



SIP-to-SIP Supplementary Services for Session Border Controller

The SIP-to-SIP Supplementary Services for Session Border Controller (SBC) feature enhances terminating and re-originating signaling and media between VoIP and Video networks by supporting the following features:

- IP Address Hiding in all SIP messages including supplementary services
- Media
 - Media Flow Around
- Support on Cisco AS5350XM and Cisco AS5400XM platforms
- SIP-to-SIP Supplementary services using REFER/3xx method. The following features are enabled by default:
 - Message Waiting Indication
 - Call Waiting
 - Call Transfer (Blind, Consult, Alerting)
 - Call Forward (All, Busy, No Answer)
 - Distinctive Ringing
 - Call Hold/Resume
 - Music on Hold
- Hosted NAT Traversal for SIP
- [Finding Feature Information, page 55](#)
- [Prerequisites for SIP-to-SIP Supplementary Services for Session Border Controller, page 56](#)
- [How to Configure SIP-to-SIP Supplementary Services for Session Border Controller, page 56](#)
- [Feature Information for SIP-to-SIP Supplementary Services for Session Border Controller, page 56](#)

Finding Feature Information

Your software release may not support all the features documented in this module. For the latest feature information and caveats, see the release notes for your platform and software release. To find information about the features documented in this module, and to see a list of the releases in which each feature is supported, see the Feature Information Table at the end of this document.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Prerequisites for SIP-to-SIP Supplementary Services for Session Border Controller

Cisco Unified Border Element

- Cisco IOS Release 12.4(9)T or a later release must be installed and running on your Cisco Unified Border Element.

Cisco Unified Border Element (Enterprise)

- Cisco IOS XE Release 3.1.0S or a later release must be installed and running on your Cisco ASR 1000 Series Router.

How to Configure SIP-to-SIP Supplementary Services for Session Border Controller

To configure the SIP-to-SIP Supplementary Services for Session Border Controller feature, see the SIP-to-SIP Connections on a Cisco Unified Border Element chapter in the Cisco Unified Border Element Configuration Guide at the following URL: http://www.cisco.com/en/US/docs/ios/voice/cube/configuration/guide/vb-gw-sipsip_ps10592_TSD_Products_Configuration_Guide_Chapter.html

Feature Information for SIP-to-SIP Supplementary Services for Session Border Controller

The following table provides release information about the feature or features described in this module. This table lists only the software release that introduced support for a given feature in a given software release train. Unless noted otherwise, subsequent releases of that software release train also support that feature.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Feature History Table entry for the Cisco Unified Border Element.

Table 15 *Feature Information for Configuring SIP-SIP Supplementary Features*

Feature Name	Releases	Feature Information
SIP-to-SIP Supplementary Services for Session Border Controller	12.4(9)T,	The SIP-to-SIP Supplementary Services for Session Border Controller feature enhances terminating and re-originating signaling and media between VoIP and Video networks This feature uses no new or modified commands.

Feature History Table entry for the Cisco Unified Border Element (Enterprise).

Table 16 *Feature Information for Configuring SIP-SIP Supplementary Features*

Feature Name	Releases	Feature Information
SIP-to-SIP Supplementary Services for Session Border Controller	Cisco IOS XE Release 3.1S	The SIP-to-SIP Supplementary Services for Session Border Controller feature enhances terminating and re-originating signaling and media between VoIP and Video networks This feature uses no new or modified commands.

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: www.cisco.com/go/trademarks. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.



Session Refresh with Reinvites

- The **allow-connections sip to sip** command must be configured before you configure the Session refresh with Reinvites feature. For more information and configuration steps see the "Configuring SIP-to-SIP Connections in a Cisco Unified Border Element" section.

Cisco Unified Border Element

- Cisco IOS Release 12.4(20)T or a later release must be installed and running on your Cisco Unified Border Element.

Cisco Unified Border Element (Enterprise)

- Cisco IOS XE Release 2.5 or a later release must be installed and running on your Cisco ASR 1000 Series Router.



Note

- SIP-to-SIP video calls and SIP-to-SIP ReInvite-based supplementary services fail if the **midcall-signaling** command is not configured.



Note

The following features function if the **midcall-signaling** command is not configured: sess and refer-based supplementary services.

- Configuring Session Refresh with Reinvites is for SIP-to-SIP calls only. All other calls (H323-to-SIP, and H323-to-H323) do not require the **midcall-signaling** command be configured
- Configuring the Session Refresh with Reinvites feature on a dial-peer basis is not supported.

>

Configuring support for session refresh with reinvites expands the ability of the Cisco Unified Border Element to receive a REINVITE message that contains either a session refresh parameter or a change in media via a new SDP and ensure the session does not time out. The **midcall-signaling** command distinguishes between the way a Cisco Unified Communications Express and Cisco Unified Border Element releases signaling messages. Most SIP-to-SIP video and SIP-to-SIP ReInvite-based supplementary services features require the Configuring Session Refresh with Reinvites feature to be configured.

Cisco IOS Release 12.4(15)XZ and Earlier Releases

Session refresh support via OPTIONS method. For configuration information, see the "Enabling In-Dialog OPTIONS to Monitor Active SIP Sessions" section.

Cisco IOS Release 12.4(15)XZ and Later Releases

Cisco Unified BE transparently passes other session refresh messages and parameters so that UAs and proxies can establish keepalives on a call.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **voice service voip**
4. **sip**
5. **midcall-signaling passthru**
6. **exit**
7. **end**

DETAILED STEPS

	Command or Action	Purpose
Step 1	enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2	configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3	voice service voip Example: Router(config)# voice service voip	Enters VoIP voice-service configuration mode.
Step 4	sip Example: Router(conf-voi-serv)# sip	Enters SIP configuration mode.
Step 5	midcall-signaling passthru Example: Router(conf-serv-sip)# midcall-signaling passthru	Passes SIP messages from one IP leg to another IP leg.

	Command or Action	Purpose
Step 6	exit Example: <pre>Router(conf-serv-sip)# exit</pre>	Exits the current mode.
Step 7	end Example: <pre>Router(conf-serv-sip) end</pre>	Returns to privileged EXEC mode.

- [Finding Feature Information, page 61](#)
- [Feature Information for Session Refresh with Reinvites, page 61](#)

Finding Feature Information

Your software release may not support all the features documented in this module. For the latest feature information and caveats, see the release notes for your platform and software release. To find information about the features documented in this module, and to see a list of the releases in which each feature is supported, see the Feature Information Table at the end of this document.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Feature Information for Session Refresh with Reinvites

The following table provides release information about the feature or features described in this module. This table lists only the software release that introduced support for a given feature in a given software release train. Unless noted otherwise, subsequent releases of that software release train also support that feature.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Feature History Table for the ASR

Table 17 Feature Information for Session Refresh with Reinvites

Feature Name	Releases	Feature Information
Session Refresh with Reinvites	12.4(20)T	Expands the ability of the Cisco Unified BE to control the session refresh parameters and ensure the session does not time out. midcall-signaling

Feature History Table for the ISR

Table 18 *Feature Information for Session Refresh with Reinvites*

Feature Name	Releases	Feature Information
Session Refresh with Reinvites	Cisco IOS XE Release 2.5	Expands the ability of the Cisco Unified BE to control the session refresh parameters and ensure the session does not time out. midcall-signaling

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: www.cisco.com/go/trademarks. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.



Configuring Cisco UBE Out-of-dialog OPTIONS Ping for Specified SIP Servers or Endpoints

- The following are required for OOD Options ping to function. If any are missing, the Out-of-dialog (OOD) Options ping will not be sent and the dial peer is reset to the default active state.
 - Dial-peer should be in active state
 - Session protocol must be configured for SIP
 - Configure Session target or outbound proxy must be configured. If both are configured, outbound proxy has preference over session target.

Cisco Unified Border Element

- Cisco IOS Release 15.0(1)M or a later release must be installed and running on your Cisco Unified Border Element.

Cisco Unified Border Element (Enterprise)

- Cisco IOS XE Release 3.1S or a later release must be installed and running on your Cisco ASR 1000 Series Router



Note

- The Cisco Unified Border Element OOD Options ping feature can only be configured at the VoIP Dial-peer level.
- All dial peers start in an active (not busied out) state on a router boot or reboot.
- If a dial-peer has both an outbound proxy and a session target configured, the OOD options ping is sent to the outbound proxy address first.
- Though multiple dial-peers may point to the same SIP server IP address, an independent OOD options ping is sent for each dial-peer.
- If a SIP server is configured as a DNS hostname, OOD Options pings are sent to all the returned addresses until a response is received.
- Configuration for Cisco Unified Border Element OOD and TDM Gateway OOD are different, but can co-exist.

>

The Out-of-dialog (OOD) Options Ping feature provides a keepalive mechanism at the SIP level between any number of destinations. A generic heartbeat mechanism allows Cisco Unified Border Element to monitor the status of SIP servers or endpoints and provide the option of busying-out a dial-peer upon total heartbeat failure. When a monitored endpoint heartbeat fails, the dial-peer is busied out. If an alternate dial-peer is configured for the same destination pattern, the call is failed over to the next preferred dial peer, or else the on call is rejected with an error cause code.

The table below describes error codes option ping responses considered unsuccessful and the dial-peer is busied out for following scenarios:

Table 19 Error Codes that busyout the endpoint

Error Code	Description
503	service unavailable
505	sip version not supported
no response	i.e. request timeout

All other error codes, including 400 are considered a valid response and the dial peer is not busied out.



Note

The purpose of this feature is to determine if the SIP session protocol on the endpoint is UP and available to handle calls. It may not handle OPTIONS message but as long as the SIP protocol is available, it should be able to handle calls.

When a dial-peer is busied out, Cisco Unified Border Element continues the heartbeat mechanism and the dial-peer is set to active upon receipt of a response.

SUMMARY STEPS

1. enable
2. configure terminal
3. dial-peer voice *tag* voip
4. voice-class sip options-keepalive {up-interval *seconds* | down-interval *seconds* | retry *retries*}
5. exit

DETAILED STEPS

	Command or Action	Purpose
Step 1	enable Example: Router> enable	Enables privileged EXEC mode. Enter your password if prompted.
Step 2	configure terminal Example: Router# configure terminal	Enters global configuration mode.

	Command or Action	Purpose
Step 3	<p>dial-peer voice <i>tag</i> voip</p> <p>Example:</p> <pre>Router(config)# dial-peer voice 200 voip</pre>	Enters dial-peer configuration mode for the VoIP peer designated by tag.
Step 4	<p>voice-class sip options-keepalive {up-interval <i>seconds</i> down-interval <i>seconds</i> retry <i>retries</i>}</p> <p>Example:</p> <pre>Router(config-dial-peer)# voice-class sip options-keepalive up-interval 12 down-interval 65 retry 3</pre>	<p>Monitors connectivity between endpoints.</p> <ul style="list-style-type: none"> • up-interval seconds -- Number of up-interval seconds allowed to pass before marking the UA as unavailable. The range is 5-1200. The default is 60. • down-interval seconds -- Number of down-interval seconds allowed to pass before marking the UA as unavailable. The range is 5-1200. The default is 30. • retry retries -- Number of retry attempts before marking the UA as unavailable. The range is 1 to 10. The default is 5 attempts.
Step 5	<p>exit</p> <p>Example:</p> <pre>Router(config-dial-peer)# exit</pre>	Exits the current mode.

- [Finding Feature Information, page 65](#)
- [Troubleshooting Tips, page 65](#)
- [Feature Information for Cisco UBE Out-of-dialog OPTIONS Ping for Specified SIP Servers or Endpoints, page 66](#)

Finding Feature Information

Your software release may not support all the features documented in this module. For the latest feature information and caveats, see the release notes for your platform and software release. To find information about the features documented in this module, and to see a list of the releases in which each feature is supported, see the Feature Information Table at the end of this document.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Troubleshooting Tips

The following commands can help troubleshoot the OOD Options Ping feature:

- **debug ccsip all** --shows all Session Initiation Protocol (SIP)-related debugging.
- **show dial-peer voice x** --shows configuration of keepalive information.

```
Router# show dial-peer voice | in options
```

```
voice class sip options-keepalive up-interval 60 down-interval 30 retry 5
voice class sip options-keepalive dial-peer action = active
```

- **show dial-peer voice summary** --shows Active or Busyout dial-peer status.

```
Router# show dial-peer voice summary
          AD          PRE PASS
TAG TYPE MIN OPER PREFIX  DEST-PATTERN KEEPALIVE
111 voip up    up      0 syst active
9  voip up    down   0 syst busy-out
```

Feature Information for Cisco UBE Out-of-dialog OPTIONS Ping for Specified SIP Servers or Endpoints

The following table provides release information about the feature or features described in this module. This table lists only the software release that introduced support for a given feature in a given software release train. Unless noted otherwise, subsequent releases of that software release train also support that feature.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Feature History Table entry for the Cisco Unified Border Element.

Table 20 *Feature Information for Cisco UBE Out-of-dialog OPTIONS Ping for Specified SIP Servers or Endpoints*

Feature Name	Releases	Feature Information
Out-of-dialog OPTIONS Ping to Monitor Dial-peers to Specified SIP Servers and Endpoints	15.0(1)M	<p>This feature provides a keepalive mechanism at the SIP level between any number of destinations. The generic heartbeat mechanism allows Cisco UBE to monitor the status of SIP servers or endpoints and provide the option of busying-out associated dial-peer upon total heartbeat failure.</p> <p>The following command was introduced: voice-class sip options-keepalive</p>

Feature History Table entry for the Cisco Unified Border Element (Enterprise).

Table 21 **Feature Information for Cisco UBE Out-of-dialog OPTIONS Ping for Specified SIP Servers or Endpoints**

Feature Name	Releases	Feature Information
Out-of-dialog OPTIONS Ping to Monitor Dial-peers to Specified SIP Servers and Endpoints	Cisco IOS XE Release 3.1S	<p>This feature provides a keepalive mechanism at the SIP level between any number of destinations. The generic heartbeat mechanism allows Cisco UBE to monitor the status of SIP servers or endpoints and provide the option of busying-out associated dial-peer upon total heartbeat failure.</p> <p>The following command was introduced: voice-class sip options-keepalive</p>

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: www.cisco.com/go/trademarks. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.



Configuring an Error Response Code upon an Out-of-Dialog OPTIONS Ping Failure

Cisco Unified Border Element (Cisco UBE) provides an option to configure the error response code when a dial peer is busied out because of an Out-of-Dialog OPTIONS ping failure.

The OPTIONS ping mechanism monitors the status of a remote Session Initiation Protocol (SIP) server, proxy or endpoints. Cisco UBE monitors these endpoints periodically. When there is no response from these monitored endpoints, the configured dial peer is busied out. If the dial-peer endpoint is busied out due to an OPTIONS ping failure, the call is passed on to the next dial-peer endpoint if an alternate dial peer is configured for the same destination. Otherwise the error response 404 is sent. This feature provides the option of configuring the error response code to reroute the call. Therefore when a dial peer is busied out due to the OPTIONS ping failure, the SIP error code configured in the inbound dial-peer is sent as a response.

To configure the SIP error code response, perform the following tasks:

- [Finding Feature Information, page 69](#)
- [Prerequisites for Configuring an Error Response Code upon an Out-of-Dialog OPTIONS Ping Failure, page 70](#)
- [Restrictions for Configuring an Error Response Code upon an Out-of-Dialog OPTIONS Ping Failure, page 70](#)
- [Configuring an Error Response Code upon an Out-of-Dialog OPTIONS Ping Failure at the Global Level, page 70](#)
- [Configuring an Error Response Code upon an Out-of-Dialog OPTIONS Ping Failure at the Dial Peer Level, page 72](#)
- [Troubleshooting Tips, page 73](#)
- [Feature Information for Configuring an Error Response Code upon an Out-of-Dialog OPTIONS Ping Failure, page 74](#)

Finding Feature Information

Your software release may not support all the features documented in this module. For the latest feature information and caveats, see the release notes for your platform and software release. To find information about the features documented in this module, and to see a list of the releases in which each feature is supported, see the Feature Information Table at the end of this document.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Prerequisites for Configuring an Error Response Code upon an Out-of-Dialog OPTIONS Ping Failure

- The Cisco UBE Out-of-Dialog (OOD) OPTIONS Ping for Specified SIP Servers or Endpoints feature should be configured before configuring this error response code for a ping OPTIONS failure.

Cisco Unified Border Element

- Cisco IOS Release 15.1(1)T or a later release must be installed and running on your Cisco Unified Border Element.

Cisco Unified Border Element (Enterprise)

- Cisco IOS XE Release 3.1S or a later release must be installed and running on your Cisco ASR 1000 Series Router.

Restrictions for Configuring an Error Response Code upon an Out-of-Dialog OPTIONS Ping Failure

The error code configuration will not have any effect if it is configured on the outbound dial peer.

Configuring an Error Response Code upon an Out-of-Dialog OPTIONS Ping Failure at the Global Level

The table below describes the SIP error codes.

Table 22 *SIP Error Codes*

Error Code Number	Description
400	Bad Request
401	Unauthorized
402	Payment Required
403	Forbidden
404	Not Found
408	Request Timed Out
416	Unsupported URI
480	Temporarily Unavailable

Error Code Number	Description
482	Loop Detected
484	Address Incomplete
486	Busy Here
487	Request Terminated
488	Not Acceptable Here
500-599	SIP 5xx--Server/Service Failure
500	Internal Server Error
502	Bad Gateway
503	Service Unavailable
600-699	SIP 6xx--Global Failure

To configure the error response code for the OPTIONS ping failure to support the Cisco Unified Border Element at the global level, perform the steps in this section.

SUMMARY STEPS

1. enable
2. configure terminal
3. voice service voip
4. sip
5. error-code-override options-keepalive failure *sip-status-code-number*
6. end

DETAILED STEPS

Command or Action	Purpose
<p>Step 1 enable</p> <p>Example:</p> <pre>Router> enable</pre>	<p>Enables privileged EXEC mode.</p> <ul style="list-style-type: none"> • Enter your password if prompted.
<p>Step 2 configure terminal</p> <p>Example:</p> <pre>Router# configure terminal</pre>	<p>Enters global configuration mode.</p>

Command or Action	Purpose
Step 3 <code>voice service voip</code> Example: <pre>Router(config)# voice service voip</pre>	Enters voice service configuration mode.
Step 4 <code>sip</code> Example: <pre>Router(conf-voi-serv)# sip</pre>	Enters voice service SIP configuration mode.
Step 5 <code>error-code-override options-keepalive failure sip-status-code-number</code> Example: <pre>Router(conf-serv-sip)# error-code-override options-keepalive failure 402</pre>	Configures the specified SIP error code number. <ul style="list-style-type: none"> • <i>sip-status-code-number</i> --SIP status code to be sent for an options keepalive failure. Range: 400 to 699. Default: 503. • The table above provides more details about these error codes.
Step 6 <code>end</code> Example: <pre>Router(conf-serv-sip)# end</pre>	Exits voice service SIP configuration mode and returns to privileged EXEC mode.

Configuring an Error Response Code upon an Out-of-Dialog OPTIONS Ping Failure at the Dial Peer Level

To configure the error response code for the OPTIONS ping failure to support the Cisco Unified Border Element at the dial-peer level, perform the steps in this section.

SUMMARY STEPS

1. `enable`
2. `configure terminal`
3. `dial-peer voice voice-dial-peer-tag voip`
4. `voice-class sip error-code-error-override options-keepalive failure {sip-status-code-number | system}`
5. `end`

DETAILED STEPS

Command or Action	Purpose
<p>Step 1 <code>enable</code></p> <p>Example:</p> <pre>Router> enable</pre>	<p>Enables privileged EXEC mode.</p> <ul style="list-style-type: none"> Enter your password if prompted.
<p>Step 2 <code>configure terminal</code></p> <p>Example:</p> <pre>Router# configure terminal</pre>	<p>Enters global configuration mode.</p>
<p>Step 3 <code>dial-peer voice voice-dial-peer-tag voip</code></p> <p>Example:</p> <pre>Router(config)# dial-peer voice 234 voip</pre>	<p>Enters dial peer voice configuration mode.</p>
<p>Step 4 <code>voice-class sip error-code-error-override options-keepalive failure {sip-status-code-number system}</code></p> <p>Example:</p> <pre>Router(config-dial-peer)# voice-class sip error-code-override options-keepalive failure 500</pre>	<p>Configures the specified SIP error code number.</p> <ul style="list-style-type: none"> <code>sip-status-code-number</code> --SIP status code to be sent for an options keepalive failure. Range: 400 to 699. Default: 503. Configuring an Error Response Code upon an Out-of-Dialog OPTIONS Ping Failure at the Dial Peer Level, page 72 provides more details about these error codes. <p>Note If the system keyword is configured, the global level configuration will override the dial-peer configuration.</p>
<p>Step 5 <code>end</code></p> <p>Example:</p> <pre>Router(config-dial-peer)# end</pre>	<p>Exits dial peer voice configuration mode and returns to privileged EXEC mode.</p>

Troubleshooting Tips

The following debug commands display any error that occurs with the error code response:

- `debug ccsip messages--` shows SIP messages.

```
Router# debug ccsip messages
SIP Call messages tracing is enabled
```

- `debug ccsip all` --shows all SIP-related debugging.

```
Router# debug ccsip all
```

```
This may severely impact system performance. Continue? [confirm]
All SIP Call tracing is enabled
```

Feature Information for Configuring an Error Response Code upon an Out-of-Dialog OPTIONS Ping Failure

The following table provides release information about the feature or features described in this module. This table lists only the software release that introduced support for a given feature in a given software release train. Unless noted otherwise, subsequent releases of that software release train also support that feature.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Feature History Table entry for the Cisco Unified Border Element.

Table 23 *Feature Information for Configuring an Error Response Code upon an Out-of-Dialog OPTIONS Ping Failure*

Feature Name	Releases	Feature Information
Error Response Code upon an Out-of-Dialog OPTIONS Ping Failure	15.1(1)T	<p>This feature provides option to configure the error response code when a dial peer is busied out because of an Out-of-Dialog OPTIONS ping failure.</p> <p>The following commands were introduced or modified in this release: error-code-override options-keepalive failure, voice-class sip error-code-override options-keepalive failure.</p>

Feature History Table entry for the Cisco Unified Border Element (Enterprise)

Table 24 **Feature Information for Configuring an Error Response Code upon an Out-of-Dialog OPTIONS Ping Failure**

Feature Name	Releases	Feature Information
Error Response Code upon an Out-of-Dialog OPTIONS Ping Failure	Cisco IOS XE Release 3.1S	<p>This feature provides option to configure the error response code when a dial peer is busied out because of an Out-of-Dialog OPTIONS ping failure.</p> <p>The following commands were introduced or modified in this release: error-code-override options-keepalive failure, voice-class sip error-code-override options-keepalive failure.</p>

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: www.cisco.com/go/trademarks. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.



SIP INFO Method for DTMF Tone Generation

The SIP: INFO Method for DTMF Tone Generation feature uses the Session Initiation Protocol (SIP) INFO method to generate dual tone multifrequency (DTMF) tones on the telephony call leg. SIP info methods, or request message types, request a specific action be taken by another user agent (UA) or proxy server. The SIP INFO message is sent along the signaling path of the call. Upon receipt of a SIP INFO message with DTMF relay content, the gateway generates the specified DTMF tone on the telephony end of the call.

- [Finding Feature Information, page 77](#)
- [Prerequisites for SIP INFO Method for DTMF Tone Generation, page 77](#)
- [Information About SIP INFO Method for DTMF Tone Generation, page 78](#)
- [How to Review SIP INFO Messages, page 78](#)
- [Prerequisites, page 78](#)
- [Restrictions, page 78](#)
- [Configuring for SIP INFO Method for DTMF Tone Generation, page 79](#)
- [Troubleshooting Tips, page 79](#)
- [Feature Information for SIP INFO Method for DTMF Tone Generation, page 80](#)

Finding Feature Information

Your software release may not support all the features documented in this module. For the latest feature information and caveats, see the release notes for your platform and software release. To find information about the features documented in this module, and to see a list of the releases in which each feature is supported, see the Feature Information Table at the end of this document.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Prerequisites for SIP INFO Method for DTMF Tone Generation

Cisco Unified Border Element

- Cisco IOS Release 12.2(11)T or a later release must be installed and running on your Cisco Unified Border Element.

Cisco Unified Border Element (Enterprise)

- Cisco IOS XE Release 2.5 or a later release must be installed and running on your Cisco ASR 1000 Series Router.

Information About SIP INFO Method for DTMF Tone Generation

The SIP: INFO Method for DTMF Tone Generation feature is always enabled, and is invoked when a SIP INFO message is received with DTMF relay content. This feature is related to the DTMF Events Through SIP Signaling feature, which allows an application to be notified about DTMF events using SIP NOTIFY messages. Together, the two features provide a mechanism to both send and receive DTMF digits along the signaling path. For more information on sending DTMF event notification using SIP NOTIFY messages, refer to the DTMF Events Through SIP Signaling feature.

How to Review SIP INFO Messages

The SIP INFO method is used by a UA to send call signaling information to another UA with which it has an established media session. The following example shows a SIP INFO message with DTMF content:

```
INFO sip:2143302100@172.17.2.33 SIP/2.0
Via: SIP/2.0/UDP 172.80.2.100:5060
From: <sip:9724401003@172.80.2.100>;tag=43
To: <sip:2143302100@172.17.2.33>;tag=9753.0207
Call-ID: 984072_15401962@172.80.2.100
CSeq: 25634 INFO
Supported: 100rel
Supported: timer
Content-Length: 26
Content-Type: application/dtmf-relay
Signal= 1
Duration= 160
```

This sample message shows a SIP INFO message received by the gateway with specifics about the DTMF tone to be generated. The combination of the "From", "To", and "Call-ID" headers identifies the call leg. The signal and duration headers specify the digit, in this case 1, and duration, 160 milliseconds in the example, for DTMF tone play.

Prerequisites

The following are general prerequisites for SIP functionality:

- Ensure that the gateway has voice functionality that is configured for SIP.
- Establish a working IP network.
- Configure VoIP.

Restrictions

The SIP: INFO Method for DTMF Tone Generation feature includes the following signal duration parameters:

- Minimum signal duration is 100 milliseconds (ms). If a request is received with a duration less than 100 ms, the minimum duration of 100 ms is used by default.
- Maximum signal duration is 5000 ms. If a request is received with a duration longer than 5000 ms, the maximum duration of 5000 ms is used by default.
- If no duration parameter is included in a request, the gateway defaults to a signal duration of 250 ms.

Configuring for SIP INFO Method for DTMF Tone Generation

You cannot configure, enable, or disable this feature. No configuration tasks are required to configure the SIP - INFO Method for DTMF Tone Generation feature. The feature is enabled by default.

Troubleshooting Tips

You can display SIP statistics, including SIP INFO method statistics, by using the **show sip-ua statistics** and **show sip-ua status** commands in privileged EXEC mode. See the following fields for SIP INFO method statistics:

- **OkInfo 0/0**, under SIP Response Statistics, Success, displays the number of successful responses to an INFO request.
- **Info 0/0**, under SIP Total Traffic Statistics, displays the number of INFO messages received and sent by the gateway.

The following is sample output from the **show sip-ua statistics** command:

```
Router# show sip-ua statistics
SIP Response Statistics (Inbound/Outbound)
Informational:
Trying 1/1, Ringing 0/0,
Forwarded 0/0, Queued 0/0,
SessionProgress 0/1
Success:
OkInvite 0/1, OkBye 1/0,
OkCancel 0/0, OkOptions 0/0,
OkPrack 0/0, OkPreconditionMet 0/0
OkSubscribe 0/0, OkNotify 0/0,
OkInfo 0/0, 202Accepted 0/0
Redirection (Inbound only):
MultipleChoice 0, MovedPermanently 0,
MovedTemporarily 0, SeeOther 0,
UseProxy 0, AlternateService 0
Client Error:
BadRequest 0/0, Unauthorized 0/0,
PaymentRequired 0/0, Forbidden 0/0,
NotFound 0/0, MethodNotAllowed 0/0,
NotAcceptable 0/0, ProxyAuthReqd 0/0,
ReqTimeout 0/0, Conflict 0/0, Gone 0/0,
LengthRequired 0/0, ReqEntityTooLarge 0/0,
ReqURITooLarge 0/0, UnsupportedMediaType 0/0,
BadExtension 0/0, TempNotAvailable 0/0,
CallLegNonExistent 0/0, LoopDetected 0/0,
TooManyHops 0/0, AddrIncomplete 0/0,
Ambiguous 0/0, BusyHere 0/0,
BadEvent 0/0
Server Error:
InternalError 0/0, NotImplemented 0/0,
BadGateway 0/0, ServiceUnavail 0/0,
GatewayTimeout 0/0, BadSipVer 0/0
Global Failure:
BusyEverywhere 0/0, Decline 0/0,
NotExistAnywhere 0/0, NotAcceptable 0/0
```

```
SIP Total Traffic Statistics (Inbound/Outbound)
  Invite 0/0, Ack 0/0, Bye 0/0,
  Cancel 0/0, Options 0/0,
  Prack 0/0, Comet 0/0,
  Subscribe 0/0, Notify 0/0,
  Refer 0/0, Info 0/0
Retry Statistics
Invite 0, Bye 0, Cancel 0, Response 0, Notify 0
```

The following is sample output from the **show sip-ua status** command:

```
Router# show sip-ua status
SIP User Agent Status
SIP User Agent for UDP : ENABLED
SIP User Agent for TCP : ENABLED
SIP User Agent bind status(signaling): DISABLED
SIP User Agent bind status(media): DISABLED
SIP max-forwards : 6
SIP DNS SRV version: 2 (rfc 2782)
SDP application configuration:
  Version line (v=) required
  Owner line (o=) required
  Session name line (s=) required
  Timespec line (t=) required
  Media supported: audio image
  Network types supported: IN
  Address types supported: IP4
  Transport types supported: RTP/AVP udptl
```

Feature Information for SIP INFO Method for DTMF Tone Generation

The following table provides release information about the feature or features described in this module. This table lists only the software release that introduced support for a given feature in a given software release train. Unless noted otherwise, subsequent releases of that software release train also support that feature.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

ISR Feature table entry

Table 25 Feature Information for SIP: INFO Method for DTMF Tone Generation

Feature Name	Releases	Feature Information
SIP: INFO Method for DTMF Tone Generation	12.2(11)T 12.3(2)T 12.2(8)YN 12.2(11)YV 12.2(11)T 12.2(15)T	The SIP: INFO Method for DTMF Tone Generation feature uses the Session Initiation Protocol (SIP) INFO method to generate dual-tone multifrequency (DTMF) tones on the telephony call leg. SIP methods, or request message types, request a specific action be taken by another user agent (UA) or proxy server. The SIP INFO message is sent along the signaling path of the call. The following command was introduced: show sip-ua .

ASR Feature table entry

Table 26 Feature Information for SIP: INFO Method for DTMF Tone Generation

Feature Name	Releases	Feature Information
SIP: INFO Method for DTMF Tone Generation	IOS XE Release 2.5	The SIP: INFO Method for DTMF Tone Generation feature uses the Session Initiation Protocol (SIP) INFO method to generate dual-tone multifrequency (DTMF) tones on the telephony call leg. SIP methods, or request message types, request a specific action be taken by another user agent (UA) or proxy server. The SIP INFO message is sent along the signaling path of the call. The following command was introduced: show sip-ua .

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: www.cisco.com/go/trademarks. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams,

and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.



SIP Enhanced 180 Provisional Response Handling

The SIP: Enhanced 180 Provisional Response Handling feature enables early media cut-through on Cisco IOS gateways for Session Initiation Protocol (SIP) 180 response messages.

- [Finding Feature Information, page 83](#)
- [Prerequisites SIP Enhanced 180 Provisional Response Handling, page 83](#)
- [Information About SIP Enhanced 180 Provisional Response Handling, page 84](#)
- [How to Disable the SIP Enhanced 180 Provisional Response Handling Feature, page 84](#)
- [Verifying SIP Enhanced 180 Provisional Response Handling, page 85](#)
- [Configuration Examples for SIP - Enhanced 180 Provisional Response Handling, page 86](#)
- [Feature Information for SIP Enhanced 180 Provisional Response Handling, page 89](#)

Finding Feature Information

Your software release may not support all the features documented in this module. For the latest feature information and caveats, see the release notes for your platform and software release. To find information about the features documented in this module, and to see a list of the releases in which each feature is supported, see the Feature Information Table at the end of this document.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Prerequisites SIP Enhanced 180 Provisional Response Handling

Cisco Unified Border Element

- Cisco IOS Release 12.2(8)T or a later release must be installed and running on your Cisco Unified Border Element.

Cisco Unified Border Element (Enterprise)

- Cisco IOS XE Release 2.5 or a later release must be installed and running on your Cisco ASR 1000 Series Router.

Information About SIP Enhanced 180 Provisional Response Handling

The Session Initiation Protocol (SIP) feature allows you to specify whether 180 messages with Session Description Protocol (SDP) are handled in the same way as 183 responses with SDP. The 180 Ringing message is a provisional or informational response used to indicate that the INVITE message has been received by the user agent and that alerting is taking place. The 183 Session Progress response indicates that information about the call state is present in the message body media information. Both 180 and 183 messages may contain SDP, which allows an early media session to be established prior to the call being answered.

Prior to this feature, Cisco gateways handled a 180 Ringing response with SDP in the same manner as a 183 Session Progress response; that is, the SDP was assumed to be an indication that the far end would send early media. Cisco gateways handled a 180 response without SDP by providing local ringback, rather than early media cut-through. This feature provides the capability to ignore the presence or absence of SDP in 180 messages, and as a result, treat all 180 messages in a uniform manner. The SIP: Enhanced 180 Provisional Response Handling feature allows you to specify which call treatment, early media or local ringback, is provided for 180 responses with SDP:

The table below shows the call treatments available with this feature:

Table 27 *Call Treatments with SIP Enhanced 180 Provisional Response Handling*

Response Message	SIP Enhanced 180 Provisional Response Handling Status	Treatment
180 response with SDP	Enabled (default)	Early media cut-through
180 response with SDP	Disabled	Local ringback
180 response without SDP	Not affected by the SIP--Enhanced 180 Provisional Response Handling feature	Local ringback
183 response with SDP	Not affected by the SIP--Enhanced 180 Provisional Response Handling feature	Early media cut-through

How to Disable the SIP Enhanced 180 Provisional Response Handling Feature

- [Disabling Early Media Cut-Through, page 84](#)

Disabling Early Media Cut-Through

The early media cut-through feature is enabled by default. To disable early media cut-through, perform the following task:

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **interface** *type number*
4. **sip ua**
5. **disable-early-media 180**

DETAILED STEPS

Command or Action	Purpose
Step 1 enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2 configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3 interface <i>type number</i> Example: Router(config)# ethernet 0/0/0	Configures an interface type and enters interface configuration mode.
Step 4 sip ua Example: Router(config-sip-ua)# sip ua	Enables SIP UA configuration commands in order to configure the user agent.
Step 5 disable-early-media 180 Example: Router(config-sip-ua)# disable-early-media 180	Disables the gateway's ability to process SDP in a 180 response as a request for early media cut-through.

Verifying SIP Enhanced 180 Provisional Response Handling

- To verify the SIP Enhanced 180 Provisional Response Handling feature use the **show running configuration** or **show sip-ua status** or **show logging** command to display the output.

- If early media is enabled, which is the default setting, the **show running-config** output does not show any information related to the new feature.
- To monitor this feature, use the **show sip-ua statistics** and **show sip-ua status EXEC** commands.

Configuration Examples for SIP - Enhanced 180 Provisional Response Handling

- [show running-config Command, page 86](#)
- [show sip-ua status Command, page 86](#)
- [show logging Command, page 87](#)

show running-config Command

The following is sample output from the **show running-config** command after the **disable-early-media 180** command was used:

```
Router# show running-config
.
.
.
dial-peer voice 223 pots
 application session
 destination-pattern 223
 port 1/0/0
!
gateway
!
sip-ua
 disable-early-media 180
```

show sip-ua status Command

The following is sample output from the **show sip-ua status** command after the **disable-early-media 180** command was used.

```
Router# show sip-ua status
SIP User Agent Status
SIP User Agent for UDP :ENABLED
SIP User Agent for TCP :ENABLED
SIP User Agent bind status(signaling):ENABLED 10.0.0.0
SIP User Agent bind status(media):ENABLED 0.0.0.0
SIP early-media for 180 responses with SDP:DISABLED
SIP max-forwards :6
SIP DNS SRV version:2 (rfc 2782)
NAT Settings for the SIP-UA
Role in SDP:NONE
Check media source packets:DISABLED
Redirection (3xx) message handling:ENABLED
SDP application configuration:
 Version line (v=) required
 Owner line (o=) required
 Timespec line (t=) required
 Media supported:audio image
 Network types supported:IN
 Address types supported:IP4
 Transport types supported:RTP/AVP udpt1
```


show logging Command

The following is partial sample output from the **show logging** command. The outgoing gateway is receiving a 180 message with SDP and is configured to ignore the SDP.

```
Router# show logging
Log Buffer (600000 bytes):
00:12:19:%SYS-5-CONFIG_I:Configured from console by console
00:12:19:%SYS-5-CONFIG_I:Configured from console by console
00:12:20:0x639F6EEC :State change from (STATE_NONE, SUBSTATE_NONE) to
(STATE_IDLE, SUBSTATE_NONE)
00:12:20:****Adding to UAC table
00:12:20:adding call id 2 to table
00:12:20: Queued event from SIP SPI :SIPSPI_EV_CC_CALL_SETUP
00:12:20:CCSIP-SPI-CONTROL: act_idle_call_setup
00:12:20: act_idle_call_setup:Not using Voice Class Codec
00:12:20:act_idle_call_setup:preferred_codec set[0] type :g711ulaw
bytes:160
00:12:20:sipSPICopyPeerDataToCCB:From CLI:Modem NSE payload = 100,
Passthrough = 0,Modem relay = 0, Gw-Xid = 1
SPRT latency 200, SPRT Retries = 12, Dict Size = 1024
String Len = 32, Compress dir = 3
00:12:20:sipSPICanSetFallbackFlag - Local Fallback is not active
00:12:20:****Deleting from UAC table
00:12:20:****Adding to UAC table
00:12:20: Queued event from SIP SPI :SIPSPI_EV_CREATE_CONNECTION
00:12:20:0x639F6EEC :State change from (STATE_IDLE, SUBSTATE_NONE) to
(STATE_IDLE, SUBSTATE_CONNECTING)
00:12:20:0x639F6EEC :State change from (STATE_IDLE,
SUBSTATE_CONNECTING) to (STATE_IDLE, SUBSTATE_CONNECTING)
00:12:20:sipSPIUsetBillingProfile:sipCallId for billing records =
41585FCE-14F011CC-8005AF80-D4AA3153@172.31.1.42
00:12:20:CCSIP-SPI-CONTROL: act_idle_connection_created
00:12:20:CCSIP-SPI-CONTROL: act_idle_connection_created:Connid(1)
created to 172.31.1.15:5060, local_port 57838
00:12:20:CCSIP-SPI-CONTROL: sipSPIOutgoingCallSDP
00:12:20:sipSPISetMediaSrcAddr: media src addr for stream 1 = 10.1.1.42
00:12:20:sipSPIReserveRtpPort:reserved port 18978 for stream 1
00:12:20: convert_codec_bytes_to_ptime:Values :Codec:g711ulaw
codecbytes :160, ptime:20
00:12:20:sip_generate_sdp_xcaps_list:Modem Relay disabled. X-cap not
needed
00:12:20:Received Octet3A=0x00 -> Setting ;screen=no ;privacy=off
00:12:20:sipSPIAddLocalContact
00:12:20: Queued event from SIP SPI :SIPSPI_EV_SEND_MESSAGE
00:12:20:sip_stats_method
00:12:20:sipSPIProcessRtpSessions
00:12:20:sipSPIAddStream:Adding stream 1 (callid 2) to the VOIP RTP
library
00:12:20:sipSPISetMediaSrcAddr: media src addr for stream 1 = 10.1.1.42
00:12:20:sipSPIUpdateRtcpSession:for m-line 1
00:12:20:sipSPIUpdateRtcpSession:rtcp_session info
laddr = 10.1.1.42, lport = 18978, raddr = 0.0.0.0,
rport=0, do_rtcp=FALSE
src_callid = 2, dest_callid = -1
00:12:20:sipSPIUpdateRtcpSession:No rtp session, creating a new one
00:12:20:sipSPIAddStream:In State Idle
00:12:20:act_idle_connection_created:Transaction active. Facilities will
be queued.
00:12:20:0x639F6EEC :State change from (STATE_IDLE,
SUBSTATE_CONNECTING) to (STATE_SENT_INVITE, SUBSTATE_NONE)
00:12:20:Sent:
INVITE sip:222@172.31.1.15:5060 SIP/2.0
Via:SIP/2.0/UDP 10.1.1.42:5060
From:"111" <sip:111@172.31.1.42>;tag=B4DC4-9E1
To:<sip:222@172.31.1.15>
Date:Mon, 01 Mar 1993 00:12:20 GMT
Call-ID:41585FCE-14F011CC-8005AF80-D4AA3153@172.31.1.42
Supported:timer
Min-SE: 1800
```

```

Cisco-Guid:1096070726-351277516-2147659648-3567923539
User-Agent: Cisco-SIPGateway/IOS-12.x
Allow: INVITE, OPTIONS, BYE, CANCEL, ACK, PRACK, COMET, REFER, SUBSCRIBE,
NOTIFY, INFO
CSeq: 101 INVITE
Max-Forwards: 6
Remote-Party-ID: <sip:111@172.31.1.42>;party=calling;screen=no;privacy=off
Timestamp: 730944740
Contact: <sip:111@172.31.1.42:5060>
Expires: 180
Allow-Events: telephone-event
Content-Type: application/sdp
Content-Length: 230
v=0
o=CiscoSystemsSIP-GW-UserAgent 4629 354 IN IP4 172.31.1.42
s=SIP Call
c=IN IP4 172.31.1.42
t=0 0
m=audio 18978 RTP/AVP 0 100
c=IN IP4 10.1.1.42
a=rtpmap:0 PCMU/8000
a=rtpmap:100 X-NSE/8000
a=fmtp:100 192-194
aptime:20
00:12:21:Received:
SIP/2.0 100 Trying
Via: SIP/2.0/UDP 10.1.1.42:5060
From: "111" <sip:111@172.31.1.42>;tag=B4DC4-9E1
To: <sip:222@172.31.1.15>;tag=442AC-22
Date: Wed, 16 Feb 2000 18:19:56 GMT
Call-ID: 41585FCE-14F011CC-8005AF80-D4AA3153@172.31.1.42
Timestamp: 730944740
Server: Cisco-SIPGateway/IOS-12.x
CSeq: 101 INVITE
Allow-Events: telephone-event
Content-Length: 0
00:12:21:HandleUdpSocketReads :Msg enqueued for SPI with IPaddr:
10.1.1.15:5060
00:12:21:CCSIP-SPI-CONTROL: act_sentininvite_new_message
00:12:21:CCSIP-SPI-CONTROL: sipSPICheckResponse
00:12:21:sip_stats_status_code
00:12:21: Roundtrip delay 420 milliseconds for method INVITE
00:12:21:0x639F6EEC :State change from (STATE_SENT_INVITE,
SUBSTATE_NONE) to (STATE_REC'D_PROCEEDING, SUBSTATE_PROCEEDING_PROCEEDING)
00:12:21:Received:
SIP/2.0 180 Ringing
Via: SIP/2.0/UDP 10.1.1.42:5060
From: "111" <sip:111@10.1.1.42>;tag=B4DC4-9E1
To: <sip:222@172.31.1.15>;tag=442AC-22
Date: Wed, 16 Feb 2000 18:19:56 GMT
Call-ID: 41585FCE-14F011CC-8005AF80-D4AA3153@172.31.1.42
Timestamp: 730944740
Server: Cisco-SIPGateway/IOS-12.x
CSeq: 101 INVITE
Allow-Events: telephone-event
Contact: <sip:222@172.31.1.59:5060>
Record-Route: <sip:222@10.1.1.15:5060;maddr=10.1.1.15>
Content-Length: 230
Content-Type: application/sdp
v=0
o=CiscoSystemsSIP-GW-UserAgent 4629 354 IN IP4 10.1.1.42
s=SIP Call
c=IN IP4 10.1.1.42
t=0 0
m=audio 18978 RTP/AVP 0 100
c=IN IP4 10.1.1.42
a=rtpmap:0 PCMU/8000
a=rtpmap:100 X-NSE/8000
a=fmtp:100 192-194
aptime:20
00:12:21:HandleUdpSocketReads :Msg enqueued for SPI with IPaddr:
10.1.1.15:5060
00:12:21:CCSIP-SPI-CONTROL: act_recdproc_new_message

```

```

00:12:21:CCSIP-SPI-CONTROL: act_recdproc_new_message_response
00:12:21:CCSIP-SPI-CONTROL: sipSPICheckResponse
00:12:21:sip_stats_status_code
00:12:21: Roundtrip delay 496 milliseconds for method INVITE
00:12:21:CCSIP-SPI-CONTROL: act_recdproc_new_message_response :Early
media disabled for 180:Ignoring SDP if present
00:12:21:HandleSIPxxxRinging:SDP in 180 will be ignored if present: No
early media cut through
00:12:21:HandleSIPxxxRinging:SDP Body either absent or ignored in 180
RINGING:- would wait for 200 OK to do negotiation.
00:12:21:HandleSIPxxxRinging:MediaNegotiation expected in 200 OK
00:12:21:sipSPIGetGtdBody:No valid GTD body found.
00:12:21:sipSPICreateRawMsg:No GTD passed.
00:12:21:0x639F6EEC :State change from (STATE_REC'D_PROCEEDING,
SUBSTATE_PROCEEDING_PROCEEDING) to (STATE_REC'D_PROCEEDING,
SUBSTATE_PROCEEDING_ALERTING)
00:12:21:HandleSIPxxxRinging:Transaction Complete. Lock on Facilities
released.
00:12:22:Received:
SIP/2.0 200 OK
Via:SIP/2.0/UDP 10.1.1.42:5060
From:"111" <sip:111@10.1.1.42>;tag=B4DC4-9E1
To:<sip:222@10.1.1.15>;tag=442AC-22
Date:Wed, 16 Feb 2000 18:19:56 GMT
Call-ID:41585FCE-14F011CC-8005AF80-D4AA3153@172.31.1.42
Timestamp:730944740
Server:Cisco-SIPGateway/IOS-12.x
CSeq:101 INVITE
Allow:INVITE, OPTIONS, BYE, CANCEL, ACK, PRACK, COMET, REFER, SUBSCRIBE,
NOTIFY, INFO
Allow-Events:telephone-event
Contact:<sip:222@10.1.1.59:5060>
Record-Route:<sip:222@10.1.1.15:5060;maddr=10.1.1.15>
Content-Type:application/sdp
Content-Length:231
v=0
o=CiscoSystemsSIP-GW-UserAgent 9600 4816 IN IP4 10.1.1.59
s=SIP Call
c=IN IP4 10.1.1.59
t=0 0
m=audio 19174 RTP/AVP 0 100
c=IN IP4 10.1.1.59
a=rtpmap:0 PCMU/8000
a=rtpmap:100 X-NSE/8000
a=fmtp:100 192-194
a=ptime:20

```

Feature Information for SIP Enhanced 180 Provisional Response Handling

The following table provides release information about the feature or features described in this module. This table lists only the software release that introduced support for a given feature in a given software release train. Unless noted otherwise, subsequent releases of that software release train also support that feature.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Feature Information Table for the ISR

Table 28 **Feature Information for SIP :Enhanced 180 Provisional Response Handling**

Feature Name	Releases	Feature Information
SIP - Enhanced 180 Provisional Response Handling	12.2(11)T 12.2(8)YN 12.2(15)T 12.2(11)YV 12.2(11)T	The Session Initiation Protocol (SIP) Enhanced 180 Provisional Response Handling feature provides the ability to enable or disable early media cut-through on Cisco IOS gateways for SIP 180 response messages. The following commands were introduced or modified: disable-early-media 180 and show sip-ua status .

Feature Information Table for the ASR

Table 29 **Feature Information for SIP: Enhanced 180 Provisional Response Handling**

Feature Name	Releases	Feature Information
SIP - Enhanced 180 Provisional Response Handling	Cisco IOS XE Release 2.5	The Session Initiation Protocol (SIP) Enhanced 180 Provisional Response Handling feature provides the ability to enable or disable early media cut-through on Cisco IOS gateways for SIP 180 response messages. The following commands were introduced or modified: disable-early-media 180 and show sip-ua status .

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: www.cisco.com/go/trademarks. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.



Configuring SIP 181 Call is Being Forwarded Message

You can configure support for SIP 181 Call is Being Forwarded messages either globally or on a specific dial-peer. Use the **block** command in voice service SIP configuration mode to globally configure Cisco IOS voice gateways and Cisco UBEs to drop specified SIP provisional response messages. To configure settings for an individual dial peer, use the **voice-class sip block** command in dial peer voice configuration mode. Both globally and at the dial peer level, you can also use the **sdp** keyword to further control when the specified SIP message is dropped based on either the absence or presence of SDP information.

Additionally, you can use commands introduced for this feature to configure a Cisco UBE, either globally or at the dial peer level, to map specific received SIP provisional response messages to a different SIP provisional response message on the outgoing SIP dial peer. To do so, use the **map resp-code** command in voice service SIP configuration mode for global configuration or, to configure a specific dial peer, use the **voice-class sip map resp-code** in dial peer voice configuration mode.

This section contains the following tasks:

- [Finding Feature Information, page 91](#)
- [Prerequisites for SIP 181 Call is Being Forwarded Message, page 91](#)
- [Configuring SIP 181 Call is Being Forwarded Message Globally, page 92](#)
- [Configuring SIP 181 Call is Being Forwarded Message at the Dial-Peer Level, page 93](#)
- [Configuring Mapping of SIP Provisional Response Messages Globally, page 94](#)
- [Configuring Mapping of SIP Provisional Response Messages at the Dial-Peer Level, page 95](#)
- [Feature Information for Configuring SIP 181 Call is Being Forwarded Message, page 97](#)

Finding Feature Information

Your software release may not support all the features documented in this module. For the latest feature information and caveats, see the release notes for your platform and software release. To find information about the features documented in this module, and to see a list of the releases in which each feature is supported, see the Feature Information Table at the end of this document.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Prerequisites for SIP 181 Call is Being Forwarded Message

Cisco Unified Border Element

Cisco IOS Release 15.0(1)XA or a later release must be installed and running on your Cisco Unified Border Element.

Cisco Unified Border Element (Enterprise)

- Cisco IOS XE Release 3.1S or a later release must be installed and running on your Cisco ASR 1000 Series Router.

Configuring SIP 181 Call is Being Forwarded Message Globally

Perform this task to configure support for SIP 181 messages at a global level in SIP configuration (conf-serv-sip) mode.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **voice service voip**
4. **sip**
5. **block {180 | 181 | 183} [sdp {absent | present}]**
6. **exit**

DETAILED STEPS

Command or Action	Purpose
Step 1 enable Example: Router> enable	Enters privileged EXEC mode, or other security level set by a system administrator. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2 configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3 voice service voip Example: Router(config)# voice service voip	Enters voice service VoIP configuration mode.

Command or Action	Purpose
Step 4 sip Example: Router(conf-voi-serv)# sip	Enters SIP configuration mode.
Step 5 block {180 181 183} [sdp {absent present}] Example: Router(conf-serv-sip)# block 181 sdp present	Configures support of SIP 181 messages globally so that messages are passed as is. The sdp keyword is optional and allows for dropping or passing of SIP 181 messages based on the presence or absence of SDP.
Step 6 exit Example: Router(conf-serv-sip)# exit	Exits the current mode.

Configuring SIP 181 Call is Being Forwarded Message at the Dial-Peer Level

Perform this task to configure support for SIP 181 messages at the dial-peer level, in dial peer voice configuration (config-dial-peer) mode.

SUMMARY STEPS

1. enable
2. configure terminal
3. dial-peer voice *tag* voip
4. voice-class sip block {180 | 181 | 183} [sdp {absent | present}]
5. exit

DETAILED STEPS

Command or Action	Purpose
Step 1 enable Example: Router> enable	Enters privileged EXEC mode, or other security level set by a system administrator. <ul style="list-style-type: none"> • Enter your password if prompted.

Command or Action	Purpose
Step 2 <code>configure terminal</code> Example: <pre>Router# configure terminal</pre>	Enters global configuration mode.
Step 3 <code>dial-peer voice tag voip</code> Example: <pre>Router(config)# dial-peer voice 2 voip</pre>	Enters dial peer VoIP configuration mode.
Step 4 <code>voice-class sip block {180 181 183} [sdp {absent present}]</code> Example: <pre>Router(config-dial-peer)# voice-class sip block 181 sdp present</pre>	Configures support of SIP 181 messages on a specific dial peer so that messages are passed as is. The sdp keyword is optional and allows for dropping or passing of SIP 181 messages based on the presence or absence of SDP.
Step 5 <code>exit</code> Example: <pre>Router(config-dial-peer)# exit</pre>	Exits the current mode.

Configuring Mapping of SIP Provisional Response Messages Globally

Perform this task to configure mapping of specific received SIP provisional response messages at a global level in SIP configuration (conf-serv-sip) mode.

SUMMARY STEPS

1. `enable`
2. `configure terminal`
3. `voice service voip`
4. `sip`
5. `map resp-code 181 to 183`
6. `exit`

DETAILED STEPS

Command or Action	Purpose
<p>Step 1 <code>enable</code></p> <p>Example:</p> <pre>Router> enable</pre>	<p>Enters privileged EXEC mode, or other security level set by a system administrator.</p> <ul style="list-style-type: none"> Enter your password if prompted.
<p>Step 2 <code>configure terminal</code></p> <p>Example:</p> <pre>Router# configure terminal</pre>	<p>Enters global configuration mode.</p>
<p>Step 3 <code>voice service voip</code></p> <p>Example:</p> <pre>Router(config)# voice service voip</pre>	<p>Enters voice service VoIP configuration mode.</p>
<p>Step 4 <code>sip</code></p> <p>Example:</p> <pre>Router(conf-voi-serv)# sip</pre>	<p>Enters SIP configuration mode.</p>
<p>Step 5 <code>map resp-code 181 to 183</code></p> <p>Example:</p> <pre>Router(conf-serv-sip)# map resp-code 181 to 183</pre>	<p>Enables mapping globally of received SIP messages of a specified message type to a different SIP message type.</p>
<p>Step 6 <code>exit</code></p> <p>Example:</p> <pre>Router(conf-serv-sip)# exit</pre>	<p>Exits the current mode.</p>

Configuring Mapping of SIP Provisional Response Messages at the Dial-Peer Level

Perform this task to configure mapping of received SIP provisional response messages at the dial-peer level, in dial peer voice configuration (config-dial-peer) mode.

SUMMARY STEPS

1. enable
2. configure terminal
3. dial-peer voice *tag* voip
4. voice-class sip map resp-code 181 to 183
5. exit

DETAILED STEPS

Command or Action	Purpose
Step 1 enable Example: <pre>Router> enable</pre>	Enters privileged EXEC mode, or other security level set by a system administrator. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2 configure terminal Example: <pre>Router# configure terminal</pre>	Enters global configuration mode.
Step 3 dial-peer voice <i>tag</i> voip Example: <pre>Router(config)# dial-peer voice 2 voip</pre>	Enters dial peer VoIP configuration mode.
Step 4 voice-class sip map resp-code 181 to 183 Example: <pre>Router(config-dial-peer)# voice-class sip map resp-code 181 to 183</pre>	Enables mapping of received SIP messages of a specified SIP message type on a specific dial peer to a different SIP message type.
Step 5 exit Example: <pre>Router(config-dial-peer)# exit</pre>	Exits the current mode.

Feature Information for Configuring SIP 181 Call is Being Forwarded Message

The following table provides release information about the feature or features described in this module. This table lists only the software release that introduced support for a given feature in a given software release train. Unless noted otherwise, subsequent releases of that software release train also support that feature.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Feature History Table entry for the Cisco Unified Border Element.

Table 30 Feature Information for SIP 181 Call is Being Forwarded Messages

Feature Name	Releases	Feature Information
SIP 181 Call is Being Forwarded Message	12.2(13)T	<p>This feature allows users to configure support for SIP 181 Call is Being Forwarded messages either globally or on a specific dial-peer.</p> <p>This feature includes the following new or modified commands: block, map resp-code, voice-class sip block, voice-class sip map resp-code.</p>

Feature History Table entry for the Cisco Unified Border Element (Enterprise).

Table 31 Feature Information for SIP 181 Call is Being Forwarded Messages

Feature Name	Releases	Feature Information
SIP 181 Call is Being Forwarded Message	Cisco IOS XE Release 3.1S	<p>This feature allows users to configure support for SIP 181 Call is Being Forwarded messages either globally or on a specific dial-peer.</p> <p>This feature includes the following new or modified commands: block, map resp-code, voice-class sip block, voice-class sip map resp-code.</p>

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: www.cisco.com/go/trademarks.

Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.



Expires Timer Reset on Receiving or Sending SIP 183 Message

This feature enables support for resetting the Expires timer when receiving or sending SIP 183 messages on Cisco Unified Communications Manager Express (Cisco Unified CME), a Cisco IOS voice gateway, or a Cisco Unified Border Element (Cisco UBE). When the terminating device lacks answer supervision or does not send the required SIP 200 OK message within the timer expiry, you can enable this feature to send periodic SIP 183 messages to reset the Expires timer and preserve the call until final response. This feature can be enabled globally or on a specific dial peer. Additionally, you can configure this feature based on the presence or absence of Session Description Protocol (SDP).

For details about enabling this feature, see the **reset timer expires** and **voice-class sip reset timer expires** commands in the Cisco IOS Voice Command Reference.

- [Finding Feature Information, page 99](#)
- [Prerequisites for Expires Timer Reset on Receiving or Sending SIP 183 Message, page 99](#)
- [How to Configure Expires Timer Reset on Receiving or Sending SIP 183 Message, page 100](#)
- [Feature Information for Configuring Support for Expires Timer Reset on Receiving or Sending SIP 183 Message, page 102](#)

Finding Feature Information

Your software release may not support all the features documented in this module. For the latest feature information and caveats, see the release notes for your platform and software release. To find information about the features documented in this module, and to see a list of the releases in which each feature is supported, see the Feature Information Table at the end of this document.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Prerequisites for Expires Timer Reset on Receiving or Sending SIP 183 Message

Before configuring support for Expires timer reset for SIP 183 on Cisco IOS SIP time-division multiplexing (TDM) gateways, Cisco UBEs, or Cisco Unified CME, verify the SIP configuration within the VoIP network for the appropriate originating and terminating gateways as described in the Cisco IOS SIP Configuration Guide.

Cisco Unified Border Element

- Cisco IOS Release 15.0(1)XA or a later release must be installed and running on your Cisco Unified Border Element.

Cisco Unified Border Element (Enterprise)

- Cisco IOS XE Release 3.1S or a later release must be installed and running on your Cisco ASR 1000 Series Router.

How to Configure Expires Timer Reset on Receiving or Sending SIP 183 Message

To configure the Support for Expires Timer Reset on Receiving or Sending SIP 183 Message feature, complete the tasks in this section. You can enable this feature globally, using the **reset timer expires** command in voice service SIP configuration mode, or on a specific dial-peer using the **voice-class sip reset timer expires** command in dial peer voice configuration mode.

- [Configuring Reset of Expires Timer Globally, page 100](#)
- [Configuring Reset of Expires Timer at the Dial-Peer Level, page 101](#)

Configuring Reset of Expires Timer Globally

Perform this task to enable resetting of the Expires timer at the global level in SIP configuration (conf-serv-sip) mode.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **voice service voip**
4. **sip**
5. **reset timer expires 183**
6. **exit**

DETAILED STEPS

	Command or Action	Purpose
Step 1	enable	Enables privileged EXEC mode.
	Example:	
	Router> enable	<ul style="list-style-type: none"> • Enter your password if prompted.

Command or Action	Purpose
Step 2 <code>configure terminal</code> Example: <pre>Router# configure terminal</pre>	Enters global configuration mode.
Step 3 <code>voice service voip</code> Example: <pre>Router(config)# voice service voip</pre>	Enters voice service VoIP configuration mode.
Step 4 <code>sip</code> Example: <pre>Router(conf-voi-serv)# sip</pre>	Enters SIP configuration mode.
Step 5 <code>reset timer expires 183</code> Example: <pre>Router(conf-serv-sip)# reset timer expires 183</pre>	Enables resetting of the Expires timer upon receipt of SIP 183 messages globally.
Step 6 <code>exit</code> Example: <pre>Router(conf-serv-sip)# exit</pre>	Exits the current mode.

Configuring Reset of Expires Timer at the Dial-Peer Level

Perform this task to enable resetting of the Expires timer at the dial-peer level in dial peer voice configuration (config-dial-peer) mode.

SUMMARY STEPS

1. `enable`
2. `configure terminal`
3. `dial-peer voice tag voip`
4. `voice-class sip reset timer expires 183`
5. `exit`

DETAILED STEPS

Command or Action	Purpose
Step 1 enable Example: <pre>Router> enable</pre>	Enables privileged EXEC mode. <ul style="list-style-type: none"> Enter your password if prompted.
Step 2 configure terminal Example: <pre>Router# configure terminal</pre>	Enters global configuration mode.
Step 3 dial-peer voice tag voip Example: <pre>Router(config)# dial-peer voice 2 voip</pre>	Enters dial peer VoIP configuration mode.
Step 4 voice-class sip reset timer expires 183 Example: <pre>Router(config-dial-peer)# voice-class sip reset timer expires 183</pre>	Enables resetting of the Expires timer upon receipt of SIP 183 messages on a specific dial peer.
Step 5 exit Example: <pre>Router(config-dial-peer)# exit</pre>	Exits the current mode.

Feature Information for Configuring Support for Expires Timer Reset on Receiving or Sending SIP 183 Message

The following table provides release information about the feature or features described in this module. This table lists only the software release that introduced support for a given feature in a given software release train. Unless noted otherwise, subsequent releases of that software release train also support that feature.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Feature History Table entry for the Cisco Unified Border Element.

Table 32 Feature Information for Support for Expires Timer Reset on Receiving or Sending SIP 183 Message

Feature Name	Releases	Feature Information
Support for Expires Timer Reset on Receiving or Sending SIP 183 Message	15.0(1)XA 15.1(1)T	<p>This feature enables support for resetting the Expires timer upon receipt of SIP 183 messages on Cisco Unified Communications Manager Express (Cisco Unified CME), a Cisco IOS voice gateway, or a Cisco Unified Border Element (Cisco UBE).</p> <p>The following commands were introduced or modified: reset timer expires and voice-class sip reset timer expires.</p>

Feature History Table entry for the Cisco Unified Border Element (Enterprise) .

Table 33 Feature Information for Support for Expires Timer Reset on Receiving or Sending SIP 183 Message

Feature Name	Releases	Feature Information
Support for Expires Timer Reset on Receiving or Sending SIP 183 Message	Cisco IOS XE Release 3.1S	<p>This feature enables support for resetting the Expires timer upon receipt of SIP 183 messages on Cisco Unified Communications Manager Express (Cisco Unified CME), a Cisco IOS voice gateway, or a Cisco Unified Border Element (Cisco UBE).</p> <p>The following commands were introduced or modified: reset timer expires and voice-class sip reset timer expires.</p>

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: www.cisco.com/go/trademarks. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.



SIP UPDATE Message per RFC 3311

The SIP UPDATE Message per RFC 3311 feature provides Session Description Protocol (SDP) support for Session Initiation Protocol (SIP)-to-SIP calls. The SIP Service Provider Interface (SPI) is modified to support the following media changes using the UPDATE message:

- Early dialog SIP-to-SIP media changes.
- Mid dialog SIP-to-SIP media changes.

The Support for SIP UPDATE Message Per RFC 3311 feature is enabled by default on the Cisco Unified Border Element (UBE) and no configuration is required.

- [Finding Feature Information, page 105](#)
- [Prerequisites for SIP UPDATE Message per RFC 3311, page 105](#)
- [Restrictions, page 106](#)
- [Feature Information for the SIP UPDATE Message per RFC 3311, page 106](#)

Finding Feature Information

Your software release may not support all the features documented in this module. For the latest feature information and caveats, see the release notes for your platform and software release. To find information about the features documented in this module, and to see a list of the releases in which each feature is supported, see the Feature Information Table at the end of this document.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Prerequisites for SIP UPDATE Message per RFC 3311

- At least one offer or answer negotiation must be completed for Cisco UBE to handle the UPDATE message with SDP.
- An early dialog UPDATE message with SDP is processed only when both endpoints support the UPDATE message.

Cisco Unified Border Element

- Cisco IOS Release 15.1(3)T or a later release must be installed and running on your Cisco Unified Border Element.

Cisco Unified Border Element (Enterprise)

- Cisco IOS XE Release <TBD> or a later release must be installed and running on your Cisco ASR 1000 Series Router.

Restrictions

- An UPDATE message with SDP is not supported for SIP-to-H323 calls.
- An UPDATE message with SDP with a fully qualified domain name (FQDN) is not supported.
- Contact information in the UPDATE message is not supported.
- A retransmitted UPDATE message with SDP is ignored by the SIP stack. No response is sent for retransmitted UPDATE messages.

Feature Information for the SIP UPDATE Message per RFC 3311

The following table provides release information about the feature or features described in this module. This table lists only the software release that introduced support for a given feature in a given software release train. Unless noted otherwise, subsequent releases of that software release train also support that feature.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

The table below lists the release history for the ISR.

Table 34 Feature Information for Support for SIP UPDATE Message per RFC 3311

Feature Name	Releases	Feature Information
Support for SIP UPDATE Message per RFC 3311	15.1(3)T	<p>The Support for SIP UPDATE Message per RFC 3311 feature provides Session Description Protocol (SDP) support for Session Initiation Protocol (SIP)-to-SIP calls. The SIP Service Provider Interface (SPI) is modified to support the following media changes using the UPDATE message:</p> <ul style="list-style-type: none"> • Early dialog SIP-to-SIP media changes. • Mid dialog SIP-to-SIP media changes.

The table below lists the release history for the ASR.

Table 35 **Feature Information for Support for SIP UPDATE Message per RFC 3311**

Feature Name	Releases	Feature Information
Support for SIP UPDATE Message per RFC 3311	TBD	<p>The Support for SIP UPDATE Message per RFC 3311 feature provides Session Description Protocol (SDP) support for Session Initiation Protocol (SIP)-to-SIP calls. The SIP Service Provider Interface (SPI) is modified to support the following media changes using the UPDATE message:</p> <ul style="list-style-type: none"> • Early dialog SIP-to-SIP media changes. • Mid dialog SIP-to-SIP media changes.

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: www.cisco.com/go/trademarks. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)


Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.



Support for PAID PPID Privacy PCPID and PAURI Headers on the Cisco Unified Border Element

The figure below shows a typical network topology where the Cisco Unified Border Element is configured to route messages between a call manager system (such as the Cisco Unified Call Manager) and a Next Generation Network (NGN).

Figure 1 Cisco Unified Border Element and Next Generation Topology



Devices that connect to an NGN must comply with the User-Network Interface (UNI) specification. The Cisco Unified Border Element supports the NGN UNI specification and can be configured to interconnect NGN with other call manager systems, such as the Cisco Unified Call Manager.

The Cisco Unified Border Element supports the following:

- the use of P-Preferred Identity (PPID), P-Asserted Identity (PAID), Privacy, P-Called Party Identity (PCPID), in INVITE messages
- the translation of PAID headers to PPID headers and vice versa
- the translation of From: or RPID headers to PAID or PPID headers and vice versa
- the configuration and/or pass through of privacy header values
- the use of the PCPID header to route INVITE messages
- the use of multiple PAURI headers in the response messages (200 OK) it receives to REGISTER messages

P-Preferred Identity and P-Asserted Identity Headers

NGN servers use the PPID header to identify the preferred number that the caller wants to use. The PPID is part of INVITE messages sent to the NGN. When the NGN receives the PPID, it authorizes the value, generates a PAID based on the preferred number, and inserts it into the outgoing INVITE message towards the called party.

However, some call manager systems, such as Cisco Unified Call Manager 5.0, use the Remote-Party Identity (RPID) value to send calling party information. Therefore, the Cisco Unified Border Element

must support building the PPID value for an outgoing INVITE message to the NGN, using the RPID value or the From: value received in the incoming INVITE message. Similarly, CUBE supports building the RPID and/or From: header values for an outgoing INVITE message to the call manager, using the PAID value received in the incoming INVITE message from the NGN.

In non-NGN systems, the Cisco Unified Border Element can be configured to translate between PPID and PAID values, and between From: or RPID values and PAID/PPID values, at global and dial-peer levels.

In configurations where all relevant servers support the PPID or PAID headers, the Cisco Unified Border Element can be configured to transparently pass the header.

**Note**

If the NGN sets the From: value to anonymous, the PAID is the only value that identifies the caller.

The table below describes the types of INVITE message header translations supported by the Cisco Unified Border Element. It also includes information on the configuration commands to use to configure P-header translations.

The table below shows the P-header translation configuration settings only. In addition to configuring these settings, you must configure other system settings (such as the session protocol).

Table 36 *P-header Configuration Settings*

Incoming Header	Outgoing Header	Configuration Notes
From:	PPID	<p>To enable the translation to PPID headers in the outgoing header at a global level, use the asserted-id ppi command in voice service VoIP SIP configuration mode. For example: Router(conf-serv-sip)# asserted-id ppi</p> <p>To enable the translation to PPID headers in the outgoing header on a specific dial peer, use the voice-class sip asserted-id ppi command in dial peer voice configuration mode. For example: Router(config-dial-peer)# voice-class sip asserted-id ppi</p>

Incoming Header	Outgoing Header	Configuration Notes
From:	PAID	<p>To enable the translation to PAID headers in the outgoing header at a global level, use the asserted-id pai command in voice service VoIP SIP configuration mode. For example: Router(conf-serv-sip)# asserted-id pai</p> <p>To enable the translation to PAID headers in the outgoing header on a specific dial peer, use the voice-class sip asserted-id pai command in dial peer voice configuration mode. For example: Router(config-dial-peer)# voice-class sip asserted-id pai</p>
From:	RPID	<p>To enable the translation to RPID headers in the outgoing header, use the remote-party-id command in SIP user-agent configuration mode. For example: Router(config-sip-ua)# remote-party-id</p> <p>This is the default system behavior.</p> <p>Note If both, remote-party-id and asserted-id commands are configured, then the asserted-id command takes precedence over the remote-part-id command.</p>

Incoming Header	Outgoing Header	Configuration Notes
PPID	PAID	<p>To enable the translation to PAID privacy headers in the outgoing header at a global level, use the asserted-id pai command in voice service VoIP SIP configuration mode. For example: Router(conf-serv-sip)# asserted-id pai</p> <p>To enable the translation to PAID privacy headers in the outgoing header on a specific dial peer, use the voice-class sip asserted-id pai command in dial peer voice configuration mode. For example: Router(config-dial-peer)# voice-class sip asserted-id pai</p>
PPID	From:	<p>By default, the translation to RPID headers is enabled and the system translates PPID headers in incoming messages to RPID headers in the outgoing messages. To disable the default behavior and enable the translation from PPID to From: headers, use the no remote-party-id command in SIP user-agent configuration mode. For example: Router(config-sip-ua)# no remote-party-id</p>
PPID	RPID	<p>To enable the translation to RPID headers in the outgoing header, use the remote-party-id command in SIP user-agent configuration mode. For example: Router(config-sip-ua)# remote-party-id</p> <p>This is the default system behavior.</p>

Incoming Header	Outgoing Header	Configuration Notes
PAID	PPID	<p>To enable the translation to PPID privacy headers in the outgoing header at a global level, use the asserted-id ppi command in voice service VoIP SIP configuration mode. For example: Router(conf-serv-sip)# asserted-id ppi</p> <p>To enable the translation to PPID privacy headers in the outgoing header on a specific dial peer, use the voice-class sip asserted-id ppi command in dial peer voice configuration mode. For example: Router(config-dial-peer)# voice-class sip asserted-id ppi</p>
PAID	From:	<p>By default, the translation to RPID headers is enabled and the system translates PPID headers in incoming messages to RPID headers in the outgoing messages. To disable the default behavior and enable the translation from PPID to From: headers, use the no remote-party-id command in SIP user-agent configuration mode. For example: Router(config-sip-ua)# no remote-party-id</p>
PAID	RPID	<p>To enable the translation to RPID headers in the outgoing header, use the remote-party-id command in SIP user-agent configuration mode. For example: Router(config-sip-ua)# remote-party-id</p> <p>This is the default system behavior.</p>

Incoming Header	Outgoing Header	Configuration Notes
RPID	PPID	<p>To enable the translation to PPID privacy headers in the outgoing header at a global level, use the asserted-id ppi command in voice service VoIP SIP configuration mode. For example: Router(conf-serv-sip)# asserted-id ppi</p> <p>To enable the translation to PPID privacy headers in the outgoing header on a specific dial peer, use the voice-class sip asserted-id ppi command in dial peer voice configuration mode. For example: Router(config-dial-peer)# voice-class sip asserted-id ppi</p>
RPID	PAID	<p>To enable the translation to PAID privacy headers in the outgoing header at a global level, use the asserted-id pai command in voice service VoIP SIP configuration mode. For example: Router(conf-serv-sip)# asserted-id pai</p> <p>To enable the translation to PAID privacy headers in the outgoing header on a specific dial peer, use the voice-class sip asserted-id pai command in dial peer voice configuration mode. For example: Router(config-dial-peer)# voice-class sip asserted-id pai</p>

Incoming Header	Outgoing Header	Configuration Notes
RPID	From:	By default, the translation to RPID headers is enabled and the system translates PPID headers in incoming messages to RPID headers in the outgoing messages. To disable the default behavior and enable the translation from PPID to From: headers, use the no remote-party-id command in SIP user-agent configuration mode. For example: Router(config-sip-ua)# no remote-party-id

Privacy

If the user is subscribed to a privacy service, the Cisco Unified Border Element can support privacy using one of the following methods:

- Using prefixes

The NGN dial plan can specify prefixes to enable privacy settings. For example, the dial plan may specify that if the caller dials a prefix of 184, the calling number is not sent to the called party.

The dial plan may also specify that the caller can choose to send the calling number to the called party by dialing a prefix of 186. Here, the Cisco Unified Border Element transparently passes the prefix as part of the called number in the INVITE message.

The actual prefixes for the network are specified in the dial plan for the NGN, and can vary from one NGN to another.

- Using the Privacy header

If the Privacy header is set to None, the calling number is delivered to the called party. If the Privacy header is set to a Privacy:id value, the calling number is not delivered to the called party.

- Using Privacy values from the peer call leg

If the incoming INVITE has a Privacy header or a RPID with privacy on, the outgoing INVITE can be set to Privacy: id. This behavior is enabled by configuring **privacy pstn** command globally or **voice-class sip privacy pstn** command on the selected dial-per.

Incoming INVITE can have multiple privacy header values, id, user, session, and so on. Configure the **privacy-policy passthru** command globally or **voice-class sip privacy-policy passthru** command to transparently pass across these multiple privacy header values.

Some NGN servers require a Privacy header to be sent even though privacy is not required. In this case the Privacy header must be set to none. The Cisco Unified Border Element can add a privacy header with the value None while forwarding the outgoing INVITE to NGN. Configure the **privacy-policy send-always** globally or **voice-class sip privacy-policy send-always** command in dial-peer to enable this behavior.

If the user is not subscribed to a privacy service, the Cisco Unified Border Element can be configured with no Privacy settings.

P-Called Party Identity

The Cisco Unified Border Element can be configured to use the PCPID header in an incoming INVITE message to route the call, and to use the PCPID value to set the To: value of outgoing INVITE messages.

The PCPID header is part of the INVITE messages sent by the NGN, and is used by Third Generation Partnership Project (3GPP) networks. The Cisco Unified Border Element uses the PCPID from incoming INVITE messages (from the NGN) to route calls to the Cisco Unified Call Manager.

**Note**

The PCPID header supports the use of E.164 numbers only.

P-Associated URI

The Cisco Unified Border Element supports the use of PAURI headers sent as part of the registration process. After the Cisco Unified Border Element sends REGISTER messages using the configured E.164 number, it receives a 200 OK message with one or more PAURIs. The number in the first PAURI (if present) must match the contract number. The Cisco Unified Border Element supports a maximum of six PAURIs for each registration.

**Note**

The Cisco Unified Border Element performs the validation process only when a PAURI is present in the 200 OK response.

The registration validation process works as follows:

- The Cisco Unified Border Element receives a REGISTER response message that includes PAURI headers that include the contract number and up to five secondary numbers.
- The Cisco Unified Border Element validates the contract number against the E.164 number that it is registering:
 - If the values match, the Cisco Unified Border Element completes the registration process and stores the PAURI value. This allows administration tools to view or retrieve the PAURI if needed.
 - If the values do not match, the Cisco Unified Border Element unregisters and then reregisters the contract number. The Cisco Unified Border Element performs this step until the values match.

Random Contact Support

The Cisco Unified Border Element can use random-contact information in REGISTER and INVITE messages so that user information is not revealed in the contact header.

To provide random contact support, the Cisco Unified Border Element performs SIP registration based on the random-contact value. The Cisco Unified Border Element then populates outgoing INVITE requests with the random-contact value and validates the association between the called number and the random value in the Request-URI of the incoming INVITE. The Cisco Unified Border Element routes calls based on the PCPID, instead of the Request-URI which contains the random value used in contact header of the REGISTER message.

The default contact header in REGISTER messages is the calling number. The Cisco Unified Border Element can generate a string of 32 random alphanumeric characters to replace the calling number in the REGISTER contact header. A different random character string is generated for each pilot or contract number being registered. All subsequent registration requests will use the same random character string.

The Cisco Unified Border Element uses the random character string in the contact header for INVITE messages that it forwards to the NGN. The NGN sends INVITE messages to the Cisco Unified Border

Element with random-contact information in the Request URI. For example: INVITE sip:FefhH3zIHe9i8ImcGjDD1PEc5XfFy51G@10.12.1.46:5060.

The Cisco Unified Border Element will not use the To: value of the incoming INVITE message to route the call because it might not identify the correct user agent if supplementary services are invoked. Therefore, the Cisco Unified Border Element must use the PCPID to route the call to the Cisco Unified Call Manager. You can configure routing based on the PCPID at global and dial-peer levels.

- [Finding Feature Information, page 117](#)
- [Prerequisites for Support for PAID PPID Privacy PCPID and PAURI Headers on the Cisco UBE, page 117](#)
- [Restrictions for Support for PAID PPID Privacy PCPID and PAURI Headers on the Cisco UBE, page 117](#)
- [Configuring P-Header and Random-Contact Support on the Cisco Unified Border Element, page 118](#)
- [Feature Information for PAID PPID Privacy PCPID and PAURI Headers on the Cisco Unified Border Element, page 129](#)

Finding Feature Information

Your software release may not support all the features documented in this module. For the latest feature information and caveats, see the release notes for your platform and software release. To find information about the features documented in this module, and to see a list of the releases in which each feature is supported, see the Feature Information Table at the end of this document.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Prerequisites for Support for PAID PPID Privacy PCPID and PAURI Headers on the Cisco UBE

Cisco Unified Border Element

- Cisco IOS Release 12.4(22)YB or a later release must be installed and running on your Cisco Unified Border Element.

Cisco Unified Border Element (Enterprise)

- Cisco IOS XE Release 3.1S or a later release must be installed and running on your Cisco ASR 1000 Series Router.

Restrictions for Support for PAID PPID Privacy PCPID and PAURI Headers on the Cisco UBE

- To enable random-contact support, you must configure the Cisco Unified Border Element to support SIP registration with random-contact information. In addition, you must configure random-contact support in VoIP voice-service configuration mode or on the dial peer.
- If random-contact support is configured for SIP registration only, the system generates the random-contact information, includes it in the SIP REGISTER message, but does not include it in the SIP INVITE message.
- If random-contact support is configured in VoIP voice-service configuration mode or on the dial peer only, no random contact is sent in either the SIP REGISTER or INVITE message.

Configuring P-Header and Random-Contact Support on the Cisco Unified Border Element

To enable random contact support you must configure the Cisco Unified Border Element to support Session Initiation Protocol (SIP) registration with random-contact information, as described in this section.

To enable the Cisco Unified Border Element to use the PCPID header in an incoming INVITE message to route the call, and to use the PCPID value to set the To: value of outgoing INVITE messages, you must configure P-Header support as described in this section.

- [Configuring P-Header Translation on a Cisco Unified Border Element, page 118](#)
- [Configuring P-Header Translation on an Individual Dial Peer, page 119](#)
- [Configuring P-Called-Party-Id Support on a Cisco Unified Border Element, page 120](#)
- [Configuring P-Called-Party-Id Support on an Individual Dial Peer, page 122](#)
- [Configuring Privacy Support on a Cisco Unified Border Element, page 123](#)
- [Configuring Privacy Support on an Individual Dial Peer, page 125](#)
- [Configuring Random-Contact Support on a Cisco Unified Border Element, page 126](#)
- [Configuring Random-Contact Support for an Individual Dial Peer, page 128](#)

Configuring P-Header Translation on a Cisco Unified Border Element

To configure P-Header translations on a Cisco Unified Border Element, perform the steps in this section.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **voice service voip**
4. **sip**
5. **asserted-id *header-type***
6. **exit**

DETAILED STEPS

Command or Action	Purpose
<p>Step 1 <code>enable</code></p> <p>Example:</p> <pre>Router> enable</pre>	<p>Enables privileged EXEC mode.</p> <ul style="list-style-type: none"> Enter your password if prompted.
<p>Step 2 <code>configure terminal</code></p> <p>Example:</p> <pre>Router# configure terminal</pre>	<p>Enters global configuration mode.</p>
<p>Step 3 <code>voice service voip</code></p> <p>Example:</p> <pre>Router(config)# voice service voip</pre>	<p>Enters VoIP voice-service configuration mode.</p>
<p>Step 4 <code>sip</code></p> <p>Example:</p> <pre>Router(conf-voi-serv)# sip</pre>	<p>Enters voice service VoIP SIP configuration mode.</p>
<p>Step 5 <code>asserted-id header-type</code></p> <p>Example:</p> <pre>Router(conf-serv-sip)# asserted-id ppi</pre>	<p>Specifies the type of privacy header in the outgoing SIP requests and response messages.</p>
<p>Step 6 <code>exit</code></p> <p>Example:</p> <pre>Router(conf-serv-sip)# exit</pre>	<p>Exits the current mode.</p>

Configuring P-Header Translation on an Individual Dial Peer

To configure P-Header translation on an individual dial peer, perform the steps in this section.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **dial-peer voice *tag* voip**
4. **voice-class sip asserted-id *header-type***
5. **exit**

DETAILED STEPS

Command or Action	Purpose
Step 1 enable Example: <pre>Router> enable</pre>	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2 configure terminal Example: <pre>Router# configure terminal</pre>	Enters global configuration mode.
Step 3 dial-peer voice <i>tag</i> voip Example: <pre>Router(config)# dial-peer voice 2611 voip</pre>	Defines the dial peer, specifies the method of voice encapsulation, and enters dial peer voice configuration mode.
Step 4 voice-class sip asserted-id <i>header-type</i> Example: <pre>Router(config-dial-peer)# voice-class sip asserted-id ppi</pre>	Specifies the type of privacy header in the outgoing SIP requests and response messages, on this dial peer.
Step 5 exit Example: <pre>Router(config-dial-peer)# exit</pre>	Exits the current mode.

Configuring P-Called-Party-Id Support on a Cisco Unified Border Element

To configure P-Called-Party-Id support on a Cisco Unified Border Element, perform the steps in this section.

SUMMARY STEPS

1. enable
2. configure terminal
3. voice service voip
4. sip
5. call-route p-called-party-id
6. random-request-uri validate
7. exit

DETAILED STEPS

Command or Action	Purpose
Step 1 enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2 configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3 voice service voip Example: Router(config)# voice service voip	Enters VoIP voice-service configuration mode.
Step 4 sip Example: Router(conf-voi-serv)# sip	Enters voice service VoIP SIP configuration mode.
Step 5 call-route p-called-party-id Example: Router(conf-serv-sip)# call-route p-called-party-id	Enables the routing of calls based on the PCPID header.

Command or Action	Purpose
Step 6 <code>random-request-uri validate</code> Example: <pre>Router(conf-serv-sip)# random-request-uri validate</pre>	Enables the validation of the random string in the Request URI of the incoming INVITE message.
Step 7 <code>exit</code> Example: <pre>Router(conf-serv-sip)# exit</pre>	Exits the current mode.

Configuring P-Called-Party-Id Support on an Individual Dial Peer

To configure P-Called-Party-Id support on an individual dial peer, perform the steps in this section.

SUMMARY STEPS

1. `enable`
2. `configure terminal`
3. `dial-peer voice tag voip`
4. `voice-class sip call-route p-called-party-id`
5. `voice-class sip random-request-uri validate`
6. `exit`

DETAILED STEPS

Command or Action	Purpose
Step 1 <code>enable</code> Example: <pre>Router> enable</pre>	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2 <code>configure terminal</code> Example: <pre>Router# configure terminal</pre>	Enters global configuration mode.

Command or Action	Purpose
Step 3 dial-peer voice <i>tag</i> voip Example: <pre>Router(config)# dial-peer voice 2611 voip</pre>	Defines the dial peer, specifies the method of voice encapsulation, and enters dial peer voice configuration mode.
Step 4 voice-class sip call-route p-called-party-id Example: <pre>Router(config-dial-peer)# voice-class sip call-route p-called-party-id</pre>	Enables the routing of calls based on the PCPID header on this dial peer.
Step 5 voice-class sip random-request-uri validate Example: <pre>Router(config-dial-peer)# voice-class sip random-request-uri validate</pre>	Enables the validation of the random string in the Request URI of the incoming INVITE message on this dial peer.
Step 6 exit Example: <pre>Router(config-dial-peer)# exit</pre>	Exits the current mode.

Configuring Privacy Support on a Cisco Unified Border Element

To configure privacy support on a Cisco Unified Border Element, perform the steps in this section.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **voice service voip**
4. **sip**
5. **privacy *privacy-option***
6. **privacy-policy *privacy-policy-option***
7. **exit**

DETAILED STEPS

Command or Action	Purpose
<p>Step 1 <code>enable</code></p> <p>Example:</p> <pre>Router> enable</pre>	<p>Enables privileged EXEC mode.</p> <ul style="list-style-type: none"> • Enter your password if prompted.
<p>Step 2 <code>configure terminal</code></p> <p>Example:</p> <pre>Router# configure terminal</pre>	<p>Enters global configuration mode.</p>
<p>Step 3 <code>voice service voip</code></p> <p>Example:</p> <pre>Router(config)# voice service voip</pre>	<p>Enters VoIP voice-service configuration mode.</p>
<p>Step 4 <code>sip</code></p> <p>Example:</p> <pre>Router(conf-voi-serv)# sip</pre>	<p>Enters voice service VoIP SIP configuration mode.</p>
<p>Step 5 <code>privacy <i>privacy-option</i></code></p> <p>Example:</p> <pre>Router(conf-serv-sip)# privacy id</pre>	<p>Enables the privacy settings for the header.</p>
<p>Step 6 <code>privacy-policy <i>privacy-policy-option</i></code></p> <p>Example:</p> <pre>Router(conf-serv-sip)# privacy-policy passthru</pre>	<p>Specifies the privacy policy to use when passing the privacy header from one SIP leg to the next.</p>
<p>Step 7 <code>exit</code></p> <p>Example:</p> <pre>Router(conf-serv-sip)# exit</pre>	<p>Exits the current mode.</p>

Configuring Privacy Support on an Individual Dial Peer

To configure privacy support on an individual dial peer, perform the steps in this section.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **dial-peer voice *tag* voip**
4. **voice-class sip privacy *privacy-option***
5. **voice-class sip privacy-policy *privacy-policy-option***
6. **exit**

DETAILED STEPS

	Command or Action	Purpose
Step 1	enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2	configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3	dial-peer voice <i>tag</i> voip Example: Router(config)# dial-peer voice 2611 voip	Defines the dial peer, specifies the method of voice encapsulation, and enters dial peer voice configuration mode.
Step 4	voice-class sip privacy <i>privacy-option</i> Example: Router(config-dial-peer)# voice-class sip privacy id	Enables the privacy settings for the header on this dial peer.
Step 5	voice-class sip privacy-policy <i>privacy-policy-option</i> Example: Router(config-dial-peer)# voice-class sip privacy-policy passthru	Specifies the privacy policy to use when passing the privacy header from one SIP leg to the next, on this dial peer.

Command or Action	Purpose
Step 6 <code>exit</code> Example: <code>Router(config-dial-peer)# exit</code>	Exits the current mode.

Configuring Random-Contact Support on a Cisco Unified Border Element

To configure random-contact support on a Cisco Unified Border Element, perform the steps in this section.

SUMMARY STEPS

1. `enable`
2. `configure terminal`
3. `sip-ua`
4. `credentials username username password password realm domain-name`
5. `registrar ipv4: destination-address random-contact expires expiry`
6. `exit`
7. `voice service voip`
8. `sip`
9. `random-contact`
10. `exit`

DETAILED STEPS

Command or Action	Purpose
Step 1 <code>enable</code> Example: <code>Router> enable</code>	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2 <code>configure terminal</code> Example: <code>Router# configure terminal</code>	Enters global configuration mode.
Step 3 <code>sip-ua</code> Example: <code>Router(config)# sip-ua</code>	Enters SIP user-agent configuration mode.

	Command or Action	Purpose
Step 4	<p>credentials username <i>username</i> password <i>password</i> realm <i>domain-name</i></p> <p>Example:</p> <pre>Router(config-sip-ua)# credentials username 123456 password cisco realm cisco</pre>	Sends a SIP registration message from the Cisco Unified Border Element.
Step 5	<p>registrar ipv4: <i>destination-address</i> random-contact expires <i>expiry</i></p> <p>Example:</p> <pre>Router(config-sip-ua)# registrar ipv4:10.1.2.2 random-contact expires 200</pre>	<p>Enables the SIP gateways to register E.164 numbers on behalf of analog telephone voice ports (FXS), IP phone virtual voice ports (EFXS), and Skinny Client Control Protocol (SCCP) phones with an external SIP proxy or SIP registrar.</p> <ul style="list-style-type: none"> The random-contact keyword configures the Cisco Unified Border Element to send the random string from the REGISTER message to the registrar.
Step 6	<p>exit</p> <p>Example:</p> <pre>Router(config-sip-ua)# exit</pre>	Exits the current mode.
Step 7	<p>voice service voip</p> <p>Example:</p> <pre>Router(config)# voice service voip</pre>	Enters VoIP voice-service configuration mode.
Step 8	<p>sip</p> <p>Example:</p> <pre>Router(conf-voi-serv)# sip</pre>	Enters voice service VoIP SIP configuration mode.
Step 9	<p>random-contact</p> <p>Example:</p> <pre>Router(conf-serv-sip)# random-contact</pre>	Enables random-contact support on a Cisco Unified Border Element.
Step 10	<p>exit</p> <p>Example:</p> <pre>Router(conf-serv-sip)# exit</pre>	Exits the current mode.

Configuring Random-Contact Support for an Individual Dial Peer

To configure configure random-contact support for an individual dial peer, perform the steps in this section.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **sip-ua**
4. **credentials username *username* password *password* realm *domain-name***
5. **registrar ipv4: *destination-address* random-contact expires *expiry***
6. **exit**
7. **dial-peer voice *tag* voip**
8. **voice-class sip random-contact**
9. **exit**

DETAILED STEPS

	Command or Action	Purpose
Step 1	enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2	configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3	sip-ua Example: Router(config)# sip-ua	Enters SIP user-agent configuration mode.
Step 4	credentials username <i>username</i> password <i>password</i> realm <i>domain-name</i> Example: Router(config-sip-ua)# credentials username 123456 password cisco realm cisco	Sends a SIP registration message from the Cisco Unified Border Element.

Command or Action	Purpose
<p>Step 5 registrar ipv4: <i>destination-address</i> random-contact expires <i>expiry</i></p> <p>Example:</p> <pre>Router(config-sip-ua)# registrar ipv4:10.1.2.2 random-contact expires 200</pre>	<p>Enables the SIP gateways to register E.164 numbers on behalf of FXS, EFXS, and SCCP phones with an external SIP proxy or SIP registrar.</p> <ul style="list-style-type: none"> The random-contact keyword configures the Cisco Unified Border Element to send the random string from the REGISTER message to the registrar.
<p>Step 6 exit</p> <p>Example:</p> <pre>Router(config-sip-ua)# exit</pre>	<p>Exits the current mode.</p>
<p>Step 7 dial-peer voice <i>tag</i> voip</p> <p>Example:</p> <pre>Router(config)# dial-peer voice 2611 voip</pre>	<p>Defines the dial peer, specifies the method of voice encapsulation, and enters dial peer voice configuration mode.</p>
<p>Step 8 voice-class sip random-contact</p> <p>Example:</p> <pre>Router(config-dial-peer)# voice-class sip random- contact</pre>	<p>Enables random-contact support on this dial peer.</p>
<p>Step 9 exit</p> <p>Example:</p> <pre>Router(config-dial-peer)# exit</pre>	<p>Exits the current mode.</p>

Feature Information for PAID PPID Privacy PCPID and PAURI Headers on the Cisco Unified Border Element

The following table provides release information about the feature or features described in this module. This table lists only the software release that introduced support for a given feature in a given software release train. Unless noted otherwise, subsequent releases of that software release train also support that feature.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Feature History Table entry for the Cisco Unified Border Element.

Table 37 **Feature Information for PAID, PPID, Privacy, PCPID, and PAURI Headers on the UBE**

Feature Name	Releases	Feature Information
PAID, PPID, Privacy, PCPID, and PAURI Headers on the Cisco Unified Border Element	12.4(22)YB 15.0(1)M	<p>This feature enables Cisco UBE platforms to support:</p> <ul style="list-style-type: none"> • P-Preferred Identity (PPID), P-Asserted Identity (PAID), Privacy, P-Called Party Identity (PCPID), in INVITE messages • Translation of PAID headers to PPID headers and vice versa • Translation of From: or RPID headers to PAID or PPID headers and vice versa • Configuration and/or pass through of privacy header values • PCPID header to route INVITE messages • Multiple PAURI headers in the response messages (200 OK) it receives to REGISTER messages • P-Preferred Identity and P-Asserted Identity Headers <p>The following commands were introduced: call-route p-called-party-id, privacy-policy, random-contact, random-request-uri validate, voice-class sip call-route p-called-party-id, voice-class sip privacy-policy, voice-class sip random-contact, and voice-class sip random-request-uri validate.</p>

Feature History Table entry for the Cisco Unified Border Element (Enterprise) .

Table 38 Feature Information for PAID, PPID, Privacy, PCPID, and PAURI Headers on the Cisco UBE

Feature Name	Releases	Feature Information
PAID, PPID, Privacy, PCPID, and PAURI Headers on the Cisco Unified Border Element	Cisco IOS XE Release 3.1S	<p>This feature enables Cisco UBE platforms to support:</p> <ul style="list-style-type: none"> • P-Preferred Identity (PPID), P-Asserted Identity (PAID), Privacy, P-Called Party Identity (PCPID), in INVITE messages • Translation of PAID headers to PPID headers and vice versa • Translation of From: or RPID headers to PAID or PPID headers and vice versa • Configuration and/or pass through of privacy header values • PCPID header to route INVITE messages • Multiple PAURI headers in the response messages (200 OK) it receives to REGISTER messages • P-Preferred Identity and P-Asserted Identity Headers <p>The following commands were introduced: call-route p-called-party-id, privacy-policy, random-contact, random-request-uri validate, voice-class sip call-route p-called-party-id, voice-class sip privacy-policy, voice-class sip random-contact, and voice-class sip random-request-uri validate.</p>

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: www.cisco.com/go/trademarks. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams,

and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.



Configurable Pass-through of SIP INVITE Parameters

The Configurable Pass-through of SIP INVITE Parameters feature enables the Cisco Unified Border Element (Cisco UBE) platform to pass through end-to-end headers at a global or dial-peer level, that are not processed or understood in a SIP trunk to SIP trunk scenario. The pass through functionality includes all or only a configured list of unsupported or non-mandatory SIP headers, and all unsupported content/MIME types.

- [Finding Feature Information, page 133](#)
- [Prerequisites for Configurable Pass-through of SIP INVITE Parameters, page 133](#)
- [Restrictions for Configurable Pass-through of SIP INVITE Parameters, page 134](#)
- [Information About Configurable Pass-through of SIP INVITE Parameters, page 134](#)
- [How to Configure Configurable Pass-through of SIP INVITE Parameters, page 134](#)
- [Feature Information for Configurable Pass-through of SIP INVITE Parameters, page 137](#)

Finding Feature Information

Your software release may not support all the features documented in this module. For the latest feature information and caveats, see the release notes for your platform and software release. To find information about the features documented in this module, and to see a list of the releases in which each feature is supported, see the Feature Information Table at the end of this document.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Prerequisites for Configurable Pass-through of SIP INVITE Parameters

- Configuring the media flow-around command is required for Session Description Protocol (SDP) pass-through. When flow-around is not configured, the flow-through mode of SDP pass-through will be functional.
- When the dial-peer media flow mode is asymmetrically configured, the default behavior is to fallback to SDP pass-through with flow-through.

Cisco Unified Border Element

- Cisco IOS Release 15.0(1)M or a later release must be installed and running on your Cisco Unified Border Element.

Cisco Unified Border Element (Enterprise)

- Cisco IOS XE Release 3.1S or a later release must be installed and running on your Cisco ASR 1000 Series Router.

Restrictions for Configurable Pass-through of SIP INVITE Parameters

When SDP pass-through is enabled, some of interworking that the Cisco Unified Border Element currently performs cannot be activated. These features include:

- Delayed Offer to Early Offer Interworking
- Supplementary Services with triggered Invites
- DTMF Interworking scenarios
- Fax Interworking/QoS Negotiation
- Transcoding

Information About Configurable Pass-through of SIP INVITE Parameters

The Cisco UBE does not support end-to-end media negotiation between the two endpoints that establish a call session through the Cisco UBE. This is a limitation when the endpoints intend to negotiate codec/payload types that the Cisco UBE does not process, because currently, unsupported payload types will never be negotiated by the Cisco UBE. Unsupported content types include text/plain, image/jpeg and application/resource-lists+xml. To address this problem, SDP is configured to pass through transparently at the Cisco UBE, so that both the remote ends can negotiate media independently of the Cisco UBE.

SDP pass-through is addressed in two modes:

- Flow-through--Cisco UBE plays no role in the media negotiation, it blindly terminates and re-originates the RTP packets irrespective of the content type negotiated by both the ends. This supports address hiding and NAT traversal.
- Flow-around--Cisco UBE neither plays a part in media negotiation, nor does it terminate and re-originate media. Media negotiation and media exchange is completely end-to-end.

How to Configure Configurable Pass-through of SIP INVITE Parameters

- [Configuring Configurable Pass-through of SIP INVITE Parameters at the Global Level](#), page 135
- [Configuring Configurable Pass-through of SIP INVITE Parameters at the Dial Peer Level](#), page 136

Configuring Configurable Pass-through of SIP INVITE Parameters at the Global Level

To configure Unsupported Content Pass-through on a Cisco UBE platform at the global level, perform the steps in this section.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **voice service voip**
4. **sip**
5. **pass-thru {content {sdp | un supp} | headers {un supp | list tag}}**
6. **exit**

DETAILED STEPS

Command or Action	Purpose
Step 1 enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2 configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3 voice service voip Example: Router(config)# voice service voip	Enters voice service VoIP configuration mode.
Step 4 sip Example: Router(conf-voi-serv)# sip	Enters SIP configuration mode.

Command or Action	Purpose
Step 5 <code>pass-thru {content {sdp unsupported} headers {unsupported list tag}}</code> Example: <pre>Router(conf-serv-sip)# pass-thru content unsupported</pre>	Passes the SDP transparently from in-leg to the out-leg with no media negotiation.
Step 6 <code>exit</code> Example: <pre>Router(conf-serv-sip)# exit</pre>	Exits the current mode.

Configuring Configurable Pass-through of SIP INVITE Parameters at the Dial Peer Level

To configure Unsupported Content Pass-through on a Cisco UBE platform at the dial-peer level, perform the steps in this section.

SUMMARY STEPS

1. `enable`
2. `configure terminal`
3. `dial-peer voice tag voip`
4. `voice-class sip pass-thru {content {sdp | unsupported} | headers {unsupported | list tag}}` [system]
5. `exit`

DETAILED STEPS

Command or Action	Purpose
Step 1 <code>enable</code> Example: <pre>Router> enable</pre>	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2 <code>configure terminal</code> Example: <pre>Router# configure terminal</pre>	Enters global configuration mode.

Command or Action	Purpose
<p>Step 3 <code>dial-peer voice tag voip</code></p> <p>Example:</p> <pre>Router(config)# dial-peer voice 2 voip</pre>	Enters dial peer VoIP configuration mode.
<p>Step 4 <code>voice-class sip pass-thru {content {sdp unsupp} headers {unsupp list tag}} [system]</code></p> <p>Example:</p> <pre>Router(config-dial-peer)# voice-class sip pass-thru content sdp</pre>	Passes the SDP transparently from in-leg to the out-leg with no media negotiation.
<p>Step 5 <code>exit</code></p> <p>Example:</p> <pre>Router(config-dial-peer)# exit</pre>	Exits the current mode.

Feature Information for Configurable Pass-through of SIP INVITE Parameters

The following table provides release information about the feature or features described in this module. This table lists only the software release that introduced support for a given feature in a given software release train. Unless noted otherwise, subsequent releases of that software release train also support that feature.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Feature History Table entry for the Cisco Unified Border Element.

Table 39 **Feature Information for Configurable Pass-through of SIP INVITE Parameters**

Feature Name	Releases	Feature Information
Configurable Pass-through of SIP INVITE Parameters	15.0(1)M	<p>This feature enables the Cisco UBE to pass through end-to-end headers at a global or dial-peer level, that are not processed or understood in a SIP trunk to SIP trunk scenario. The pass through functionality includes all or only a configured list of unsupported or non-mandatory SIP headers, and all unsupported content/MIME types.</p> <p>This feature introduces the following commands: pass-thru and voice-class sip pass-thru.</p>

Feature History Table entry for the Cisco Unified Border Element (Enterprise).

Table 40 **Feature Information for Configurable Pass-through of SIP INVITE Parameters**

Feature Name	Releases	Feature Information
Configurable Pass-through of SIP INVITE Parameters	Cisco IOSXE Release 3.1S	<p>This feature enables the Cisco UBE to pass through end-to-end headers at a global or dial-peer level, that are not processed or understood in a SIP trunk to SIP trunk scenario. The pass through functionality includes all or only a configured list of unsupported or non-mandatory SIP headers, and all unsupported content/MIME types.</p> <p>This feature introduces the following commands: pass-thru and voice-class sip pass-thru.</p>

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: www.cisco.com/go/trademarks. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams,

and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.



Conditional Header Manipulation of SIP Headers

The Conditional Header Manipulation of SIP Headers feature provides the following enhancements to Cisco Unified Border Element (Cisco UBE):

- The ability to pass unsupported parameters present in a mandatory Session Initiation Protocol (SIP) header from one call leg to another of Cisco UBE.
- The ability to copy contents from one header to another in an outgoing SIP message.
- [Finding Feature Information, page 141](#)
- [Prerequisites for Conditional Header Manipulation of SIP Headers, page 141](#)
- [Restrictions, page 142](#)
- [Passing an Unsupported Parameter Present in a Mandatory Header from One Call Leg to Another of Cisco UBE, page 142](#)
- [Copying Contents from One Header to Another in an Outgoing SIP Message, page 143](#)
- [Feature Information for Support for Conditional Header Manipulation of SIP Headers, page 146](#)

Finding Feature Information

Your software release may not support all the features documented in this module. For the latest feature information and caveats, see the release notes for your platform and software release. To find information about the features documented in this module, and to see a list of the releases in which each feature is supported, see the Feature Information Table at the end of this document.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Prerequisites for Conditional Header Manipulation of SIP Headers

Cisco Unified Border Element

- Cisco IOS Release 15.1(3)T or a later release must be installed and running on your Cisco Unified Border Element.

Cisco Unified Border Element (Enterprise)

- Cisco IOS XE Release <TBD> or a later release must be installed and running on your Cisco ASR 1000 Series Router.

Restrictions

- You cannot configure more than 99 variables for the SIP profiles copy option.
- This feature does not support any header other than SIP.

Passing an Unsupported Parameter Present in a Mandatory Header from One Call Leg to Another of Cisco UBE

Perform this task to pass an unsupported parameter present in a mandatory header from one call leg to another of Cisco UBE.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **voice class sip-copylist tag**
4. **sip-header {sip-req-uri | header-name}**
5. **exit**

DETAILED STEPS

	Command or Action	Purpose
Step 1	enable Example: Router> enable	Enables privileged EXEC mode. • Enter your password if prompted.
Step 2	configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3	voice class sip-copylist tag Example: Router(config)# voice class sip-copylist 100	Configures a list of entities to be sent to a peer call leg and enters voice class configuration mode.

Command or Action	Purpose
Step 4 <code>sip-header {sip-req-uri header-name}</code> Example: <code>Router(config-class)# sip-header From</code>	Specifies the SIP header to be sent to the peer call leg.
Step 5 <code>exit</code> Example: <code>Router(config-class)# exit</code>	Exits voice class configuration mode.

Copying Contents from One Header to Another in an Outgoing SIP Message

- [Copying Contents from One SIP Header to Another in an Outgoing Message, page 143](#)
- [Copying Contents from Peer Header to a SIP Header in an Outgoing Message, page 144](#)

Copying Contents from One SIP Header to Another in an Outgoing Message

Perform this task to copy contents from one SIP to another in an outgoing message.

SUMMARY STEPS

1. `enable`
2. `configure terminal`
3. `voice class sip-profiles tag`
4. `request method sip-header field {add | copy | modify | remove} string`
5. `response option sip-header field {add | copy | modify | remove} string`
6. `exit`

DETAILED STEPS

Command or Action	Purpose
Step 1 <code>enable</code> Example: <code>Router> enable</code>	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.

Command or Action	Purpose
<p>Step 2 <code>configure terminal</code></p> <p>Example:</p> <pre>Router# configure terminal</pre>	Enters global configuration mode.
<p>Step 3 <code>voice class sip-profiles tag</code></p> <p>Example:</p> <pre>Router(config)# voice class sip-profiles 10</pre>	Enables dial peer-based VoIP SIP profile configurations and enters voice class configuration mode.
<p>Step 4 <code>request method sip-header field {add copy modify remove} string</code></p> <p>Example:</p> <pre>Router(config-class)# request INVITE sip-header contact copy "(.*)" u01</pre>	Modifies SIP profiles to copy the contents from one SIP header to another in a SIP request message.
<p>Step 5 <code>response option sip-header field {add copy modify remove} string</code></p> <p>Example:</p> <pre>Router(config-class)# response 200 sip-header contact copy "(.*)" u01</pre>	Modifies SIP profiles to copy contents from one SIP header to another in a SIP response message.
<p>Step 6 <code>exit</code></p> <p>Example:</p> <pre>Router(config-class)# exit</pre>	Exits voice class configuration mode.

Copying Contents from Peer Header to a SIP Header in an Outgoing Message

Perform this task to copy contents from peer header to a SIP header in an outgoing message.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **voice class sip-profiles tag**
4. **request method peer-header sip {sip-req-uri | header-name} copy match-pattern variable**
5. **response option peer-header sip {sip-req-uri | header-name} copy match-pattern variable**
6. **exit**

DETAILED STEPS

Command or Action	Purpose
<p>Step 1 enable</p> <p>Example:</p> <pre>Router> enable</pre>	<p>Enables privileged EXEC mode.</p> <ul style="list-style-type: none"> • Enter your password if prompted.
<p>Step 2 configure terminal</p> <p>Example:</p> <pre>Router# configure terminal</pre>	<p>Enters global configuration mode.</p>
<p>Step 3 voice class sip-profiles tag</p> <p>Example:</p> <pre>Router(config)# voice class sip-profiles 10</pre>	<p>Enables dial peer-based VoIP SIP profile configurations and enters class configuration mode.</p>
<p>Step 4 request method peer-header sip {sip-req-uri header-name} copy match-pattern variable</p> <p>Example:</p> <pre>Router(config-class)# request invite peer-header contact copy "(.*)" u01</pre>	<p>Copies contents from a peer header to a SIP header in an outgoing SIP request message.</p>
<p>Step 5 response option peer-header sip {sip-req-uri header-name} copy match-pattern variable</p> <p>Example:</p> <pre>Router(config-class)# response 200 peer-header contact copy "(.*)" u01</pre>	<p>Copies contents from a peer header to a SIP header in an outgoing SIP response message.</p>

Command or Action	Purpose
Step 6 <code>exit</code> Example: <code>Router(config-class)# exit</code>	Exits voice class configuration mode.

Feature Information for Support for Conditional Header Manipulation of SIP Headers

The following table provides release information about the feature or features described in this module. This table lists only the software release that introduced support for a given feature in a given software release train. Unless noted otherwise, subsequent releases of that software release train also support that feature.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

The table below lists the release history for the ISR.

Table 41 Feature Information for Support for Conditional Header Manipulation of SIP Headers

Feature Name	Releases	Feature Information
Support for Conditional Header Manipulation of SIP Headers	15.1(3)T	<p>The Support for Conditional Header Manipulation of SIP Headers feature provides the following enhancements to Cisco UBE:</p> <ul style="list-style-type: none"> • The ability to pass unsupported parameters present in a mandatory header from one call leg to another. • The ability to copy contents from one header to another header in an outgoing SIP message. <p>The following commands were introduced or modified: response, response peer-header, request, request peer-header, sip-header, voice-class sip copy-list, voice class sip-copylist.</p>

The table below lists the release history for the ASR.

Table 42 **Feature Information for Support for Conditional Header Manipulation of SIP Headers**

Feature Name	Releases	Feature Information
Support for Conditional Header Manipulation of SIP Headers	<TBD>	<p>The Support for Conditional Header Manipulation of SIP Headers feature provides the following enhancements to Cisco UBE:</p> <ul style="list-style-type: none"> • The ability to pass unsupported parameters present in a mandatory header from one call leg to another. • The ability to copy contents from one header to another header in an outgoing SIP message. <p>The following commands were introduced or modified: response, response peer-header, request, request peer-header, sip-header, voice-class sip copy-list, voice class sip-copylist.</p>

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: www.cisco.com/go/trademarks. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.



Transparent Tunneling of QSIG and Q.931

Transparent Tunneling of QSIG and Q.931 over Session Initiation Protocol (SIP) Time-Division Multiplexing (TDM) Gateway and SIP-to-SIP Cisco Unified Border Element (Enterprise) was first introduced on Cisco IOS SIP gateways in phases. In the first phase, the Transparent Tunneling of QSIG over SIP TDM Gateway feature added the ability to transparently tunnel Q-signaling (QSIG) protocol ISDN messages across the Session Initiation Protocol (SIP) trunk. With this feature, QSIG messages (supplementary services carried within Q.931 FACILITY-based messages) can be passed end to end across a SIP network. However, in Cisco IOS Release 12.4(15)XY, deployment of this feature is limited to QSIG messages over SIP TDM gateways. In later releases, the ISDN Q.931 Tunneling over SIP TDM Gateway feature adds support for transparent tunneling of all Q.931 messages over SIP and for the Transparent Tunneling of QSIG and Q.931 over a SIP-SIP Cisco Unified Border Element.

Transparent tunneling is accomplished by encapsulating QSIG or Q.931 messages within SIP message bodies. These messages are encapsulated using "application/qsig" or "application/x-q931" Multipurpose Internet Mail Extensions (MIME) to tunnel between SIP endpoints. Using MIME to tunnel through Cisco SIP messaging does not include any additional QSIG/Q.931 services to SIP interworking.

Beginning with Cisco IOS XE Release 3.1S, support for this feature is expanded to include the Cisco ASR 1000 Series Router.

- [Finding Feature Information, page 149](#)
- [Prerequisites for Transparent Tunneling of QSIG and Q.931, page 150](#)
- [Restrictions for Transparent Tunneling of QSIG and Q.931, page 150](#)
- [Information About Transparent Tunneling of QSIG or Q.931, page 150](#)
- [How to Transparently Tunnel QSIG over SIP, page 153](#)
- [Configuration Examples for Transparent Tunneling of QSIG, page 157](#)
- [Feature Information for Transparent Tunneling of QSIG and Q.931, page 159](#)

Finding Feature Information

Your software release may not support all the features documented in this module. For the latest feature information and caveats, see the release notes for your platform and software release. To find information about the features documented in this module, and to see a list of the releases in which each feature is supported, see the Feature Information Table at the end of this document.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Prerequisites for Transparent Tunneling of QSIG and Q.931

- Before configuring transparent tunneling of QSIG and Q.931 over a SIP trunk, verify the SIP configuration within the VoIP network for the appropriate originating and terminating gateways.

Cisco Unified Border Element

- Cisco IOS Release 12.4(15)XZ or a later release must be installed and running on your Cisco Unified Border Element.
- The Transparent Tunneling of QSIG over SIP TDM Gateway feature is intended for TDM PBX toll bypass and call center applications. In its first release (Cisco IOS Release 12.4(15)XY), only tunneling of QSIG messages is supported and only on TDM gateways. From Cisco IOS release 12.4(15)XZ and 12.4(20)T onward, support is added for the ISDN Q.931 Tunneling over SIP TDM Gateway and Transparent Tunneling of QSIG and Q.931 over SIP-SIP Cisco Unified Border Element.

Cisco Unified Border Element (Enterprise)

- Cisco IOS XE Release 2.5 or a later release must be installed and running on your Cisco ASR 1000 Series Router.

Restrictions for Transparent Tunneling of QSIG and Q.931

- Transparent tunneling of QSIG or Q.931 does not function unless both the originating gateway (OGW) and the terminating gateway (TGW) are configured using the same ISDN switch type.
- This function is supported only on SIP-to-SIP configurations on Cisco Unified Border Element. Tunneling of QSIG or Q.931 is not supported on SIP-to-H.323 or H.323-to-H.323 configurations on Cisco Unified Border Element.

Information About Transparent Tunneling of QSIG or Q.931

- [Use of the QSIG or Q.931 Protocols, page 150](#)
- [Purpose of Tunneling QSIG or Q.931 over SIP, page 151](#)
- [Encapsulation of QSIG in SIP Messaging, page 151](#)
- [Mapping of QSIG Message Elements to SIP Message Elements, page 153](#)

Use of the QSIG or Q.931 Protocols

Q-series documents, controlled by the International Telecommunication Union (ITU), define the network Layer. The Q.931 document defines the Layer 3 protocol that serves as the connection control protocol for ISDN signaling--it is used primarily to manage the initiation, maintenance, and termination of connections over a digital network.

The Q signaling (QSIG) protocol is based on the Q.931 standard and is used for ISDN communications in a Private Integrated Services Network (PISN). The QSIG protocol makes it possible to pass calls from one circuit switched network, such as a PBX or private integrated services network exchange (PINX), to

another. QSIG messages are, essentially, a subset of Q.931 messages that ensure the essential Q.931 FACILITY-based functions successfully traverse the network regardless of the various hardware involved.


Q.931 tunneling over Cisco IOS SIP gateways was introduced as the ability to transparently tunnel only QSIG messages--the FACILITY-based Q.931 messages. Beginning with Cisco IOS Release 12.4(15)XZ and Cisco IOS Release 12.4(20)T, tunneling of all Q.931 messages (SETUP, ALERTING, CONNECT, and RELEASE COMPLETE messages in addition to FACILITY-based messages) is supported on Cisco IOS SIP gateways. However, for clarity, the descriptions and examples in this document focus primarily on QSIG messages.

Purpose of Tunneling QSIG or Q.931 over SIP

TDM Gateways

Transparently tunneling QSIG or Q.931 messages over SIP through SIP TDM gateways allows calls from one PINX to another to be passed through a SIP-based IP network with the equivalent functionality of passing through an H.323 network--without losing the functionality of the QSIG or Q.931 protocol to establish the call. To do this, QSIG or Q.931 messages are encapsulated within SIP messages (see the figure below).


Figure 2 Tunneling QSIG (or Q.931) Messages Across a SIP Trunk



Cisco Unified Border Elements

Transparently tunneling QSIG or Q.931 over SIP through a Cisco Unified Border Element allows calls from one network to be passed through a SIP-to-SIP Cisco Unified Border Element connection to a bordering network (see the figure below).

Figure 3 Tunneling QSIG (or Q.931) Messages Through a SIP-SIP Cisco Unified Border Element



Encapsulation of QSIG in SIP Messaging

QSIG messages are tunneled by encapsulating them as a MIME body in a SIP INVITE message on the OGW. Then, the MIME body is extracted from the SIP message by the TGW at the other end of the SIP

network. To tunnel QSIG messages to a TGW on another network, configure and use a SIP-to-SIP Cisco Unified Border Element connection between each network over which the SIP INVITE must travel to reach the TGW. This tunneling process helps preserve all QSIG capabilities associated with a call or call-independent signal as it travels to its destination.

The following events make it possible to tunnel QSIG messaging across a SIP network:

- The ingress gateway (OGW) receives a QSIG call (or signal) establishment request (a SETUP message) and generates a corresponding SIP INVITE request.
- A corresponding SIP INVITE message is created and will contain the following:
 - A Request-URI--message part containing a destination derived from the called party number information element (IE) in the QSIG SETUP message. The destination can be the egress (TGW or the Cisco Unified Border Element) for exiting the SIP network or it can be the required destination, leaving SIP proxies to determine which gateway will be used.
 - A From header--message header containing a uniform resource identifier (URI) for either the OGW or calling party itself.
 - A Session Description Protocol (SDP) offer--a message part proposing two media streams, one for each direction.
 - A Multipart-MIME body--message part containing the tunneled QSIG data.
- In addition to normal user agent (UA) handling of a SIP response, the OGW performs a corresponding action when it receives a SIP response, as follows:
 - OGW receives 18x response with tunneled content--identifies the QSIG message (FACILITY, ALERTING, or PROGRESS) and sends a corresponding ISDN message.
 - OGW receives 3xx , 4xx , 5xx , or 6xx final response--attempts alternative action to route the initial QSIG message or clears the call or signal using an appropriate QSIG cause value (DISCONNECT, RELEASE, or RELEASE COMPLETE). When the OGW receives a valid encapsulated QSIG RELEASE COMPLETE message, the OGW should use the cause value included in that QSIG message to determine the cause value.

**Note**

You should expect a SIP 415 final response message (Unsupported Media Type) if the user agent server (UAS) is unable to process tunneled QSIG or Q.931 messages.

- ◦ OGW receives a SIP 200 OK response--performs normal SIP processing, which includes sending an ACK message. Additionally, the OGW will encapsulate the QSIG message in the response to the PSTN side and will connect the QSIG user information channel to the appropriate media streams as called out in the SDP reply.

**Note**

A nonzero port number for each media stream must be provided in a SIP 200 OK response to the OGW before the OGW receives the QSIG CONNECT message. Otherwise, the OGW will behave as if the QSIG T301 timer expired.

- The TGW sends and the OGW receives a 200 OK response--the OGW sends an ACK message to the TGW and all successive messages during the session are encapsulated into the body of SIP INFO request messages. There are two exceptions:
 - When a SIP connection requires an extended handshake process, renegotiation, or an update, the gateway may encapsulate a waiting QSIG message into a SIP re-INVITE or SIP UPDATE message during QSIG call establishment.

- When the session is terminated, gateways send a SIP BYE message. If the session is terminated by notice of a QSIG RELEASE COMPLETE message, that message can be encapsulated into the SIP BYE message.

Mapping of QSIG Message Elements to SIP Message Elements

This section lists QSIG message elements and their associated SIP message elements when QSIG messages are tunneled over a SIP trunk.

• QSIG FACILITY/NOTIFY/ INFO	<-->	SIP INFO
• QSIG SETUP	<-->	SIP INVITE
• QSIG ALERTING	<-->	SIP 180 RINGING
• QSIG PROGRESS	<-->	SIP 183 PROGRESS
• QSIG CONNECT	<-->	SIP 200 OK
• QSIG DISCONNECT	<-->	SIP BYE/CANCEL/4xx --6xx Response

How to Transparently Tunnel QSIG over SIP

To create a tunnel for QSIG messages across a SIP trunk, you must configure signaling forward settings on both the OGW and the TGW.

In the IP TDM gateway scenario, a gateway receives QSIG messages from PSTN and the ISDN module passes the raw QSIG message and, additionally, creates and includes a Generic Transparency Descriptor (GTD) that is passed with the raw QSIG message across the IP leg of the call.

In the SIP TDM gateway scenario, there are two options--raw message (rawmsg) and unconditional. The rawmsg option specifies tunneling of only raw message (application/qsig or application/x-q931). The unconditional option specifies tunneling of all additional message bodies, such as GTD and raw message (application/qsig or application/x-q931).

Use the **signaling forward** command at the global configuration level to configure the feature for the entire gateway. You can also enable the QSIG tunneling feature for only a specific interface. If you enable this feature at both the global and dial peer configuration level and the option specified for the interface is different than for the gateway, the interface setting will override the global setting.

- [Configuring Signaling Forward Settings for a Gateway, page 154](#)
- [Signaling Forward Settings for a Gateway, page 154](#)
- [Configuring Signaling Forward Settings for an Interface, page 155](#)
- [Signaling Forward Settings for an Interface, page 155](#)

Configuring Signaling Forward Settings for a Gateway

To create a tunnel for QSIG messages across a SIP trunk using the same signaling forward setting for all interfaces on a gateway, configure the signaling forward settings in voice service voip configuration mode.

Signaling Forward Settings for a Gateway

The two options--raw messages (rawmsg) and unconditional--are mutually exclusive, which means you can specify only one option at the global configuration level. To enable and specify the signaling forward option, use the **signaling forward** command in voice service voip configuration mode.



Note

To override the global setting for a specific interface, use the **signaling forward** command at the dial-peer level (see the [Configuring Signaling Forward Settings for an Interface, page 155](#)).

To create QSIG tunnels using the signaling forward configuration, configure both gateways. You can configure gateways globally or you can configure one or more interfaces on a gateway. In either case, you must include the recommended configuration for PRACK to avoid message/data loss.



Note

It is not necessary that both gateways are configured with the same signaling forward option but, if they are not, only raw QSIG messages can be tunneled. However, it is recommended that you tunnel QSIG messages with at least one interface configured on both gateways. If only one gateway is configured, QSIG tunneling might work in one direction but may not work properly in both directions.

You must also specify the central office switch type on the ISDN interface for both the OGW and the TGW. Use the **isdn switch-type** command in global or dial peer configuration mode to enable and specify the switch type for QSIG or Q.931 support.

Furthermore, before the **isdn switch-type** setting can function properly, you must assign network-side functionality for the primary-qsig switch type (either at the global or dial-peer level) using the **isdn protocol-emulate** command.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. voice service voip
4. Do one of the following:
 - **signaling forward** *message-type*

DETAILED STEPS

Command or Action	Purpose
<p>Step 1 <code>enable</code></p> <p>Example:</p> <pre>Router> enable</pre>	<p>Enables privileged EXEC mode.</p> <ul style="list-style-type: none"> Enter your password if prompted.
<p>Step 2 <code>configure terminal</code></p> <p>Example:</p> <pre>Router# configure terminal</pre>	<p>Enters global configuration mode.</p>
<p>Step 3 <code>voice service voip</code></p> <p>Example:</p> <pre>Router(config)# voice service voip</pre>	<p>Enters voice-service configuration mode and specifies a voice-encapsulation type globally.</p>
<p>Step 4 Do one of the following:</p> <ul style="list-style-type: none"> <code>signaling forward <i>message-type</i></code> <p>Example:</p> <pre>Router(conf-voi-serv)# signaling forward rawmsg</pre> <p>Example:</p> <pre>Router(conf-voi-serv)# signaling forward unconditional</pre>	<p>Enables tunneling of QSIG raw messages (application-qsig) only.</p> <p>or</p> <p>Enables tunneling of all QSIG message bodies unconditionally.</p>

Configuring Signaling Forward Settings for an Interface

To create a tunnel for QSIG messages across a SIP trunk on a specific interface on a gateway, configure the signaling forward settings in dial peer configuration mode.

Signaling Forward Settings for an Interface

The two options--raw messages (rawmsg) and unconditional--are mutually exclusive, which means you can specify only one option per interface at the dial-peer level. To enable and specify the signaling forward option for an interface, use the **signaling forward** command in dial peer configuration mode.

**Note**

To set the signaling forward option for an entire gateway, use the **signaling forward** command at the global level (see the [Feature Information for Transparent Tunneling of QSIG and Q.931](#), page 159).

To create QSIG tunnels using the signaling forward configuration, configure at least one interface on both gateways. You can also configure all interfaces at once by configuring the gateway globally. In either case, you must include the recommended configuration for PRACK to avoid data loss.

**Note**

It is not necessary that both gateways are configured with the same signaling forward option but, if they are not, only raw QSIG messages can be tunneled. However, it is recommended that you tunnel QSIG messages with at least one interface configured on both gateways. If only one gateway is configured, QSIG tunneling might work in one direction but may not work properly in both directions.

You must also specify the central office switch type on the ISDN interface for both the OGW and the TGW. Use the **isdn switch-type** command in global or dial peer configuration mode to enable and specify the switch type for QSIG or Q.931 support.

Furthermore, before the **isdn switch-type** setting can function properly, you must assign network-side functionality for the primary-qsig switch type (either at the global or dial-peer level) using the **isdn protocol-emulate** command.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **dial-peer voice *number* voip**
4. Do one of the following:
 - **signaling forward *message-type***

DETAILED STEPS

Command or Action	Purpose
Step 1 enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2 configure terminal Example: Router# configure terminal	Enters global configuration mode.

Command or Action	Purpose
<p>Step 3 <code>dial-peer voice <i>number</i> voip</code></p> <p>Example:</p> <pre>Router(config)# dial-peer voice 3 voip</pre>	<p>Enters voice-service configuration mode and specifies a voice-encapsulation type for a specific interface.</p>
<p>Step 4 Do one of the following:</p> <ul style="list-style-type: none"> • <code>signaling forward <i>message-type</i></code> <p>Example:</p> <pre>Router(config-dial-peer)# signaling forward rawmsg</pre> <p>Example:</p> <pre>Router(config-dial-peer)# signaling forward unconditional</pre>	<p>Enables tunneling of QSIG raw messages (application-qsig) only.</p> <p>or</p> <p>Enables tunneling of all QSIG message bodies unconditionally.</p>

Configuration Examples for Transparent Tunneling of QSIG

- [Tunneling QSIG Raw Messages over SIP Example, page 157](#)
- [Tunneling QSIG Messages Unconditionally over SIP Example, page 158](#)
- [Tunneling QSIG Raw Messages over SIP on an Interface Example, page 158](#)
- [Tunneling QSIG Messages Unconditionally over SIP on an Interface Example, page 159](#)

Tunneling QSIG Raw Messages over SIP Example

The following example shows how to configure transparent tunneling of only QSIG raw messages (application-qsig) through a SIP TDM gateway on a SIP trunk at either the OGW or TG:

```
!
voice service voip
  signaling forward rawmsg
  sip
  rel1xx require "100rel"
!
```

Tunneling QSIG Messages Unconditionally over SIP Example


The following example shows how to configure transparent tunneling of QSIG messages unconditionally through a SIP TDM gateway on a SIP trunk at either the OGW or TGW:

```
!
voice service voip
  signaling forward unconditional
  sip
    rellxx require "100rel"
!
```

Tunneling QSIG Raw Messages over SIP on an Interface Example

The following example shows how to configure transparent tunneling of only QSIG raw messages (application-qsig) on a gateway interface in a SIP network (see the figure below):

Figure 4 Tunneling of Only QSIG Raw Messages over a SIP Trunk (Interface-Level)



Configuration for OGW (172.24.2.15) Tunneling only QSIG Raw Mmessages

```
!
dial-peer voice 7777 voip
description OGW-OUT-TGW
destination-pattern 222
signaling forward rawmsg
session protocol sipv2
session target ipv4:172.24.2.14
!
```


Configuration for TGW (172.24.2.14) Tunneling only QSIG Raw Mmessages

```
!
dial-peer voice 333 voip
description TGW_RSVP_IN-DP
session protocol sipv2
signaling forward rawmsg
incoming called-number 222
!
```


Tunneling QSIG Messages Unconditionally over SIP on an Interface Example

The following example shows how to configure transparent tunneling of QSIG messages unconditionally over a gateway interface in a SIP network (see the figure below):

Figure 5 Tunneling of QSIG Messages Unconditionally over a SIP Trunk (Interface-Level)



Configuration for OGW (172.24.2.14) Tunneling QSIG Messages Unconditionally

```
dial-peer voice 7777 voip
description OGW-OUT-TGW
destination-pattern 222
signaling forward unconditional
session protocol sipv2
session target ipv4:172.24.2.14
```

Configuration for TGW (172.24.2.15) Tunneling QSIG Messages Unconditionally

```
dial-peer voice 333 voip
description TGW-RSVP-IN-DP
session protocol sipv2
signaling forward unconditional
incoming called-number 222
```

Feature Information for Transparent Tunneling of QSIG and Q.931

The following table provides release information about the feature or features described in this module. This table lists only the software release that introduced support for a given feature in a given software release train. Unless noted otherwise, subsequent releases of that software release train also support that feature.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

History Table for the Cisco Unified Border Element

Table 43 *Feature Information for Transparent Tunneling of QSIG and Q.931 over SIP TDM Gateway and SIP-SIP Cisco Unified Border Element*

Feature Name	Releases	Feature Information
Transparent Tunneling of QSIG and Q.931 over SIP TDM Gateway and SIP-SIP Cisco Unified Border Element	12.4(15)XZ 12.4(20)T	<p>This feature adds support for transparent tunneling of all Q.931 messages over SIP and for the Transparent Tunneling of QSIG and Q.931 over a SIP-SIP Cisco Unified Border Element.</p> <p>Transparent tunneling is accomplished by encapsulating QSIG or Q.931 messages within SIP message bodies. These messages are encapsulated using "application/qsig" or "application/x-q931" Multipurpose Internet Mail Extensions (MIME) to tunnel between SIP endpoints. Using MIME to tunnel through Cisco SIP messaging does not include any additional QSIG/Q.931 services to SIP interworking.</p> <p>This feature uses no new or modified commands.</p>

History Table for the Cisco Unified Border Element (Enterprise)

Table 44 **Feature Information for Transparent Tunneling of QSIG and Q.931 over SIP TDM Gateway and SIP-SIP Cisco Unified Border Element**

Feature Name	Releases	Feature Information
Transparent Tunneling of QSIG and Q.931 over SIP TDM Gateway and SIP-SIP Cisco Unified Border Element	Cisco IOS XE Release 3.1S	<p>This feature adds support for transparent tunneling of all Q.931 messages over SIP and for the Transparent Tunneling of QSIG and Q.931 over a SIP-SIP Cisco Unified Border Element.</p> <p>Transparent tunneling is accomplished by encapsulating QSIG or Q.931 messages within SIP message bodies. These messages are encapsulated using "application/qsig" or "application/x-q931" Multipurpose Internet Mail Extensions (MIME) to tunnel between SIP endpoints. Using MIME to tunnel through Cisco SIP messaging does not include any additional QSIG/Q.931 services to SIP interworking.</p> <p>This feature uses no new or modified commands.</p>

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: www.cisco.com/go/trademarks. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.



SIP Diversion Header Enhancements

The SIP Diversion Header Enhancements feature enables time-division multiplex (TDM) gateways and Cisco Unified Communications Manager Express to populate the SIP Diversion Header with a domain name. Localhost command-line interface commands can be used to configure the domain name globally or at the dial peer level. This feature also provides choice of transparent pass through or application of address hiding to the SIP Diversion Header on Cisco UBE platforms.

- [Finding Feature Information, page 163](#)
- [Prerequisites for SIP Diversion Header Enhancements, page 163](#)
- [Information about SIP Diversion Header Enhancements, page 164](#)
- [How to Configure SIP Diversion Header Enhancements, page 164](#)
- [Feature Information for SIP Diversion Header Enhancements, page 165](#)

Finding Feature Information

Your software release may not support all the features documented in this module. For the latest feature information and caveats, see the release notes for your platform and software release. To find information about the features documented in this module, and to see a list of the releases in which each feature is supported, see the Feature Information Table at the end of this document.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Prerequisites for SIP Diversion Header Enhancements

Cisco Unified Border Element

- Cisco IOS Release 12.4(22)T or a later release must be installed and running on your Cisco Unified Border Element.

Cisco Unified Border Element (Enterprise)

- Cisco IOS XE Release 3.1S or a later release must be installed and running on your Cisco ASR 1000 Series Router.

Information about SIP Diversion Header Enhancements

To enable this feature, you must first configure the **sip-ua** command to place the router in SIP user-agent configuration mode before you can use the **host-registrars** command.

By default, the Session Initiation Protocol (SIP) gateway and Cisco Unified Communications Manager Express (Cisco Unified CME) populate the host portion of the diversion header with the domain name or IP address of the gateway that generates the request or response. The SIP gateway and Cisco Unified CME also populate the host portion of the redirect contact header with the session target IP address or hostname of the matching dial peer.

When the **host-registrars** command and the **registrars** command are both configured in SIP user-agent configuration mode, the SIP gateway or Cisco Unified CME populate the host portion of both the diversion and redirect contact headers with the domain name or IP address configured by the **registrars** command.

The **host-registrars** command should be configured along with the **registrars** command in SIP user-agent configuration mode. If the **host-registrars** command is configured without the **registrars** command, the host portion of the diversion header is populated with the domain name or IP address of the gateway and the host portion of the redirect contact header is populated with the session target IP address or hostname of the matching dial peer.

How to Configure SIP Diversion Header Enhancements

To configure the SIP Diversion Header Enhancements feature, complete this task in this section.



Note

Some keywords and arguments have been omitted from the command syntax shown here. For complete command syntax information, see the Cisco IOS Voice Command Reference at the following URL: http://www.cisco.com/en/US/docs/ios/voice/command/reference/vr_book.html

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **sip-ua**
4. **registrars** *registrars-server-address*
5. **host-registrars**

DETAILED STEPS

Command or Action	Purpose
Step 1 enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.

Command or Action	Purpose
<p>Step 2 <code>configure terminal</code></p> <p>Example:</p> <pre>Router# configure terminal</pre>	Enters global configuration mode.
<p>Step 3 <code>sip-ua</code></p> <p>Example:</p> <pre>Router(config)# sip-ua</pre>	Enters SIP User Agent configuration mode.
<p>Step 4 <code>registrar registrar-server-address</code></p> <p>Example:</p> <pre>Router(config-sip-us)# registrar ipv4:10.1.1.1</pre>	<p>The SIP registrar server address to be used for endpoint registration. This value can be entered in one of three formats:</p> <ul style="list-style-type: none"> • dns: <i>address</i> --the Domain Name System (DNS) address of the primary SIP registrar server (the dns: delimiter must be included as the first four characters). • ipv4: <i>address</i> --the IP address of the SIP registrar server (the ipv4: delimiter must be included as the first five characters). • ipv6:[<i>address</i>] --the IPv6 address of the SIP registrar server (the ipv6: delimiter must be included as the first five characters and the address itself must include opening and closing square brackets).
<p>Step 5 <code>host-registrar</code></p> <p>Example:</p> <pre>Router(config-sip-ua)# host- registrar</pre>	Populates the SIP User Agetnet registrar domain name or IP address value in the host portion of the diversion header and redirects the contact header of the 302 response.

Feature Information for SIP Diversion Header Enhancements

The following table provides release information about the feature or features described in this module. This table lists only the software release that introduced support for a given feature in a given software release train. Unless noted otherwise, subsequent releases of that software release train also support that feature.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Feature History Table entry for the Cisco Unified Border Element.

Table 45 Feature Information for SIP Diversion Header Enhancements

Feature Name	Releases	Feature Information
SIP Diversion Header Enhancements	12.4(22)T	<p>The SIP Diversion Header Enhancements feature enables time-division multiplex (TDM) gateways and Cisco Unified Communications Manager Express to populate the SIP Diversion Header with a domain name. This feature also provides choice of transparent pass through or application of address hiding to the SIP Diversion Header on Cisco UBE platforms.</p> <p>This feature modifies the following commands: host-registrar, and registrar</p>

Feature History Table entry for the Cisco Unified Border Element (Enterprise).

Table 46 Feature Information for SIP Diversion Header Enhancements

Feature Name	Releases	Feature Information
SIP Diversion Header Enhancements	Cisco IOS XE Release 3.1S	<p>The SIP Diversion Header Enhancements feature enables time-division multiplex (TDM) gateways and Cisco Unified Communications Manager Express to populate the SIP Diversion Header with a domain name. This feature also provides choice of transparent pass through or application of address hiding to the SIP Diversion Header on Cisco UBE platforms.</p> <p>This feature modifies the following commands: host-registrar, and registrar</p>

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: www.cisco.com/go/trademarks. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams,

and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.



SIP History INFO

The SIP History-info Header Support feature provides support for the history-info header in SIP INVITE messages only. The SIP gateway generates history information in the INVITE message for all forwarded and transferred calls. The history-info header records the call or dialog history. The receiving application uses the history-info header information to determine how and why the call has reached it.

- [Finding Feature Information, page 169](#)
- [Prerequisites, page 169](#)
- [Configuring SIP History INFO, page 169](#)
- [Feature Information for SIP History-info Header, page 170](#)

Finding Feature Information

Your software release may not support all the features documented in this module. For the latest feature information and caveats, see the release notes for your platform and software release. To find information about the features documented in this module, and to see a list of the releases in which each feature is supported, see the Feature Information Table at the end of this document.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Prerequisites

Cisco Unified Border Element

- Cisco IOS Release 12.4(22)T or a later release must be installed and running on your Cisco Unified Border Element.

Cisco Unified Border Element (Enterprise)

- Cisco IOS XE Release 3.1 or a later release must be installed and running on your Cisco ASR 1000 Series Router.

Configuring SIP History INFO

To configure the SIP History INFO feature, see the Configuring SIP History-info Header Support section of the "Cisco IOS SIP Configuration Guide, Release 15.1" at the following URL: http://www.cisco.com/en/US/docs/ios/voice/sip/configuration/guide/sip_cg-msg_tmr_rspns.html#wp1073292

Feature Information for SIP History-info Header

The following table provides release information about the feature or features described in this module. This table lists only the software release that introduced support for a given feature in a given software release train. Unless noted otherwise, subsequent releases of that software release train also support that feature.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Feature History Table entry for the Cisco Unified Border Element.

Table 47 Feature Information for SIP History-info Header

Feature Name	Releases	Feature Information
SIP History-info Header	12.4(22)T	<p>The SIP History-info feature provides the capability for the SIP TDM gateway to generate History-info messages in the INVITE dialog for calls that are forwarded or transferred. Cisco Unified Border Element platforms transparently pass the History-info across SIP legs. The receiving application uses the history-info header information to determine how and why the call has reached it.</p> <p>The following commands were introduced or modified: history-info and voice-class sip history-info</p>

Feature History Table entry for the Cisco Unified Border Element (Enterprise).

Table 48 **Feature Information for SIP History-info Header**

Feature Name	Releases	Feature Information
SIP History-info Header	Cisco IOS XE Release 3.1S	<p>The SIP History-info feature provides the capability for the SIP TDM gateway to generate History-info messages in the INVITE dialog for calls that are forwarded or transferred. Cisco Unified Border Element platforms transparently pass the History-info across SIP legs. The receiving application uses the history-info header information to determine how and why the call has reached it.</p> <p>The following commands were introduced or modified: history-info and voice-class sip history-info.</p>

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: www.cisco.com/go/trademarks. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.



SIP Ability to Send a SIP Registration Message on a Border Element

- Configure a registrar in sip UA configuration mode.

Cisco Unified Border Element

- Cisco IOS Release 12.4(24)T or a later release must be installed and running on your Cisco Unified Border Element.

Cisco Unified Border Element (Enterprise)

- Cisco IOS XE Release 2.5 or a later release must be installed and running on your Cisco ASR 1000 Series Router.

The SIP: Ability to Send a SIP Registration Message on a Border Element feature allows users to register e164 numbers from the Cisco UBE without POTS dial-peers in the UP state. Registration messages can include numbers, number ranges (such as E.164-numbers), or text information.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **sip-ua**
4. **credentials username *username* password *password* realm *domain-name***
5. **exit**
6. **end**

DETAILED STEPS

	Command or Action	Purpose
Step 1	enable	Enables privileged EXEC mode. <ul style="list-style-type: none">• Enter your password if prompted.
	Example: Router> enable	

	Command or Action	Purpose
Step 2	configure terminal Example: <pre>Router# configure terminal</pre>	Enters global configuration mode.
Step 3	sip-ua Example: <pre>Router(config)# sip-ua</pre>	Enters sip user-agent configuration mode.
Step 4	credentials username <i>username</i> password <i>password</i> realm <i>domain-name</i> Example: <pre>Router(config-sip-ua)# credentials username alex password test realm cisco.com</pre>	Enters SIP digest credentials in sip-ua configuration mode.
Step 5	exit Example: <pre>Router(config-sip-ua)# exit</pre>	Exits the current mode.
Step 6	end Example: <pre>Router(config)# end</pre>	Returns to privileged EXEC mode.

- [Finding Feature Information, page 174](#)
- [Feature Information for Sending a SIP Registration Message from a Cisco Unified Border Element, page 175](#)

Finding Feature Information

Your software release may not support all the features documented in this module. For the latest feature information and caveats, see the release notes for your platform and software release. To find information about the features documented in this module, and to see a list of the releases in which each feature is supported, see the Feature Information Table at the end of this document.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Feature Information for Sending a SIP Registration Message from a Cisco Unified Border Element

The following table provides release information about the feature or features described in this module. This table lists only the software release that introduced support for a given feature in a given software release train. Unless noted otherwise, subsequent releases of that software release train also support that feature.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Feature History Table entry for the Cisco Unified Border Element.

Table 49 Feature Information for Sending a SIP Registration Message from a Cisco Unified Border Element

Feature Name	Releases	Feature Information
SIP: Ability to Send a SIP Registration Message on a Border Element	12.4(24)T	Provides the ability to send a SIP Registration Message from Cisco Unified Border Element. The following command was modified: credentials (SIP UA)

Feature History Table entry for the Cisco Unified Border Element (Enterprise).

Table 50 Feature Information for Sending a SIP Registration Message from a Cisco Unified Border Element

Feature Name	Releases	Feature Information
SIP: Ability to Send a SIP Registration Message on a Border Element	Cisco IOS XE Release 2.5	Provides the ability to send a SIP Registration Message from Cisco Unified Border Element. The following command was modified: credentials (SIP UA)

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: www.cisco.com/go/trademarks. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.



Configurable SIP Parameters via DHCP

The Configurable SIP Parameters via DHCP feature allows a Dynamic Host Configuration Protocol (DHCP) server to provide Session Initiation Protocol (SIP) parameters via a DHCP client. These parameters are used for user registration and call routing.

The DHCP server returns the SIP Parameters via DHCP options 120 and 125. These options are used to specify the SIP user registration and call routing information. The SIP parameters returned are the SIP server address via Option 120, and vendor-specific information such as the pilot, contract or primary number, an additional range of secondary numbers, and the SIP domain name via Option 125.

In the event of changes to the SIP parameter values, this feature also allows a DHCP message called DHCPFORCERENEW to reset or apply a new set of values.

The SIP parameters provisioned by DHCP are stored, so that on reboot they can be reused.

- [Finding Feature Information, page 177](#)
- [Prerequisites for Configurable SIP Parameters via DHCP, page 177](#)
- [Restrictions for Configurable SIP Parameters via DHCP, page 178](#)
- [Information About Configurable SIP Parameters via DHCP, page 178](#)
- [How to Configure SIP Parameters via DHCP, page 181](#)
- [Feature Information for Configurable SIP Parameters via DHCP, page 189](#)

Finding Feature Information

Your software release may not support all the features documented in this module. For the latest feature information and caveats, see the release notes for your platform and software release. To find information about the features documented in this module, and to see a list of the releases in which each feature is supported, see the Feature Information Table at the end of this document.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Prerequisites for Configurable SIP Parameters via DHCP

- A DHCP interface has to be associated with SIP before configurable SIP parameters via DHCP can be enabled.

Cisco Unified Border Element

- Cisco IOS Release 12.4(22)YB or a later release must be installed and running on your Cisco Unified Border Element.

Cisco Unified Border Element (Enterprise)

- Cisco IOS XE Release <TBD> or a later release must be installed and running on your Cisco ASR 1000 Series Router.

Restrictions for Configurable SIP Parameters via DHCP

- DHCP Option 120 is the standard DHCP option (RFC3361) to get a SIP server address, and this can be used by any vendor DHCP server. Only one address is supported, which is in the IPv4 address format. Multiple IPv4 address entries are not supported. Also, there is no support for a DNS name in this or for any port number given behind the IPv4 address.
- DHCP Option 125 (RFC 3925) provides vendor-specific information and its interpretation is associated with the enterprise identity. The primary and secondary phone numbers and domain are obtained using Option 125, which is vendor-specific. As long as other customers use the same format as in the Next Generation Network (NGN) DHCP specification, they can use this feature.
- A primary or contract number is required in suboption 202 of DHCP Option 125. There can be only one instance of the primary number and not multiple instances.
- Multiple secondary or numbers in suboption 203 of DHCP Option 125 are supported. Up to five numbers are accepted and the rest ignored. Also, they have to follow the contract number in the DHCP packet data.
- Authentication is not supported for REGISTER and INVITE messages sent from a Cisco Unified Border Element that uses DHCP provisioning
- The DHCP provisioning of SIP Parameters is supported only over one DHCP interface.
- The DHCP option is available only to be configured for the primary registrar. It will not be available for a secondary registrar.

Information About Configurable SIP Parameters via DHCP

To perform basic Configurable SIP Parameters via DHCP configuration tasks, you should understand the following concepts:

Cisco Unified Border Element Support for Configurable SIP Parameters via DHCP

The Cisco Unified Border Element provides the support for the DHCP provisioning of the SIP parameters. The NGN is modeled using SIP as a VoIP protocol. In order to connect to NGN, the User to Network Interface (UNI) specification is used. Cisco TelePresence Systems (CTS), consisting of an IP Phone, a codec, and Cisco Unified Communications Manager, are required to interconnect over the NGN for point-to-point and point-to-multipoint video calls. Because Cisco Unified Communications Manager does not provide a UNI interface, there has to be an entity to provide the UNI interface. The Cisco Unified Border Element provides the UNI interface and has several advantages such as demarcation, delayed offer to early offer, and registration.

The figure below shows the Cisco Unified Border Element providing the UNI interface for the NGN.

Figure 6 Cisco NGN with Cisco Unified Border Element providing UNI interface



DHCP to Provision SIP Server, Domain Name, and Phone Number

NGN requires Cisco Unified Border Element to support DHCP (RFC 2131 and RFC 2132) to provision the following:


- IP address for Cisco Unified Border Element's UNI interface facing NGN
- SIP server address using option 120
- Option 125 vendor specific information to get:
 - Pilot number (also called primary or contract number), there is only one pilot number in DHCPACK, and REGISTER is done only for the pilot number
 - Additional numbers, or secondary numbers, are in DHCPACK; there is no REGISTER for additional numbers
 - SIP domain name
- DHCPFORCERENEW to reset or apply a new set of SIP parameters (RFC 3203)

DHCP-SIP Call Flow

The following scenario shows the DHCP messages involved in provisioning information such as the IP address for UNI interface, and SIP parameters including the SIP server address, phone number, and domain name, along with how SIP messages use the provisioned information.

The figure below shows the DHCP and SIP messages involved in obtaining the SIP parameters and using them for REGISTER and INVITE.


Figure 7 DHCP-SIP Call Flow



DHCP Message Details

The DHCP call flow involved in obtaining Cisco Unified Border Element provision information, including the IP address for UNI interface and SIP information such as phone number, domain, and SIP server, is shown in the figure below.

Figure 8 DHCP Message Details



The DHCP messages involved in provisioning the SIP parameters are described in Steps 1 to 6.

- 1 F1: The Cisco Unified Border Element DHCP client sends a DHCPDISCOVER message to find the available NGN DHCP servers on the network and obtain a valid IPv4 address. The Cisco Unified Border Element DHCP client identity (computer name) and MAC address are included in this message.
- 2 F2: The Cisco Unified Border Element DHCP client receives a DHCPOFFER message from each available NGN DHCP server. The DHCPOFFER message includes the offered DHCP server's IPv4 address, the DHCP client's MAC address, and other configuration parameters.
- 3 F3: The Cisco Unified Border Element DHCP client selects an NGN DHCP server and its IPv4 address configuration from the DHCPOFFER messages it receives, and sends a DHCPREQUEST message requesting its usage. Note that this is where Cisco Unified Border Element requests SIP server information via DHCP Option 120 and vendor-identifying information via DHCP Option 125.
- 4 F4: The chosen NGN DHCP server assigns its IPv4 address configuration to the Cisco Unified Border Element DHCP client by sending a DHCPACK message to it. The Cisco Unified Border Element DHCP client receives the DHCPACK message. This is where the SIP server address, phone number and

domain name information are received via DHCP options 120 and 125. The Cisco Unified Border Element will use the information for registering the phone number and routing INVITE messages to the given SIP server.

- 5 F5: When NGN has a change of information or additional information (such as changing SIP server address from 1.1.1.1 to 2.2.2.2) for assigning to Cisco Unified Border Element, the DHCP server initiates DHCPFORCERENEW to the Cisco Unified Border Element. If the authentication is successful, the Cisco Unified Border Element DHCP client accepts the DHCPFORCERENEW and moves to the next stage of sending DHCPREQUEST. Otherwise DHCPFORCERENEW is ignored and the current information is retained and used.
- 6 F6 and F7: In response to DHCPFORCERENEW, similar to steps F3 and F4, the Cisco Unified Border Element requests DHCP Options 120 and 125. Upon getting the response, SIP will apply these parameters if they are different by sending an UN-REGISTER message for the previous phone number and a REGISTER message for the new number. Similarly, a new domain and SIP server address will be used. If the returned information is the same as the current set, it is ignored and hence registration and call routing remains the same.

How to Configure SIP Parameters via DHCP

- [Configuring the DHCP Client, page 181](#)
- [Configuring the DHCP Client Example, page 183](#)
- [Enabling the SIP Configuration, page 183](#)
- [Enabling the SIP Configuration Example, page 185](#)
- [Troubleshooting Tips, page 185](#)
- [Configuring a SIP Outbound Proxy Server, page 185](#)
- [Configuring a SIP Outbound Proxy Server in Voice Service VoIP Configuration Mode, page 186](#)
- [Configuring a SIP Outbound Proxy Server in Voice Service VoIP Configuration Mode Example, page 187](#)
- [Configuring a SIP Outbound Proxy Server and Session Target in Dial Peer Configuration Mode, page 187](#)
- [Configuring a SIP Outbound Proxy Server in Dial Peer Configuration Mode Example, page 189](#)

Configuring the DHCP Client

To receive the SIP configuration parameters the Cisco Unified Border Element has to act as a DHCP client. This is because in the NGN network, a DHCP server pushes the configuration to a DHCP client. Thus the Cisco Unified Border Element must be configured as a DHCP client.

Perform this task to configure the DHCP client.

You must configure the **ip dhcp client** commands before entering the **ip address dhcp** command on an interface to ensure that the DHCPDISCOVER messages that are generated contain the correct option values. The **ip dhcp client** commands are checked only when an IP address is acquired from DHCP. If any of the **ip dhcp client** commands are entered after an IP address has been acquired from DHCP, the DHCPDISCOVER messages' correct options will not be present or take effect until the next time the router acquires an IP address from DHCP. This means that the new configuration will only take effect after either the **ip address dhcp** command or the **release dhcp** and **renew dhcp EXEC** commands have been configured.

SUMMARY STEPS

1. enable
2. configure terminal
3. interface type number
4. ip dhcp client request sip-server-address
5. ip dhcp client request vendor-identifying-specific
6. ip address dhcp
7. exit

DETAILED STEPS

Command or Action	Purpose
Step 1 enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2 configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3 interface type number Example: Router(config)# interface gigabitethernet 0/0	Configures an interface type and enters interface configuration mode.
Step 4 ip dhcp client request sip-server-address Example: Router(config-if)# ip dhcp client request sip-server-address	Configures the DHCP client to request a SIP server address from a DHCP server.
Step 5 ip dhcp client request vendor-identifying-specific Example: Router(config-if)# ip dhcp client request vendor-identifying-specific	Configures the DHCP client to request vendor-specific information from a DHCP server.

Command or Action	Purpose
Step 6 <code>ip address dhcp</code> Example: Router(config-if)# <code>ip address dhcp</code>	Acquires an IP address on the interface from the DHCP.
Step 7 <code>exit</code> Example: Router(config-if)# <code>exit</code>	Exits the current mode.

Configuring the DHCP Client Example

The following is an example of how to enable the DHCP client:

```
Router> enable
Router# configure terminal
Router(config)# interface gigabitethernet 1/1
Router(config-if)# ip dhcp client request sip-server-address
Router(config-if)# ip dhcp client request vendor-identifying-specific
Router(config-if)# ip address dhcp
Router(config-if)# exit
```

Enabling the SIP Configuration

Enabling the SIP configuration allows the Cisco Unified Border Element to use the SIP parameters received via DHCP for user registration and call routing. Perform this task to enable the SIP configuration.

The **dhcp interface** command has to be entered to declare the interface before the **registrar** and **credential** commands are entered.

SUMMARY STEPS

1. `enable`
2. `configure terminal`
3. `interface type number`
4. `sip-ua`
5. `dhcp interface type number`
6. `registrar dhcp expires seconds random-contact refresh-ratio seconds`
7. `credentials dhcp password [0|7] password realm domain-name`
8. `exit`

DETAILED STEPS

Command or Action	Purpose
<p>Step 1 <code>enable</code></p> <p>Example:</p> <pre>Router> enable</pre>	<p>Enables privileged EXEC mode.</p> <ul style="list-style-type: none"> Enter your password if prompted.
<p>Step 2 <code>configure terminal</code></p> <p>Example:</p> <pre>Router# configure terminal</pre>	<p>Enters global configuration mode.</p>
<p>Step 3 <code>interface type number</code></p> <p>Example:</p> <pre>Router(config)# interface gigabitethernet 0/0</pre>	<p>Configures an interface type and enters interface configuration mode.</p>
<p>Step 4 <code>sip-ua</code></p> <p>Example:</p> <pre>Router(config-if)# sip-ua</pre>	<p>Enters SIP user-agent configuration mode.</p>
<p>Step 5 <code>dhcp interface type number</code></p> <p>Example:</p> <pre>Router(sip-ua)# dhcp interface gigabitethernet 0/0</pre>	<p>Assigns a specific interface for DHCP provisioning of SIP parameters.</p> <ul style="list-style-type: none"> Multiple interfaces on the CUBE can be configured with DHCP--this command specifies the DHCP interface used with SIP.
<p>Step 6 <code>registrar dhcp expires seconds random-contact refresh-ratio seconds</code></p> <p>Example:</p> <pre>Router(sip-ua)# registrar dhcp expires 100 random-contact refresh-ratio 90</pre>	<p>Registers E.164 numbers on behalf of analog telephone voice ports (FXS) and IP phone virtual voice ports (EFXS) with an external SIP proxy or SIP registrar server.</p> <ul style="list-style-type: none"> expires <i>seconds</i> --Specifies the default registration time, in seconds. Range is 60 to 65535. Default is 3600. refresh-ratio <i>seconds</i> --Specifies the refresh-ratio, in seconds. Range is 1 to 100 seconds. Default is 80.

Command or Action	Purpose
<p>Step 7 <code>credentials dhcp password [0 7] password realm domain-name</code></p> <p>Example:</p> <pre>Router(sip-ua)# credentials dhcp password cisco realm cisco.com</pre>	Sends a SIP registration message from a Cisco Unified Border Element in the UP state.
<p>Step 8 <code>exit</code></p> <p>Example:</p> <pre>Router(sip-ua)# exit</pre>	Exits the current mode.

Enabling the SIP Configuration Example

The following is an example of how to enable the SIP configuration:

```
Router> enable
Router# configure terminal
Router(config)# interface gigabitethernet 1/0
Router(config-if)# sip-ua
Router(sip-ua)# dhcp interface gigabitethernet 1/0
Router(sip-ua)# registrar dhcp expires 90 random-contact refresh-ratio 90
Router(sip-ua)# credentials dhcp password cisco realm cisco.com
Router(sip-ua)# exit
```

Troubleshooting Tips

To display information on DHCP and SIP interaction when SIP parameters are provisioned by DHCP, use the `debug ccsip dhcp` command in privileged EXEC mode.

Configuring a SIP Outbound Proxy Server

An outbound-proxy configuration sets the Layer 3 address (IP address) for any outbound REGISTER and INVITE SIP messages. The SIP server can be configured as an outbound proxy server in voice service SIP configuration mode or dial peer configuration mode. When enabled in voice service SIP configuration mode, all the REGISTER and INVITE messages are forwarded to the configured outbound proxy server. When enabled in dial-peer configuration mode, only the messages hitting the defined dial-peer will be forwarded to the configured outbound proxy server.

The configuration tasks in each mode are presented in the following sections:

Perform either of these tasks to configure the SIP server as a SIP outbound proxy server.

Configuring a SIP Outbound Proxy Server in Voice Service VoIP Configuration Mode

Perform this task to configure the SIP server as a SIP outbound proxy server in voice service SIP configuration mode.

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **voice service voip**
4. **sip**
5. **outbound-proxy dhcp**
6. **exit**

DETAILED STEPS

Command or Action	Purpose
Step 1 enable Example: Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2 configure terminal Example: Router# configure terminal	Enters global configuration mode.
Step 3 voice service voip Example: Router(config)# voice service voip	Enters voice service VoIP configuration mode and specifies VoIP as the voice-encapsulation type.
Step 4 sip Example: Router(config-voi-srv)# sip	Enters voice service SIP configuration mode.

Command or Action	Purpose
Step 5 <code>outbound-proxy dhcp</code> Example: <code>Router(config-serv-sip)# outbound-proxy dhcp</code>	Configures the DHCP client to request a SIP server address from a DHCP server.
Step 6 <code>exit</code> Example: <code>Router(config-serv-sip)# exit</code>	Exits the current mode.

Configuring a SIP Outbound Proxy Server in Voice Service VoIP Configuration Mode Example

The following is an example of how to configure a SIP outbound proxy in voice service SIP configuration mode:

```
Router> enable
Router# configure terminal

Router(config)# voice service voip
Router(config-voi-srv)# sip
Router(config-serv-sip)# outbound-proxy dhcp
Router(config-serv-if)# exit
```

Configuring a SIP Outbound Proxy Server and Session Target in Dial Peer Configuration Mode

Perform this task to configure the SIP server as a SIP outbound proxy server in dial peer configuration mode.



Note

SIP must be configured on the dial peer before DHCP is configured. Therefore the **session protocol sipv2** command must be executed before the **session target dhcp** command. DHCP is supported only with SIP configured on the dial peer.

>

SUMMARY STEPS

1. enable
2. configure terminal
3. dial-peer voice number voip
4. session protocol sipv2
5. voice-class sip outbound-proxy dhcp
6. session target dhcp
7. exit

DETAILED STEPS

Command or Action	Purpose
<p>Step 1 enable</p> <p>Example:</p> <pre>Router> enable</pre>	<p>Enables privileged EXEC mode.</p> <ul style="list-style-type: none"> • Enter your password if prompted.
<p>Step 2 configure terminal</p> <p>Example:</p> <pre>Router# configure terminal</pre>	<p>Enters global configuration mode.</p>
<p>Step 3 dial-peer voice number voip</p> <p>Example:</p> <pre>Router(config)# dial-peer voice 10 voip</pre>	<p>Defines a dial peer, specifies VoIP as the method of voice encapsulation, and enters dial peer configuration mode.</p>
<p>Step 4 session protocol sipv2</p> <p>Example:</p> <pre>Router(config-dial-peer)# session protocol sipv2</pre>	<p>Enters the session protocol type as SIP.</p>
<p>Step 5 voice-class sip outbound-proxy dhcp</p> <p>Example:</p> <pre>Router(config-dial-peer)# voice-class sip outbound-proxy dhcp</pre>	<p>Configures the SIP server received from the DHCP server as a SIP outbound proxy server.</p>

Command or Action	Purpose
<p>Step 6 <code>session target dhcp</code></p> <p>Example:</p> <pre>Router(config-dial-peer)# session target dhcp</pre>	<p>Specifies that the DHCP protocol is used to determine the IP address of the session target.</p>
<p>Step 7 <code>exit</code></p> <p>Example:</p> <pre>Router(config-dial-peer)# exit</pre>	<p>Exits the current mode.</p>

Configuring a SIP Outbound Proxy Server in Dial Peer Configuration Mode Example

The following is an example of how to configure a SIP outbound proxy in dial peer configuration mode:

```
Router> enable
Router# configure terminal
Router(config)# dial-peer voice 11 voip
Router(config-dial-peer)# session protocol sipv2

Router(config-dial-peer)# voice-class sip outbound-proxy dhcp
Router(config-dial-peer)# session target dhcp
Router(config-dial-peer)# exit
```

Feature Information for Configurable SIP Parameters via DHCP

The following table provides release information about the feature or features described in this module. This table lists only the software release that introduced support for a given feature in a given software release train. Unless noted otherwise, subsequent releases of that software release train also support that feature.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Feature History Table for the ISR.

Table 51 **Feature Information for Configurable SIP Parameters via DHCP**

Feature Name	Releases	Feature Information
Configurable SIP Parameters via DHCP	12.4(22)YB 15.0(1)M	<p>The Configurable SIP Parameters via DHCP feature introduces the configuring of SIP parameters via DHCP.</p> <p>The following commands were introduced or modified: credentials (sip-ua), debug ccsip dhcp, dhcp interface, ip dhcp-client forcerenew, outbound-proxy, registrar, session target (VoIP dial peer), show sip dhcp, voice-class sip outbound-proxy.</p>

Feature History Table for the ASR.

Table 52 **Feature Information for Configurable SIP Parameters via DHCP**

Feature Name	Releases	Feature Information
Configurable SIP Parameters via DHCP	IOS XE Release <TBD>	<p>The Configurable SIP Parameters via DHCP feature introduces the configuring of SIP parameters via DHCP.</p> <p>The following commands were introduced or modified: credentials (sip-ua), debug ccsip dhcp, dhcp interface, ip dhcp-client forcerenew, outbound-proxy, registrar, session target (VoIP dial peer), show sip dhcp, voice-class sip outbound-proxy.</p>

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: www.cisco.com/go/trademarks. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.



Multiple Registrars on SIP Trunks

The Support for Multiple Registrars on SIP Trunks on a Cisco Unified Border Element, on Cisco IOS SIP TDM Gateways, and on a Cisco Unified Communications Manager Express feature allows configuration of multiple registrars on Session Initiation Protocol (SIP) trunks, each simultaneously registered using its respective authentication instance. Beginning with Cisco IOS XE Release 3.1S, support for this feature is expanded to include the Cisco ASR 1000 Series Router. This feature allows a redundant registrar for each of the SIP trunks, which provides SIP trunk redundancy across multiple service providers.

- [Finding Feature Information, page 191](#)
- [Prerequisites for Multiple Registrars on SIP Trunks, page 191](#)
- [Restrictions for Multiple Registrars on SIP Trunks, page 192](#)
- [Configuring Multiple Registrars on SIP Trunks Feature, page 192](#)
- [Feature Information for the Multiple Registrars on SIP Trunks Feature, page 192](#)

Finding Feature Information

Your software release may not support all the features documented in this module. For the latest feature information and caveats, see the release notes for your platform and software release. To find information about the features documented in this module, and to see a list of the releases in which each feature is supported, see the Feature Information Table at the end of this document.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Prerequisites for Multiple Registrars on SIP Trunks

Cisco Unified Border Element

- Cisco IOS Release 15.0(1)XA or a later release must be installed and running on your Cisco Unified Border Element.

Cisco Unified Border Element (Enterprise)

- Cisco IOS XE Release 3.1S or a later release must be installed and running on your Cisco ASR 1000 Series Router.

Restrictions for Multiple Registrars on SIP Trunks

The Support for Multiple Registrars on SIP trunks feature has the following restrictions:

- Old and new forms of the **registrar** command are mutually exclusive: the registrar can be configured in either primary/secondary mode or multiple registrar mode--not both.
- Dynamic Host Configuration Protocol (DHCP) support is not available with multiple registrars (available for primary/secondary mode only).
- Only one authentication configuration per username can be configured at any one time.
- A maximum of six registrars can be configured at any given time.
- A maximum of 12 different realms can be configured for each endpoint.
- You cannot restrict the registration of specific endpoints with specific registrars--once a new registrar is configured, all endpoints will begin registering to the new registrar.
- You cannot remove multiple configurations of credentials simultaneously--only one credential can be removed at a time.

Configuring Multiple Registrars on SIP Trunks Feature

For information about the Support for Multiple Registrars on SIP Trunks feature and for detailed procedures for enabling this feature, see the "Configuring Multiple Registrars on SIP Trunks" chapter of the Cisco IOS SIP Configuration Guide.

Feature Information for the Multiple Registrars on SIP Trunks Feature

The following table provides release information about the feature or features described in this module. This table lists only the software release that introduced support for a given feature in a given software release train. Unless noted otherwise, subsequent releases of that software release train also support that feature.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Feature History Table entry for the Cisco Unified Border Element.

Table 53 **Feature Information for the Multiple Registrars on SIP Trunks Feature**

Feature Name	Releases	Feature Information
Multiple Registrars on SIP Trunks	15.0(1)XA 15.1(1)T	<p>This feature provides support for multiple registrars on SIP trunks on Cisco IOS SIP TDM gateways, Cisco Unified CME, and Cisco UBEs. This feature allows for a redundant registrar for each SIP trunk and enables registrar redundancy across multiple service providers.</p> <p>This feature includes the following new or modified commands: credentials, localhost, registrar, voice-class sip localhost.</p>

Feature History Table entry for the Cisco Unified Border Element (Enterprise) .

Table 54 **Feature Information for the Multiple Registrars on SIP Trunks Feature**

Feature Name	Releases	Feature Information
Multiple Registrars on SIP Trunks	Cisco IOS XE Release 3.1S	<p>This feature provides support for multiple registrars on SIP trunks on Cisco IOS SIP TDM gateways, Cisco Unified CME, and Cisco UBEs. This feature allows for a redundant registrar for each SIP trunk and enables registrar redundancy across multiple service providers.</p> <p>This feature includes the following new or modified commands: credentials, localhost, registrar, voice-class sip localhost.</p>

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: www.cisco.com/go/trademarks. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams,

and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.



Additional References

The following sections provide references related to the Cisco Unified Border Element (Enterprise) Configuration Guide.

- [Related Documents](#), page 195
- [Standards](#), page 196
- [MIBs](#), page 196
- [RFCs](#), page 197
- [Technical Assistance](#), page 198

Related Documents

Related Topic	Document Title
Cisco IOS commands	Cisco IOS Master Commands List, All Releases
Cisco IOS Voice commands	<i>Cisco IOS Voice Command Reference</i>
Cisco IOS Voice Configuration Library	For more information about Cisco IOS voice features, including feature documents, and troubleshooting information--at http://www.cisco.com/en/US/docs/ios/12_3/vvf_c/cisco_ios_voice_configuration_library_glossary/vcl.htm
Cisco IOS Release 15.0	Cisco IOS Release 15.0 Configuration Guides
Cisco IOS Release 12.2	Cisco IOS Voice, Video, and Fax Configuration Guide, Release 12.2

Related Topic	Document Title
internet Low Bitrate Codec (iLBC) Documents	<ul style="list-style-type: none"> Codecs section of the Dial Peer Configuration on Voice Gateway Routers Guide <p>http://www.cisco.com/en/US/docs/ios/12_3/vvf_c/dial_peer/dp_ovrvw.html</p> <ul style="list-style-type: none"> Dial Peer Features and Configuration section of the Dial Peer Configuration on Voice Gateway Routers Guide <p>http://www.cisco.com/en/US/docs/ios/12_3/vvf_c/dial_peer/dp_config.html</p>
Related Application Guides	<ul style="list-style-type: none"> <i>Cisco Unified Communications Manager and Cisco IOS Interoperability Guide</i> <i>Cisco IOS SIP Configuration Guide</i> Cisco Unified Communications Manager (CallManager) Programming Guides
Troubleshooting and Debugging guides	<ul style="list-style-type: none"> Cisco IOS Debug Command Reference, Release 12.4 at <p>http://www.cisco.com/en/US/docs/ios/debug/command/reference/db_book.html</p> <ul style="list-style-type: none"> <i>Troubleshooting and Debugging VoIP Call Basics</i> at http://www.cisco.com/en/US/tech/tk1077/technologies_tech_note09186a0080094045.shtml <i>VoIP Debug Commands</i> at <p>http://www.cisco.com/en/US/docs/routers/access/1700/1750/software/configuration/guide/debug.html</p>

Standards

Standard	Title
ITU-T G.711	--

MIBs

MIB	MIBs Link
<ul style="list-style-type: none"> • CISCO-PROCESS MIB • CISCO-MEMORY-POOL-MIB • CISCO-SIP-UA-MIB • DIAL-CONTROL-MIB • CISCO-VOICE-DIAL-CONTROL-MIB • CISCO-DSP-MGMT-MIB • IF-MIB • IP-TAP-MIB • TAP2-MIB • USER-CONNECTION-TAP-MIB 	<p>To locate and download MIBs for selected platforms, Cisco IOS XE software releases, and feature sets, use Cisco MIB Locator found at the following URL:</p> <p>http://www.cisco.com/go/mibs</p>

RFCs

RFC	Title
RFC 1889	<i>RTP: A Transport Protocol for Real-Time Applications</i>
RFC 2131	<i>Dynamic Host Configuration Protocol</i>
RFC 2132	<i>DHCP Options and BOOTP Vendor Extensions</i>
RFC 2198	<i>RTP Payload for Redundant Audio Data</i>
RFC 2327	<i>SDP: Session Description Protocol</i>
RFC 2543	<i>SIP: Session Initiation Protocol</i>
RFC 2543-bis-04	<i>SIP: Session Initiation Protocol, draft-ietf-sip-rfc2543bis-04.txt</i>
RFC 2782	<i>A DNS RR for Specifying the Location of Services (DNS SRV)</i>
RFC 2833	<i>RTP Payload for DTMF Digits, Telephony Tones and Telephony Signals</i>
RFC 3203	<i>DHCP reconfigure extension</i>
RFC 3261	<i>SIP: Session Initiation Protocol</i>
RFC 3262	<i>Reliability of Provisional Responses in Session Initiation Protocol (SIP)</i>
RFC 3323	<i>A Privacy Mechanism for the Session Initiation Protocol (SIP)</i>

RFC	Title
RFC 3325	<i>Private Extensions to the Session Initiation Protocol (SIP) for Asserted Identity within Trusted Networks</i>
RFC 3515	<i>The Session Initiation Protocol (SIP) Refer Method</i>
RFC 3361	<i>Dynamic Host Configuration Protocol (DHCP-for-IPv4) Option for Session Initiation Protocol (SIP) Servers</i>
RFC 3455	<i>Private Header (P-Header) Extensions to the Session Initiation Protocol (SIP) for the 3rd-Generation Partnership Project (3GPP)</i>
RFC 3608	<i>Session Initiation Protocol (SIP) Extension Header Field for Service Route Discovery During Registration</i>
RFC 3711	<i>The Secure Real-time Transport Protocol (SRTP)</i>
RFC 3925	<i>Vendor-Identifying Vendor Options for Dynamic Host Configuration Protocol version 4 (DHCPv4)</i>

Technical Assistance

Description	Link
<p>The Cisco Support website provides extensive online resources, including documentation and tools for troubleshooting and resolving technical issues with Cisco products and technologies.</p> <p>To receive security and technical information about your products, you can subscribe to various services, such as the Product Alert Tool (accessed from Field Notices), the Cisco Technical Services Newsletter, and Really Simple Syndication (RSS) Feeds.</p> <p>Access to most tools on the Cisco Support website requires a Cisco.com user ID and password.</p>	<p>http://www.cisco.com/cisco/web/support/index.html</p>



Glossary

AMR-NB --Adaptive Multi Rate codec - Narrow Band.

Allow header --Lists the set of methods supported by the UA generating the message.

bind -- In SIP, configuring the source address for signaling and media packets to the IP address of a specific interface.

call --In SIP, a call consists of all participants in a conference invited by a common source. A SIP call is identified by a globally unique call identifier. A point-to-point IP telephony conversation maps into a single SIP call.

call leg --A logical connection between the router and another endpoint.

CLI --command-line interface.

Content-Type header --Specifies the media type of the message body.

CSeq header --Serves as a way to identify and order transactions. It consists of a sequence number and a method. It uniquely identifies transactions and differentiates between new requests and request retransmissions.

delta --An incremental value. In this case, the delta is the difference between the current time and the time when the response occurred. **dial peer**--An addressable call endpoint.

dial peer --An addressable call endpoint.

DNS --Domain Name System. Used to translate H.323 IDs, URLs, or e-mail IDs to IP addresses. DNS is also used to assist in locating remote gatekeepers and to reverse-map raw IP addresses to host names of administrative domains.

DNS SRV --Domain Name System Server. Used to locate servers for a given service.

DSP --Digital Signal Processor.

DTMF --dual-tone multifrequency. Use of two simultaneous voice-band tones for dialing (such as touch-tone).

EFXS --IP phone virtual voice ports.

FQDN --fully qualified domain name. Complete domain name including the host portion; for example, *serverA.companyA.com*.

FXS --analog telephone voice ports.

gateway --A gateway allows SIP or H.323 terminals to communicate with terminals configured to other protocols by converting protocols. A gateway is the point where a circuit-switched call is encoded and repackaged into IP packets.

H.323 --An International Telecommunication Union (ITU-T) standard that describes packet-based video, audio, and data conferencing. H.323 is an umbrella standard that describes the architecture of the

conferencing system and refers to a set of other standards (H.245, H.225.0, and Q.931) to describe its actual protocol.

iLBC --internet Low Bitrate Codec.

INVITE--A SIP message that initiates a SIP session. It indicates that a user is invited to participate, provides a session description, indicates the type of media, and provides insight regarding the capabilities of the called and calling parties.

IP-- Internet Protocol. A connectionless protocol that operates at the network layer (Layer 3) of the OSI model. IP provides features for addressing, type-of-service specification, fragmentation and reassemble, and security. Defined in RFC 791. This protocol works with TCP and is usually identified as TCP/IP. See TCP/IP.

ISDN --Integrated Services Digital Network.

Minimum Timer --Configured minimum value for session interval accepted by SIP elements (proxy, UAC, UAS). This value helps minimize the processing load from numerous INVITE requests.

Min-SE --Minimum Session Expiration. The minimum value for session expiration.

multicast --A process of transmitting PDUs from one source to many destinations. The actual mechanism (that is, IP multicast, multi-unicast, and so forth) for this process might be different for LAN technologies.

originator --User agent that initiates the transfer or Refer request with the recipient.

PDU --protocol data units. Used by bridges to transfer connectivity information.

PER --Packed Encoding Rule.

proxy --A SIP UAC or UAS that forwards requests and responses on behalf of another SIP UAC or UAS.

proxy server --An intermediary program that acts as both a server and a client for the purpose of making requests on behalf of other clients. Requests are serviced internally or by passing them on, possibly after translation, to other servers. A proxy interprets and, if necessary, rewrites a request message before forwarding it.

recipient --User agent that receives the Refer request from the originator and is transferred to the final recipient.

redirect server --A server that accepts a SIP request, maps the address into zero or more new addresses, and returns these addresses to the client. It does not initiate its own SIP request or accept calls.

re-INVITE --An INVITE request sent during an active call leg.

Request URI --Request Uniform Resource Identifier. It can be a SIP or general URL and indicates the user or service to which the request is being addressed.

RFC --Request For Comments.

RTP --Real-Time Transport Protocol (RFC 1889)

SCCP --Skinny Client Control Protocol.

SDP--Session Description Protocol. Messages containing capabilities information that are exchanged between gateways.

session --A SIP session is a set of multimedia senders and receivers and the data streams flowing between the senders and receivers. A SIP multimedia conference is an example of a session. The called party can be invited several times by different calls to the same session.

session expiration --The time at which an element considers the call timed out if no successful INVITE transaction occurs first.

session interval --The largest amount of time that can occur between INVITE requests in a call before a call is timed out. The session interval is conveyed in the Session-Expires header. The UAS obtains this

value from the Session-Expires header of a 2xx INVITE response that it sends. Proxies and UACs determine this value from the Session-Expires header in a 2xx INVITE response they receive.

SIP --Session Initiation Protocol. An application-layer protocol originally developed by the Multiparty Multimedia Session Control (MMUSIC) working group of the Internet Engineering Task Force (IETF). Their goal was to equip platforms to signal the setup of voice and multimedia calls over IP networks. SIP features are compliant with IETF RFC 2543, published in March 1999.

SIP URL --Session Initiation Protocol Uniform Resource Locator. Used in SIP messages to indicate the originator, recipient, and destination of the SIP request. Takes the basic form of *user@host*, where *user* is a name or telephone number, and *host* is a domain name or network address.

SPI --service provider interface.

socket listener -- Software provided by a socket client to receives datagrams addressed to the socket.

stateful proxy --A proxy in keepalive mode that remembers incoming and outgoing requests.

TCP --Transmission Control Protocol. Connection-oriented transport layer protocol that provides reliable full-duplex data transmissions. TCP is part of the TCP/IP protocol stack. See also TCP/IP and IP.

TDM --time-division multiplexing.

UA --user agent. A combination of UAS and UAC that initiates and receives calls. See **UAS** and **UAC**.

UAC --user agent client. A client application that initiates a SIP request.

UAS --user agent server. A server application that contacts the user when a SIP request is received and then returns a response on behalf of the user. The response accepts, rejects, or redirects the request.

UDP -- User Datagram Protocol. Connectionless transport layer protocol in the TCP/IP protocol stack. UDP is a simple protocol that exchanges datagrams without acknowledgments or guaranteed delivery, requiring that error processing and retransmission be handled by other protocols. UDP is defined in RFC-768.

URI --Uniform Resource Identifier. Takes a form similar to an e-mail address. It indicates the user's SIP identity and is used for redirection of SIP messages.

URL --Universal Resource Locator. Standard address of any resource on the Internet that is part of the World Wide Web (WWW).

User Agent --A combination of UAS and UAC that initiates and receives calls. See **UAS** and **UAC**.

VFC --Voice Feature Card.

VoIP --Voice over IP. The ability to carry normal telephone-style voice over an IP-based Internet with POTS-like functionality, reliability, and voice quality. VoIP is a blanket term that generally refers to the Cisco standards-based approach (for example, H.323) to IP voice traffic.

