



EMC XtremIO Tasks

This chapter contains the following sections:

- [Add XtremIO Initiator, on page 3](#)
- [Add XtremIO Volume to Consistency Group, on page 4](#)
- [Associate XtremIO LUN as Datastore, on page 5](#)
- [Attach XtremIO Tag, on page 6](#)
- [Create XtremIO Consistency Group, on page 7](#)
- [Create XtremIO Initiator Group, on page 8](#)
- [Create XtremIO Scheduler, on page 9](#)
- [Create XtremIO Snapshot Set, on page 10](#)
- [Create XtremIO Tag, on page 11](#)
- [Create XtremIO Volume, on page 12](#)
- [Create XtremIO iSCSI Portal, on page 13](#)
- [Create XtremIO iSCSI Route, on page 14](#)
- [Delete XtremIO Consistency Group, on page 15](#)
- [Delete XtremIO Initiator, on page 16](#)
- [Delete XtremIO Initiator Group, on page 17](#)
- [Delete XtremIO Scheduler, on page 18](#)
- [Delete XtremIO Snapshot, on page 19](#)
- [Delete XtremIO Snapshot Set, on page 20](#)
- [Delete XtremIO Tag, on page 21](#)
- [Delete XtremIO Volume, on page 22](#)
- [Delete XtremIO iSCSI Portal, on page 23](#)
- [Delete XtremIO iSCSI Route, on page 24](#)
- [Detach XtremIO Tag, on page 25](#)
- [Disable XtremIO Snapshot Scheduler, on page 26](#)
- [Enable XtremIO Snapshot Scheduler, on page 27](#)
- [Map XtremIO Volume, on page 28](#)
- [Modify XtremIO Initiator, on page 29](#)
- [Modify XtremIO Scheduler, on page 30](#)
- [Modify XtremIO Volume, on page 31](#)
- [Remove XtremIO Volume from Consistency Group, on page 32](#)
- [Rename XtremIO Consistency Group, on page 33](#)
- [Rename XtremIO Initiator Group, on page 34](#)

- [Rename XtremIO Tag, on page 35](#)
- [UnMap XtremIO Volume, on page 36](#)

Add XtremIO Initiator

Summary

Adds an XtremIO Initiator.

Description

Use this task to add an initiator into XMS.

Inputs

Input	Description	Mappable To Type	Mandatory
XtremIO Account Name	Select Account name	EMCXtremIOAccountIdentity	Y
Initiator Group	Select initiator group name	EMCXtremIOInitiatorGroup Identity	Y
Initiator Name	Enter initiator name	gen_text_input	
Port Address	Enter port address	gen_text_input	Y
Operating System	Select Operating System	EMCXtremIOInitiatorOSList	Y

Outputs

Output	Description	Type
OUTPUT EMC XTREMIO INITIATOR_IDENTITY	EMC XtremIO Initiator Identity	EMCXtremIOInitiatorIdentity
OUTPUT EMC XTREMIO INITIATOR_GROUP_IDENTITY	EMC XtremIO Initiator Group Identity	EMCXtremIOInitiatorGroup Identity
OUTPUT EMC XTREMIO ACCOUNT_IDENTITY	EMC XtremIO Account Identity	EMCXtremIOAccount Identity
OUTPUT EMC XTREMIO_INFRA_ACCOUNT	EMC XtremIO Account Name	EMCXtremIOAccountName

Add XtremIO Volume to Consistency Group

Summary

Adds an XtremIO Volume to Consistency Group.

Description

Use this task to add an XtremIO Volume to a Consistency group in XMS. Consistency Groups (CGs) are used to create a consistent image of a set of volumes, usually used by a single application such as database. With XtremIO CGs, you can create a snapshot of all the volumes in a group using a single command. This ensures that all volumes are created at the same time. Many operations that are applied on a single volume can also be applied on a CG.

Inputs

Input	Description	Mappable To Type	Mandatory
Consistency Group	Select consistency group	EMCXtremIOConsistencyGroup Identity	Y
Volume	Select volume	EMCXtremIOVolumeIdentity	Y

Outputs

Output	Description	Type
OUTPUT EMC XTREMIO CONSISTENCY_GROUP_IDENTITY	Output of consistency group identity	EMCXtremIOConsistency GroupIdentity
OUTPUT EMC XTREMIO_INFRA_ACCOUNT	EMC XtremIO Account Name	EMCXtremIOAccountName
OUTPUT EMC XTREMIO_ACCOUNT_IDENTITY	EMC XtremIO Account Identity	EMCXtremIOAccountIdentity
OUTPUT EMC XTREMIO_VOLUME_IDENTITY	EMC XtremIO Volume Identity	EMCXtremIOVolumeIdentity

Associate XtremIO LUN as Datastore

Summary

Associates an XtremIO LUN as a Datastore.

Description

This task associates an existing EMCXtremIO LUN as a datastore in XMS.

Inputs

Input	Description	Mappable To Type	Mandatory
XtremIO Account	Select XtremIO Account name	EMCxtremIOAccountIdentity	Y
Datastore Name	Enter a new datastore name.	gen_text_input	
Create DataStore On	Select option to create Datastore on Cluster Level/Host Level	EmcXtremIODataStoreCreationOption	Y
Select Cluster	Select a cluster to create datastore.	EMCxtremIOVMWareClusterIdentity	
Select Hostnode	Select a hostnode to create datastore.	vmwareHostNodeIdentity	Y
Initiator Type	Select the type.	EMCxtremIOPrototype	
Volume	Select Volume name to associate with datastore.	EMCxtremIOVolumeIdentity	Y
VDC Name	Select vDC to assign storage policy.	vDC	
Success Criteria	Select an option from list to pass the task	EMCxtremIOMountDatastoreSuccessCriteria	Y

Outputs

Output	Description	Type
OUTPUT EMC XTREMIO DATASTORE_NAME	Datastore name	dataStoreName
OUTPUT_VMWARE_ACCOUNT_NAME	VMware account name.	gen_text_input
OUTPUT_VMWARE_DATASTORE_IDENTITY	Datastore name identity	vmwareDatastoreIdentity
OUTPUT_VMWARE_DATASTORE_INFO_IDENTITY	Datastore Info identity	gen_text_input
OUTPUT_VMWARE_HOST_NODE_IDENTITY	VMware Host Node Identity	vmwareHostNodeIdentity
OUTPUT EMC XTREMIO_VMWARE_CLUSTER_IDENTITY	Output of VMWare Cluster identity	EMCxtremIOVMWareClusterIdentity
OUTPUT_VMWARE_HOST_NODE_NAME	Host Node Name.	vmwareHostMultiSelect

Attach XtremIO Tag

Summary

Attaches an XtremIO Tag.

Description

Use this task to attach a tag to a Volume, Initiator Group, Initiator, Snapshot, or Consistency Group in XMS.

Inputs

Input	Description	Mappable To Type	Mandatory
XtremIO Account Name	Select Account name	EMCXtremIOAccountIdentity	Y
Resource Type	Select the type of Resource	EMCXtremIOtagObjectType List	Y
XtremIO Volume	Select EMC XtremIO Volume to attach Tag	EMCXtremIOVolumeIdentity	Y
XtremIO Initiator Group	Select EMC XtremIO Initiator to attach Tag	EMCXtremIOInitiatorGroup Identity	Y
XtremIO Initiator	Select EMC XtremIO Initiator to attach Tag	EMCXtremIOInitiatorIdentity	Y
XtremIO Consistency Group	Select EMC XtremIO Consistency Group to attach Tag	ConsistencyGroup	Y
Tag Name	Select the tag Name	EMCXtremIOtagIdentity	Y

Outputs

Output	Description	Type
OUTPUT EMC XTREMIO TAG IDENTITY	EMC XtremIO Tag Identity	EMCXtremIOtagIdentity
OUTPUT EMC XTREMIO ACCOUNT IDENTITY	EMC XtremIO Account Identity	EMCXtremIOAccount Identity
OUTPUT EMC XTREMIO INFRA ACCOUNT	EMC XtremIO Account Name	EMCXtremIOAccountName

Create XtremIO Consistency Group

Summary

Creates an XtremIO Consistency Group.

Description

Use this task to create a Consistency Group and associate it with a list of Volumes in XMS.

Inputs

Input	Description	Mappable To Type	Mandatory
XtremIO Account Name	Select Account name	EMCXtremIOAccountIdentity	Y
Consistency Group Name	Enter Consistency Group Name	gen_text_input	
Volume	Select volume to add into Consistency Group	EMCXtremIOVolumeIdentity	

Outputs

Output	Description	Type
OUTPUT EMC XTREMIO CONSISTENCY_GROUP_IDENTITY	Output of consistency group identity	EMCXtremIOConsistencyGroupIdentity
OUTPUT EMC XTREMIO_INFRA_ACCOUNT	EMC XtremIO Account Name	EMCXtremIOAccountName
OUTPUT EMC XTREMIO_ACCOUNT_IDENTITY	EMC XtremIO Account Identity	EMCXtremIOAccountIdentity
OUTPUT EMC XTREMIO_VOLUME_IDENTITY	EMC XtremIO Volume Identity	EMCXtremIOVolumeIdentity

Create XtremIO Initiator Group

Summary

Creates an EMC XtremIO Initiator Groups.

Description

Use this task to add initiator Groups into XMS.

Inputs

Input	Description	Mappable To Type	Mandatory
XtremIO Account Name	Select Account name	EMCXtremIOAccountIdentity	Y
Initiator Group Name	Select initiator group name	gen_text_input	
Initiators	Enter port address	gen_text_input	

Outputs

Output	Description	Type
OUTPUT EMC XTREMIO INITIATOR_GROUP_NAME	EMC XtremIO Initiator Group Name	gen_text_input
OUTPUT EMC XTREMIO INITIATOR_GROUP_IDENTITY	EMC XtremIO Initiator Group Identity	EMCXtremIOInitiator GroupIdentity
OUTPUT EMC XTREMIO ACCOUNT_IDENTITY	EMC XtremIO Account Identity	EMCXtremIOAccount Identity
OUTPUT EMC XTREMIO INFRA_ACCOUNT	EMC XtremIO Account Name	EMCXtremIOAccount Name

Create XtremIO Scheduler

Summary

Creates an XtremIO Scheduler.

Description

Use this task to create a Scheduler on a Volume, Snapshot, or Consistency Group in XMS.

Inputs

Input	Description	Mappable To Type	Mandatory
XtremIO Account Name	Select Account name	EMCXtremIOAccountIdentity	Y
Scheduler to be created On	Select option on which Scheduler has to be created	EMCXtremIOSnapshotType List	Y
Volume	Select volume	EMCXtremIOVolumeIdentity	Y
Consistency Group	Select consistency group	EMCXtremIOConsistency GroupIdentity	Y
Schedule	Schedule is specified explicitly or by intervals.	EMCXtremIOSnapshot ScheduleList	Y
Snapshot Fixed Scheduled	Enter Schedule in hh:mm:ss format	gen_text_input	Y
Snapshot Explicit Schedule	Enter Schedule in hh:mm format	gen_text_input	Y
Snapshot Explicit Scheduled Day	Enter Day for Scheduling	EMCXtremIOSnapshot ScheduleDayList	Y
Number of Snapshots to keep	Select The number of Snapshots to keep	gen_text_input	Y
Suffix	Enter suffix	gen_text_input	
Snapshot Type	Enter Snapshot type	EMCXtremIOSnapshotType PropertyList	Y

Outputs

Output	Description	Type
OUTPUT EMC XTREMIO INFRA ACCOUNT	EMC XtremIO Account Name	EMCXtremIOAccountName
OUTPUT EMC XTREMIO ACCOUNT_IDENTITY	EMC XtremIO Account Identity	EMCXtremIOAccount Identity
OUTPUT EMC XTREMIO SCHEDULER_IDENTITY	EMC XtremIO Scheduler Identity	EMCXtremIOScheduler Identity

Create XtremIO Snapshot Set

Summary

Creates an XtremIO Snapshot Set.

Description

Use this task to create a Snapshot Set on a Volume, Consistency Group, or Snapshot set in XMS.

Inputs

Input	Description	Mappable To Type	Mandatory
Account Name	Select Account	EMCXtremIOAccountIdentity	Y
Snapshot Set Name	Enter Snapshot Set name	gen_text_input	
Snapshot Suffix	A String added after a Snapshot name	gen_text_input	
Type	Select the type of Snapshot Set.	EMCXtremIOSnapshotTypePropertyList	Y
Snapshot Origin Type	Select the origin type of Snapshot Set.	EMCXtremIOSnapshotTypeList	Y
Source Volumes	Select Source volumes	EMCXtremIOVolumeIdentityList	Y
Source Consistency Group	Select Source Consistency Group	EMCXtremIOConsistencyGroupIdentity	Y
Source Snapshot Set	Select Source Snapshot Set	EMCXtremIOSnapshotSetIdentity	Y

Outputs

Output	Description	Type
OUTPUT EMC XTREMEIO SNAPSHOT SET IDENTITY	Output of Snapshot Set identity	EMCXtremIOSnapshotSetIdentity
OUTPUT EMC XTREMIO ACCOUNT IDENTITY	EMC XtremIO Account Identity	EMCXtremIOAccountIdentity

Create XtremIO Tag

Summary

Create an XtremIO Tag.

Description

Use this task to create a tag in XMS.

Inputs

Input	Description	Mappable To Type	Mandatory
XtremIO Account Name	Select Account name	EMCXtremIOAccountIdentity	Y
Tag Name	Enter Tag name	gen_text_input	
Resource Type	Select the type of resource.	EMCXtremIOTagObjectTypeList	Y
Parent Tag	Select the Parent Tag.	EMCXtremIOParentTagList	

Outputs

Output	Description	Type
OUTPUT EMC XTREMIO TAG IDENTITY	EMC XtremIO Tag Identity	EMCXtremIOTagIdentity
OUTPUT EMC XTREMIO ACCOUNT IDENTITY	EMC XtremIO Account Identity	EMCXtremIOAccountIdentity
OUTPUT EMC XTREMIO INFRA ACCOUNT	EMC XtremIO Account Name	EMCXtremIOAccountName

Create XtremIO Volume

Summary

Creates an EMC XtremIO Volume.

Description

Use this task to add a volume to XMS.

Inputs

Input	Description	Mappable To Type	Mandatory
XtremIO Account Name	Select Account name	EMCXtremIOAccountIdentity	Y
Volume Name	Enter volume name	gen_text_input	
Volume Size	Enter volume size	gen_text_input	Y
Capacity Type	Select the type of device capacity (KB,MB,GB,TB,PB)	EMCXtremIODeviceCapacityTypeList	Y
Logical block size	Select volume block size	EMCXtremIOVolumeLBSizeList	
Small Input/Output Alerts	Select small IO alerts	EMCXtremIOVolumeAlertList	
Unaligned Input/Output Alerts	Select unaligned IO alerts	EMCXtremIOVolumeAlertList	
VAAI TP Alerts	Select VAAI TP alerts	EMCXtremIOVolumeAlertList	

Outputs

Output	Description	Type
OUTPUT EMC XTREMIO VOLUME_IDENTITY	EMC XtremIO Volume Identity	EMCXtremIOVolumeIdentity
OUTPUT EMC XTREMIO_INFRA_ACCOUNT	EMC XtremIO Account Name	EMCXtremIOAccountName
OUTPUT EMC XTREMIO_ACCOUNT_IDENTITY	EMC XtremIO Account Identity	EMCXtremIOAccountIdentity

Create XtremIO iSCSI Portal

Summary

Creates an EMC XtremIO iSCSI Portal.

Description

Use this task to create an iSCSI portal in XMS.

Inputs

Input	Description	Mappable To Type	Mandatory
XtremIO Account	Select XtremIO Account	EMCXtremIOAccountIdentity	Y
IP Address	Enter IP Address in CIDR notation for iSCSI Portal Only	gen_text_input	Y
VLAN	Enter Vlan Number for iSCSI Portal	gen_text_input	
iSCSI Target	Select iSCSI Target	EMCXtremIOTargetPort Identity	Y

Outputs

Output	Description	Type
OUTPUT_EMC_XTREMIO_iSCSI_PORTAL_IDENTITY	Output of iSCSI Portal identity	EMCXtremIOiSCSIPortal Identity
OUTPUT_EMC_XTREMIO_INFRA_ACCOUNT	EMC XtremIO Account Name	EMCXtremIOAccount Name
OUTPUT_EMC_XTREMIO_ISCSI_PORT_ADDRESS	iSCSI Port Address	gen_text_input
OUTPUT_EMC_XTREMIO_ISCSI_PORTAL_VLAN_ID	iSCSI Portal VLAN id	gen_text_input
OUTPUT_EMC_XTREMIO_ISCSI_PORTAL_IP_ADDRESS	iSCSI Portal IP Address	gen_text_input
OUTPUT_EMC_XTREMIO_ACCOUNT_IDENTITY	EMC XtremIO Account Identity	EMCXtremIOAccount Identity

Create XtremIO iSCSI Route

Summary

Creates an EMC XtremIO iSCSI Route.

Description

Use this task to create an iSCSI Route in XMS.

Inputs

Input	Description	Mappable To Type	Mandatory
XtremIO Account Name	Select Account name	EMCXtremIOAccount Identity	Y
Name	Enter name for the iSCSI Route.	gen_text_input	
Destination Network	Enter Destination Network address for iSCSI Route in CIDR format	gen_text_input	Y
Gateway Address	Enter Gateway Address	gen_text_input	Y

Outputs

Output	Description	Type
OUTPUT_EMC_XTREMIO_INFRA_ACCOUNT	EMC XtremIO Account Name	EMCXtremIOAccountName
OUTPUT_EMC_XTREMIO_iSCSI_ROUTE_IDENTITY	Output of iSCSI Route identity	EMCXtremIOiSCSIRoute Identity
OUTPUT_EMC_XTREMIO_ACCOUNT_IDENTITY	EMC XtremIO Account Identity	EMCXtremIOAccount Identity

Delete XtremIO Consistency Group

Summary

Deletes an XtremIO Consistency Group.

Description

Use this task to delete a Consistency Group from XMS.

Inputs

Input	Description	Mappable To Type	Mandatory
Consistency Group	Select consistency group	EMCXtremIOConsistencyGroup Identity	Y

Outputs

Output	Description	Type
OUTPUT_EMC_XTREMIO_CONSISTENCY_GROUP_IDENTITY	Output of consistency group identity	EMCXtremIOConsistencyGroupIdentity
OUTPUT_EMC_XTREMIO_INFRA_ACCOUNT	EMC XtremIO Account Name	EMCXtremIOAccountName
OUTPUT_EMC_XTREMIO_ACCOUNT_IDENTITY	EMC XtremIO Account Identity	EMCXtremIOAccountIdentity

Delete XtremIO Initiator

Summary

Deletes an EMC XtremIO Initiator.

Description

Use this task to delete an Initiator from XMS.

Inputs

Input	Description	Mappable To Type	Mandatory
XtremIO Initiator	Select EMC XtremIO Initiator to delete	EMCXtremIOInitiatorIdentity	Y

Outputs

No Outputs

Delete XtremIO Initiator Group

Summary

Deletes an EMC XtremIO Initiator Group.

Description

Use this task to delete an Initiator Group from XMS.

Inputs

Input	Description	Mappable To Type	Mandatory
XtremIO Initiator Group	Select EMC XtremIO Initiator to delete	EMCXtremIOInitiatorGroup Identity	Y

Outputs

No Outputs

Delete XtremIO Scheduler

Summary

Deletes an XtremIO Scheduler.

Description

Use this task to delete Schedulers created on a Volume, Snapshot, or Consistency Group in XMS.

Inputs

Input	Description	Mappable To Type	Mandatory
XtremIO Scheduler	Select EMC XtremIO Scheduler to delete	EMCXtremIOScheduler Identity	Y

Outputs

No Outputs

Delete XtremIO Snapshot

Summary

Deletes an XtremIO Snapshot.

Description

Use this task to delete a Snapshot from a Snapshot Set created on a Volume, Consistency Group, or Snapshot Set in XMS.

Inputs

Input	Description	Mappable To Type	Mandatory
XtremIO Snapshot	Select EMC XtremIO Snapshot to delete	EMCXtremIOSnapshots Identity	Y

Outputs

No Outputs

Delete XtremIO Snapshot Set

Summary

Deletes an XtremIO Snapshot Set.

Description

Use this task to delete a Snapshot Set created on a Volume, Consistency Group, or Snapshot set.

Inputs

Input	Description	Mappable To Type	Mandatory
Snapshot Set	Select EMC XtremIO Snapshot Set to delete	EMCXtremIOSnapshotSet Identity	Y

Outputs

No Outputs

Delete XtremIO Tag

Summary

Deletes an XtremIO Tag.

Description

Use this task to delete a tag in XMS.

Inputs

Input	Description	Mappable To Type	Mandatory
XtremIO Tag	Select EMC XtremIO Tag to delete	EMCXtremIOtagIdentity	Y

Outputs

No Outputs

Delete XtremIO Volume

Summary

Deletes an EMC XtremIO Volume.

Description

Use this task to delete a volume from XMS.

Inputs

Input	Description	Mappable To Type	Mandatory
XtremIO Volume	Select EMC XtremIO Volume to delete	EMCXtremIOVolumeIdentity	Y

Outputs

No Outputs

Delete XtremIO iSCSI Portal

Summary

Delete EMC XtremIO iSCSI Portal

Description

This task is used to remove iSCSI Portal details in XMS.

Inputs

Input	Description	Mappable To Type	Mandatory
iSCSI Portal	Select EMC XtremIO iSCSI Portal to delete	EMCXtremIOiSCSIPortal Identity	Y

Outputs

No Outputs

Delete XtremIO iSCSI Route

Summary

Deletes an EMC XtremIO iSCSI Route.

Description

Use this task to remove an iSCSI Route in XMS.

Inputs

Input	Description	Mappable To Type	Mandatory
iSCSI Route	Select EMC XtremIO iSCSI Route to delete	EMCXtremIOiSCSIRoute Identity	Y

Outputs

No Outputs

Detach XtremIO Tag

Summary

Detaches an XtremIO Tag.

Description

Use this task to detach the tag of a Volume, Initiator Group, Initiator, Snapshot or Consistency Group in XMS.

Inputs

Input	Description	Mappable To Type	Mandatory
XtremIO Account Name	Select Account name	EMCXtremIOAccountIdentity	Y
Resource Type	Select the type of Resource	EMCXtremIOTagObjectType List	Y
XtremIO Volume	Select EMC XtremIO Volume to attach Tag	EMCXtremIOVolumeIdentity	Y
XtremIO Initiator Group	Select EMC XtremIO Initiator to attach Tag	EMCXtremIOInitiatorGroup Identity	Y
XtremIO Initiator	Select EMC XtremIO Initiator to attach Tag	EMCXtremIOInitiatorIdentity	Y
XtremIO Consistency Group	Select EMC XtremIO Consistency Group to attach Tag	EMCXtremIOConsistency GroupIdentity	Y
Tag Name	Select the tag Name	EMCXtremIOTagIdentity	Y

Outputs

Output	Description	Type
OUTPUT_EMC_XTREMIO_TAG_IDENTITY	EMC XtremIO Tag Identity	EMCXtremIOTagIdentity
OUTPUT_EMC_XTREMIO_ACCOUNT_IDENTITY	EMC XtremIO Account Identity	EMCXtremIOAccount Identity
OUTPUT_EMC_XTREMIO_INFRA_ACCOUNT	EMC XtremIO Account Name	EMCXtremIOAccountName

Disable XtremIO Snapshot Scheduler

Summary

Disables an XtremIO Snapshot Scheduler.

Description

Use this task to disable a Scheduler created on a Volume, Snapshot, or Consistency Group in XMS.

Inputs

Input	Description	Mappable To Type	Mandatory
XtremIO Scheduler	Select EMC XtremIO Scheduler to disable	EMCXtremIOScheduler Identity	Y

Outputs

Output	Description	Type
OUTPUT EMC XTREMIO INFRA ACCOUNT	EMC XtremIO Account Name	EMCXtremIOAccountName
OUTPUT EMC XTREMIO ACCOUNT_IDENTITY	EMC XtremIO Account Identity	EMCXtremIOAccount Identity
OUTPUT EMC XTREMIO SCHEDULER_IDENTITY	EMC XtremIO Scheduler Identity	EMCXtremIOScheduler Identity

Enable XtremIO Snapshot Scheduler

Summary

Enables an EMC XtremIO Scheduler.

Description

Use this task to enable Schedulers created on a Volume, Snapshot, or Consistency Group in XMS.

Inputs

Input	Description	Mappable To Type	Mandatory
XtremIO Scheduler	Select EMC XtremIO Scheduler to enable	EMCXtremIOScheduler Identity	Y

Outputs

Output	Description	Type
OUTPUT_EMC_XTREMIO_INFRA_ACCOUNT	EMC XtremIO Account Name	EMCXtremIOAccountName
OUTPUT_EMC_XTREMIO_ACCOUNT_IDENTITY	EMC XtremIO Account Identity	EMCXtremIOAccount Identity
OUTPUT_EMC_XTREMIO_SCHEDULER_IDENTITY	EMC XtremIO Scheduler Identity	EMCXtremIOScheduler Identity

Map XtremIO Volume

Summary

Creates an EMC XtremIO LUN Mapping

Description

Use this task to create a LUN mapping between a Volume and an Initiator Group in XMS.

Inputs

Input	Description	Mappable To Type	Mandatory
XtremIO Account	Select Account name	EMCXtremIOAccountIdentity	Y
Volume	Select Volume	EMCXtremIOVolumeIdentity	Y
Initiator Group	Select Initiator Group	EMCXtremIOInitiatorGroup Identity	Y
LUN ID	Enter LUN ID as integer value and not more than 16383	gen_text_input	

Outputs

Output	Description	Type
OUTPUT EMC XTREMIO INFRA ACCOUNT	EMC XtremIO Account Name	EMCXtremIOAccountName
OUTPUT EMC XTREMIO ACCOUNT_IDENTITY	EMC XtremIO Account Identity	EMCXtremIOAccount Identity
OUTPUT EMC XTREMIO INITIATOR_GROUP_IDENTITY	EMC XtremIO Initiator Group Identity	EMCXtremIOInitiatorGroup Identity
OUTPUT EMC XTREMIO LUN_IDENTITY	EMC XtremIO LUN Identity	EMCXtremIOLunMap Identity
OUTPUT EMC XTREMEIO_HOST_LUN_ID	EMC XtremIO Host LUN ID	gen_text_input
OUTPUT EMC XTREMIO VOLUME_IDENTITY	EMC XtremIO Volume Identity	EMCXtremIOVolume Identity

Modify XtremIO Initiator

Summary

Modifies an EMC XtremIO Initiator.

Description

Use this task to modify Initiator parameters in XMS.

Inputs

Input	Description	Mappable To Type	Mandatory
XtremIO Initiator	Select EMC XtremIO Initiator to modify	EMCXtremIOInitiatorIdentity	Y
Initiator Name	Enter initiator name	gen_text_input	Y
Port Address	Enter port address	gen_text_input	Y
Operating System	Select Operating System	EMCXtremIOInitiatorOSList	Y

Outputs

Output	Description	Type
OUTPUT_EMC_XTREMIO_INITIATOR_IDENTITY	EMC XtremIO Initiator Identity	EMCXtremIOInitiatorIdentity
OUTPUT_EMC_XTREMIO_ACCOUNT_IDENTITY	EMC XtremIO Account Identity	EMCXtremIOAccountIdentity
OUTPUT_EMC_XTREMIO_INFRA_ACCOUNT	EMC XtremIO Account Name	EMCXtremIOAccountName

Modify XtremIO Scheduler

Summary

Modifies an XtremIO Scheduler.

Description

Use this task to modify a Scheduler created on a Volume, Snapshot, or Consistency Group in XMS.

Inputs

Input	Description	Mappable To Type	Mandatory
XtremIO Scheduler	Select EMC XtremIO Scheduler to delete	EMCXtremIOScheduler Identity	Y
Schedule	Schedule Every Day or Explicitly	EMCXtremIOSnapshot ScheduleList	Y
Snap Shot Fixed Interval	Enter Schedule in hh:mm:ss format	gen_text_input	Y
Snap shot Explicit Schedule	Enter Schedule in hh:mm format	gen_text_input	Y
Snapshot Explicit Scheduled Day	Enter Day for Scheduling	EMCXtremIOSnapshot ScheduleDayList	Y
Number of Snapshots to keep	Select The number of Snapshots to keep	gen_text_input	Y
Suffix	Text adjoined to the scheduler's stem name	gen_text_input	
Snapshot Type	Select Snapshot type read/write or read	EMCXtremIOSnapshotType PropertyList	

Outputs

Output	Description	Type
OUTPUT EMC XTREMIO INFRA ACCOUNT	EMC XtremIO Account Name	EMCXtremIOAccountName
OUTPUT EMC XTREMIO ACCOUNT_IDENTITY	EMC XtremIO Account Identity	EMCXtremIOAccount Identity
OUTPUT EMC XTREMIO SCHEDULER_IDENTITY	EMC XtremIO Scheduler Identity	EMCXtremIOScheduler Identity

Modify XtremIO Volume

Summary

Modifies an EMC XtremIO Volume.

Description

Use this task to modify volume parameters in XMS.

Inputs

Input	Description	Mappable To Type	Mandatory
XtremIO Volume	Select EMC XtremIO Volume to modify	EMCXtremIOVolumeIdentity	Y
Volume Name	Enter volume name	gen_text_input	Y
Volume Size	Enter volume size	gen_text_input	Y
Capacity Type	Select the type of device capacity (MB, GB, Cylinders)	EMCXtremIODeviceCapacityTypeList	Y
Small Input/Output Alerts	Select small IO alerts	EMCXtremIOVolumeAlertList	
Unaligned Input/Output Alerts	Select unaligned IO alerts	EMCXtremIOVolumeAlertList	
VAAI TP Alerts	Select VAAI TP alerts	EMCXtremIOVolumeAlertList	

Outputs

Output	Description	Type
OUTPUT_EMC_XTREMIO_VOLUME_IDENTITY	EMC XtremIO Volume Identity	EMCXtremIOVolumeIdentity
OUTPUT_EMC_XTREMIO_INFRA_ACCOUNT	EMC XtremIO Account Name	EMCXtremIOAccountName
OUTPUT_EMC_XTREMIO_ACCOUNT_IDENTITY	EMC XtremIO Account Identity	EMCXtremIOAccountIdentity

Remove XtremIO Volume from Consistency Group

Summary

Removes an XtremIO Volume from a Consistency Group.

Description

Use this task to remove an associated volume from a Consistency Group in XMS.

Inputs

Input	Description	Mappable To Type	Mandatory
Consistency Group	Select consistency group	EMCXtremIOConsistencyGroup Identity	Y
Volume	Select volume	EMCXtremIOVolumeIdentity	Y

Outputs

Output	Description	Type
OUTPUT EMC XTREMIO CONSISTENCY_GROUP_IDENTITY	Output of consistency group identity	EMCXtremIOConsistency GroupIdentity
OUTPUT EMC XTREMIO_INFRA_ACCOUNT	EMC XtremIO Account Name	EMCXtremIOAccountName
OUTPUT EMC XTREMIO_ACCOUNT_IDENTITY	EMC XtremIO Account Identity	EMCXtremIOAccountIdentity
OUTPUT EMC XTREMIO_VOLUME_IDENTITY	EMC XtremIO Volume Identity	EMCXtremIOVolumeIdentity

Rename XtremIO Consistency Group

Summary

Renames an XtremIO Consistency Group.

Description

Use this task to rename a Consistency Group in XMS.

Inputs

Input	Description	Mappable To Type	Mandatory
Consistency Group	Select consistency group	EMCXtremIOConsistency GroupIdentity	Y
Consistency Group Name	Enter Consistency Group Name	gen_text_input	

Outputs

Output	Description	Type
OUTPUT EMC XTREMIO CONSISTENCY_GROUP_IDENTITY	Output of consistency group identity	EMCXtremIOConsistency GroupIdentity
OUTPUT EMC XTREMIO_INFRA_ ACCOUNT	EMC XtremIO Account Name	EMCXtremIOAccountName
OUTPUT EMC XTREMIO_ ACCOUNT_IDENTITY	EMC XtremIO Account Identity	EMCXtremIOAccountIdentity

Rename XtremIO Initiator Group

Summary

Renames an EMC XtremIO Initiator Group.

Description

Use this task to rename an Initiator Group in XMS.

Inputs

Input	Description	Mappable To Type	Mandatory
XtremIO Initiators Group	Select EMC XtremIO Initiators Group to rename	EMCXtremIOInitiatorGroup Identity	Y
Initiator Group Name	Enter new Initiator Group name	gen_text_input	Y

Outputs

Output	Description	Type
OUTPUT EMC XTREMIO INITIATOR_GROUP_NAME	EMC XtremIO Initiator Group Name	gen_text_input
OUTPUT EMC XTREMIO INITIATOR_GROUP_IDENTITY	EMC XtremIO Initiator Group Identity	EMCXtremIOInitiatorGroupIdentity
OUTPUT EMC XTREMIO_ACCOUNT_IDENTITY	EMC XtremIO Account Identity	EMCXtremIOAccountIdentity
OUTPUT EMC XTREMIO_INFRA_ACCOUNT	EMC XtremIO Account Name	EMCXtremIOAccountName

Rename XtremIO Tag

Summary

Renames an XtremIO Tag.

Description

Use this task to rename a tag created in XMS.

Inputs

Input	Description	Mappable To Type	Mandatory
Tag	Select EMC XtremIO Tag to rename	EMCXtremIOTagIdentity	Y
Tag Caption	Enter Tag Caption	gen_text_input	Y

Outputs

Output	Description	Type
OUTPUT_EMX_XTREMIO_TAG_IDENTITY	EMC XtremIO Tag Identity	EMCXtremIOTagIdentity
OUTPUT_EMX_XTREMIO_ACCOUNT_IDENTITY	EMC XtremIO Account Identity	EMCXtremIOAccountIdentity
OUTPUT_EMX_XTREMIO_INFRA_ACCOUNT	EMC XtremIO Account Name	EMCXtremIOAccountName

UnMap XtremIO Volume

Summary

Removes an EMC XtremIO LUN Mapping.

Description

Use this task to remove a LUN mapping from an Initiator Group and a Volume in XMS.

Inputs

Input	Description	Mappable To Type	Mandatory
XtremIO LUN	Remove Lun Mapping for selected Lun	EMCXtremIOLunMapIdentity	Y

Outputs

No Outputs