Understand how User Roles for AMP in ESA and SMA Are Configured

Contents

Introduction Prerequisites Requirements Components Used Background Information Configure For ESA Add the user role Assign the user role to a user For SMA Add the user role Assign the user role to a user

Introduction

This document describes the configuration for AMP user privileges for Cisco Secure Email and Cisco Secure Email and Web Manager

Prerequisites

Requirements

Cisco recommends knowledge of these topics:

- Cisco Secure Email (aka ESA)
- Cisco Secure Email and Cisco Secure Email and Web Manager (aka SMA)

Components Used

The information in this document is based on these software and hardware versions:

- Email Security Appliance version 14.3
- Cloud email Security version 14.3
- AMP feature key

The information in this document was created from the devices in a specific lab environment. All of the devices used in this document started with a cleared (default) configuration. If your network is live, ensure that you understand the potential impact of any command.

Background Information

This feature provides you a role for AMP configurations privileges. When this privilege is assigned to a user, the user get to configure AMP security settings only.

To view AMP-relevant reports, users can use this AMP configuration privilege to view both AMP configurations and AMP Reports. AMP Reports access is given to the 4 reports:

- Advanced Malware Protection
- AMP File Analysis
- AMP Verdict Chart Updates
- Mailbox Auto Remediation reports. (Applicable to both legacy and NGUI)

Configure

For ESA

Add the user role

You first need to create a new user role on the ESA:

- 1. Go to System Administration > User Roles
- 2. Click on "Add User Role"
- 3. Name the User Role
- 4. Select "Full Access" in AMP Configuration
- 5. Select "View relevant reports" in Email Reporting
- 6. Submit and commit

Edit User Role

Mode -Cluster: Hosted_Cluster

Centralized Management Options

Change Mode...

~

Settings			
Name:	AMP_user		
Description:	AMP user role		<i>III</i>
Access Privileges:	Mail Policies and Content Filters:	 No access View assigned, edit assig View all, edit assigned View all, edit all (full accession) 	ned ess)
	DLP Policies:	 No access View assigned, edit assig View all, edit assigned View all, edit all (full access) 	ined ess)
	AMP Configurations:	 No access Full access 	
	Email Reporting:	 No access View relevant reports* View all reports 	
	Message Tracking:	No access Message Tracking access	
	Trace:	No access Trace access	
	Quarantines:	O No access O Manage assigned quaran	tines
	Encryption Profiles:	As assigned	
	Log Subscription:	 No access Log Subscription Access 	
	*Access to reports is controlled l	by Mail Policy, DLP and AMP pr	rivileges

Assign the user role to a user

Next, you need to create a new user to assign the user role created in the previous section:

- 1. Go to System Administration > Users
- 2. Click on "Add User"
- 3. Name the user
- 4. Click on "Custom Roles" and select the User Role created previously
- 5. Submit and commit changes

Add Local User

Mode -Cluster: Hosted_Cluster		Change Mode
Centralized Management Options		
Local User Settings		
Account Status:	Active	
User Name:	amp_user	
Full Name:	AMP user privileges	
User Role: ⑦	 Predefined Roles Administrator Custom Roles Add Role AMP_user Cloud DLP Admin Cloud Guest Cloud Help Desk Cloud Operator 	
Confirm your Passphrase to make changes: Passphrase: ⑦	 Generate a passphrase Enter a passphrase of your choice Passphrase: Retype Passphrase: 	Generate

Submit

Cancel

For SMA

Add the user role

You first need to create a new user role on the SMA:

- 1. Go to System Administration > User Roles
- 2. Click on "Add User Role"
- 3. Name the User Role
- 4. Select by group or all Email appliances at your convenience "AMP reports"
- 5. Submit and commit

Edit Email User Role

Settings		
Name:	AMP_usertest	
Description:	AMP user test	
Access Privileges:	Email Reporting:	 No Access Access to data by Reporting Group All Reports Access to data from all Email Appliances AMP Reports
	Message Tracking:	 No Access View Message Tracking
	Quarantines:	No Access Quarantines Access View Only Access
	Log Subscriptions:	No Access Log Subscription Access

Cancel

Submit

Assign the user role to a user

Next, you need to create a new user to assign the user role created in the previous section

- 1. Go to System Administration > Users
- 2. Click on "Add User"
- 3. Name the user
- 4. Click on "Custom Roles" and select the User Role created previously
- 5. Submit and commit changes

Add Local User

Local User Settings	
Account Status:	Active
User Name:	amp_user
Full Name:	amp user
User Role: 🕐	 Predefined Roles Administrator Custom Roles AMP_User AMP_User_ALL AMP_usertest Cloud Guest Cloud Halp Deck
	Cloud Operator
Confirm your Passphrase to make changes:	
Passphrase: 🕐	 Generate a passphrase Generate Enter a passphrase of your choice Passphrase: Retype Passphrase:

Cancel

Submit