



# APIC - Tenant Operations

---

This chapter contains the following sections:

- [Add GUID to Tenant, on page 2](#)
- [Create APIC Tenant, on page 3](#)
- [Delete APIC Tenant, on page 5](#)
- [Delete GUID from Tenant, on page 6](#)

# Add GUID to Tenant

## Summary

Add GUID to APIC Tenant.

## Description

This task adds a GUID to a tenant.

## Inputs

Input	Description	Mappable To Type	Mandatory
Tenant	Select a tenant name.	ApicDeviceTenant Identity	Y
GUID	Enter the GUID for an SCVMM provider. GUID must be in the format:xxxxxxxx-xxxx-xxxx-xxxx-xxxxxxxxxxxxxx.	gen_text_input	Y
Account Name	Enter unique name for the SCVMM account.	gen_text_input	Y

## Outputs

Output	Description	Type
APIC_ACCOUNT	APIC Account on which the selected operation was performed	ApicDeviceIdentity
TENANT_IDENTITY	APIC Tenant Identity	ApicDeviceTenantIdentity
OUTPUT_TENANT_GUID_IDENTITY	APIC Tenant's GUID Identity	ApicTenantGUIDIdentity
OUTPUT_TENANT_GUID_ACCOUNT_NAME_IDENTITY	APIC Tenant's GUID Account Name Identity	gen_text_input

# Create APIC Tenant

## Summary

Create an APIC tenant.

## Description

This task Creates an APIC Tenant on the APIC controller.

## Inputs

Input	Description	Mappable To Type	Mandatory
APIC Account Name	Select an APIC account name.	ApicDeviceIdentity	Y
Tenant Name	Enter a tenant name.	gen_text_input	Y
Tenant Description	Enter a description. The description can be up to 128 alphanumeric characters.	gen_text_input	
Tenant Alias	Enter an alias, a changeable name for an object. Unlike the name of an object, the alias can be changed.	gen_text_input	
Tenant Tags	Select tags to be assigned for the fabric module.	ApicDeviceTagIdentity	
Monitoring Policy	Select a monitoring policy.	ApicDeviceTenantMonitoringPolicyIdentity	
Security Domains	Select security domains.	ApicDeviceTenantSecurityDomainIdentity	
VRF Name	Enter unique name for VRF within the tenant.	gen_text_input	

## Outputs

Output	Description	Type
DATACENTER	Name of the Datacenter on which the selected operation was performed	datacenterName
DEVICE_IP	IP address of the APIC device on which the selected operation was performed	gen_text_input
APIC_ACCOUNT	APIC Account on which the selected operation was performed	ApicDeviceIdentity
TENANT_NAME	Tenant Name on which the selected operation was performed	gen_text_input
TENANT_IDENTITY	APIC Tenant Identity	ApicDeviceTenantIdentity
DEVICE_TENANT_MONITORING_POLICY	Apic Monitoring Policy	gen_text_input

<b>Output</b>	<b>Description</b>	<b>Type</b>
DEVICE_TENANT_ MONITORING_POLICY_ IDENTITY	Apic Monitoring Policy Identity	ApicDeviceTenant MonitoringPolicyIdentity
DEVICE_TENANT_TAG_ IDENTITY	Apic Tag Identity	ApicDeviceTagIdentity
PRIVATE_NETWORK_ IDENTITY	Private Network Identity	ApicDeviceTenantPrivate NetworkIdentity

# Delete APIC Tenant

**Summary**

Delete an APIC tenant.

**Description**

This task deletes an APIC tenant on the APIC controller.

**Inputs**

Input	Description	Mappable To Type	Mandatory
Tenant Name	Select Tenant Name	ApicDeviceTenantIdentity	Y
Do you want to delete the selected Tenant?			Y

**Outputs**

Output	Description	Type
APIC_ACCOUNT	APIC Account on which the selected operation was performed	ApicDeviceIdentity
TENANT_NAME	Tenant Name on which the selected operation was performed	gen_text_input
TENANT_IDENTITY	APIC Tenant Identity	ApicDeviceTenantIdentity

# Delete GUID from Tenant

## Summary

Delete GUID from APIC Tenant.

## Description

This task deletes a GUID from a tenant.

## Inputs

Input	Description	Mappable To Type	Mandatory
GUID	Select a GUID to be deleted.	ApicTenantGUIDIdentity	Y

## Outputs

Output	Description	Type
APIC_ACCOUNT	APIC Account on which the selected operation was performed	ApicDeviceIdentity
TENANT_IDENTITY	APIC Tenant Identity	ApicDeviceTenantIdentity
OUTPUT_TENANT_GUID_IDENTITY	APIC Tenant's GUID Identity	ApicTenantGUIDIdentity