



Security Configuration Mode Commands

The Security configuration mode is a sub-mode of the Global Configuration mode. This sub-mode enables you to define or modify the connection with the Talos Intelligence content-filtering server and configure URL categorization parameters.

Command Modes

Exec > Global Configuration > Security Configuration

configure > security

Entering the above command sequence results in the following prompt:

```
[local]host_name(config-security) #
```



Important

The commands or keywords/variables that are available are dependent on platform type, product version, and installed license(s).

- [category, on page 1](#)
- [end, on page 2](#)
- [exit, on page 2](#)
- [server, on page 2](#)

category

Adds or removes a URL categorization server.



Important

This is a license-controlled feature. For more information, contact your Cisco account or support representative.

Product

All

Privilege

Security Administrator, Administrator

Command Modes

Exec > Global Configuration > Security Configuration

configure > security

Entering the above command sequence results in the following prompt:

end

```
[local]host_name(config-security)#
```

Syntax Description [no] **category server** *server_name*

no

Removes the specified URL categorization server.

server_name

Specifies the name of the URL categorization server. *server_name* must be an alpha and/or numeric string from 1 through 31 characters that is case sensitive.

Usage Guidelines Use this command to create or remove a URL categorization server from the Security configuration mode.

end

Exits the current configuration mode and returns to the Exec mode.

Product All

Privilege Security Administrator, Administrator

Syntax Description **end**

Usage Guidelines Use this command to return to the Exec mode.

exit

Exits the current mode and returns to the parent configuration mode.

Product All

Privilege Security Administrator, Administrator

Syntax Description **exit**

Usage Guidelines Use this command to return to the parent configuration mode.

server

This command creates or specifies a Talos Security Intelligence (TSI) server entry and enters the TSI Server Configuration mode.



Important

This is a license-controlled feature. For more information, contact your Cisco account or support representative.

| | |
|---------------------------|--|
| Product | All |
| Privilege | Security Administrator, Administrator |
| Command Modes | Exec > Global Configuration > Security Configuration configure > security Entering the above command sequence results in the following prompt: <code>[local]host_name(config-security)#</code> |
| Syntax Description | [no] server talos-intelligence <i>server_name</i> no Removes the specified Talos Security Intelligence server. <i>server_name</i> Specifies the name of the Talos Security Intelligence server to create, configure, or remove. <i>server_name</i> must be an alpha and/or numeric string from 1 through 31 characters that is case sensitive. |
| Usage Guidelines | Use this command to create, configure, or remove a Talos Security Intelligence server from the Security configuration mode. Entering this command results in the following prompt: <code>[local]host_name(config-server-tsi)#</code> The various parameters available for configuration of a TSI server entry are defined in the <i>TSI Server Configuration Mode Commands</i> chapter. |

