



Cisco UCS Director Red Hat Enterprise KVM Management Guide, Release 6.6

First Published: 2018-04-27

Americas Headquarters

Cisco Systems, Inc.
170 West Tasman Drive
San Jose, CA 95134-1706
USA
<http://www.cisco.com>
Tel: 408 526-4000
800 553-NETS (6387)
Fax: 408 527-0883

THE SPECIFICATIONS AND INFORMATION REGARDING THE PRODUCTS IN THIS MANUAL ARE SUBJECT TO CHANGE WITHOUT NOTICE. ALL STATEMENTS, INFORMATION, AND RECOMMENDATIONS IN THIS MANUAL ARE BELIEVED TO BE ACCURATE BUT ARE PRESENTED WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED. USERS MUST TAKE FULL RESPONSIBILITY FOR THEIR APPLICATION OF ANY PRODUCTS.

THE SOFTWARE LICENSE AND LIMITED WARRANTY FOR THE ACCOMPANYING PRODUCT ARE SET FORTH IN THE INFORMATION PACKET THAT SHIPPED WITH THE PRODUCT AND ARE INCORPORATED HEREIN BY THIS REFERENCE. IF YOU ARE UNABLE TO LOCATE THE SOFTWARE LICENSE OR LIMITED WARRANTY, CONTACT YOUR CISCO REPRESENTATIVE FOR A COPY.

The Cisco implementation of TCP header compression is an adaptation of a program developed by the University of California, Berkeley (UCB) as part of UCB's public domain version of the UNIX operating system. All rights reserved. Copyright © 1981, Regents of the University of California.

NOTWITHSTANDING ANY OTHER WARRANTY HEREIN, ALL DOCUMENT FILES AND SOFTWARE OF THESE SUPPLIERS ARE PROVIDED "AS IS" WITH ALL FAULTS. CISCO AND THE ABOVE-NAMED SUPPLIERS DISCLAIM ALL WARRANTIES, EXPRESSED OR IMPLIED, INCLUDING, WITHOUT LIMITATION, THOSE OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NON-INFRINGEMENT OR ARISING FROM A COURSE OF DEALING, USAGE, OR TRADE PRACTICE.

IN NO EVENT SHALL CISCO OR ITS SUPPLIERS BE LIABLE FOR ANY INDIRECT, SPECIAL, CONSEQUENTIAL, OR INCIDENTAL DAMAGES, INCLUDING, WITHOUT LIMITATION, LOST PROFITS OR LOSS OR DAMAGE TO DATA ARISING OUT OF THE USE OR INABILITY TO USE THIS MANUAL, EVEN IF CISCO OR ITS SUPPLIERS HAVE BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: <https://www.cisco.com/go/trademarks>. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1721R)

© 2018 Cisco Systems, Inc. All rights reserved.



CONTENTS

Preface

Preface v

Audience v

Conventions v

Related Documentation vii

Documentation Feedback vii

Obtaining Documentation and Submitting a Service Request vii

CHAPTER 1

New and Changed Information for This Release 1

New and Changed Information for This Release 1

CHAPTER 2

Overview 3

Cisco UCS Director 3

Features and Benefits 4

Physical and Virtual Management Features 6

About the Cisco UCS Director Red Hat Enterprise KVM Connector 7

Prerequisites 7

System Requirements 7

About Workflows 8

About the Workflow Tasks 8

Workflow Designer 8

Provisioning Support for Microsoft Windows 9

CHAPTER 3

Adding the KVM Connector 11

Creating a RHEV KVM Cloud 11

Initiating Inventory Collection for a VM 13

Computing Policies 13

Creating a RHEV KVM Computing Policy 13

Creating a RHEV KVM Storage Policy	15
Creating a RHEV KVM Networking Policy	16
Virtual Data Centers	17
Creating a RHEV KVM Virtual Pod	17
Creating a KVM Deployment Policy	19
About Managing Catalogs	20
Publishing a Catalog	21
Service Requests	28
Creating a Service Request for a Standard Catalog	28

CHAPTER 4**Managing the KVM Connector 33**

Viewing Summary Information	33
Using VM and Host Level Monitoring	34
Viewing Polling Information	34
Viewing vDCs	35
Viewing Data Centers	35
Viewing Clusters	36
Viewing Hosts	37
Viewing VMs	37
Viewing RHEV KVM Events	38
Viewing VM Action Requests	39
Launching the SPICE Console for a VM	39
Viewing VM Pools	40
Viewing Events	41
Viewing Roles	41
Viewing Images	42
Viewing Tags	43
Viewing Users	43
Viewing Deleted VMs	44
Reports	45
Accessing Reports	45
Accessing Trend Reports (Summary Level)	45
Accessing Trend Reports (VM Level)	46
Managing VM Power Settings	47



Preface

- [Audience, page v](#)
- [Conventions, page v](#)
- [Related Documentation, page vii](#)
- [Documentation Feedback, page vii](#)
- [Obtaining Documentation and Submitting a Service Request, page vii](#)

Audience

This guide is intended primarily for data center administrators who use Cisco UCS Director and who have responsibilities and expertise in one or more of the following:

- Server administration
- Storage administration
- Network administration
- Network security
- Virtualization and virtual machines

Conventions

Text Type	Indication
GUI elements	GUI elements such as tab titles, area names, and field labels appear in this font . Main titles such as window, dialog box, and wizard titles appear in this font .
Document titles	Document titles appear in <i>this font</i> .
TUI elements	In a Text-based User Interface, text the system displays appears in <i>this font</i> .

Text Type	Indication
System output	Terminal sessions and information that the system displays appear in <i>this font</i> .
CLI commands	CLI command keywords appear in this font . Variables in a CLI command appear in <i>this font</i> .
[]	Elements in square brackets are optional.
{x y z}	Required alternative keywords are grouped in braces and separated by vertical bars.
[x y z]	Optional alternative keywords are grouped in brackets and separated by vertical bars.
string	A nonquoted set of characters. Do not use quotation marks around the string or the string will include the quotation marks.
<>	Nonprinting characters such as passwords are in angle brackets.
[]	Default responses to system prompts are in square brackets.
!, #	An exclamation point (!) or a pound sign (#) at the beginning of a line of code indicates a comment line.

**Note**

Means *reader take note*. Notes contain helpful suggestions or references to material not covered in the document.

**Caution**

Means *reader be careful*. In this situation, you might perform an action that could result in equipment damage or loss of data.

**Tip**

Means *the following information will help you solve a problem*. The tips information might not be troubleshooting or even an action, but could be useful information, similar to a Timesaver.

**Timesaver**

Means *the described action saves time*. You can save time by performing the action described in the paragraph.

**Warning****IMPORTANT SAFETY INSTRUCTIONS**

This warning symbol means danger. You are in a situation that could cause bodily injury. Before you work on any equipment, be aware of the hazards involved with electrical circuitry and be familiar with standard practices for preventing accidents. Use the statement number provided at the end of each warning to locate its translation in the translated safety warnings that accompanied this device.

SAVE THESE INSTRUCTIONS

Related Documentation

Cisco UCS Director Documentation Roadmap

For a complete list of Cisco UCS Director documentation, see the *Cisco UCS Director Documentation Roadmap* available at the following URL: http://www.cisco.com/en/US/docs/unified_computing/ucs/ucs-director/doc-roadmap/b_UCSDirectorDocRoadmap.html.

Cisco UCS Documentation Roadmaps

For a complete list of all B-Series documentation, see the *Cisco UCS B-Series Servers Documentation Roadmap* available at the following URL: <http://www.cisco.com/go/unifiedcomputing/b-series-doc>.

For a complete list of all C-Series documentation, see the *Cisco UCS C-Series Servers Documentation Roadmap* available at the following URL: <http://www.cisco.com/go/unifiedcomputing/c-series-doc>.

**Note**

The *Cisco UCS B-Series Servers Documentation Roadmap* includes links to documentation for Cisco UCS Manager and Cisco UCS Central. The *Cisco UCS C-Series Servers Documentation Roadmap* includes links to documentation for Cisco Integrated Management Controller.

Documentation Feedback

To provide technical feedback on this document, or to report an error or omission, please send your comments to ucs-director-docfeedback@cisco.com. We appreciate your feedback.

Obtaining Documentation and Submitting a Service Request

For information on obtaining documentation, using the Cisco Bug Search Tool (BST), submitting a service request, and gathering additional information, see [What's New in Cisco Product Documentation](#).

To receive new and revised Cisco technical content directly to your desktop, you can subscribe to the [What's New in Cisco Product Documentation RSS feed](#). RSS feeds are a free service.



CHAPTER

1

New and Changed Information for This Release

- [New and Changed Information for This Release, page 1](#)

New and Changed Information for This Release

The following table provides an overview of the significant changes to this guide for this current release.

Feature	Description	Where Documented
Support for launching consoles for VMs in a KVM Account	This release of Cisco UCS Director introduces support for launching a console for VMs within Red Hat KVM Virtual accounts.	Launching the SPICE Console for a VM, on page 39



Overview

This chapter contains the following sections:

- [Cisco UCS Director, page 3](#)
- [About the Cisco UCS Director Red Hat Enterprise KVM Connector , page 7](#)
- [Prerequisites, page 7](#)
- [System Requirements, page 7](#)
- [About Workflows, page 8](#)
- [Workflow Designer, page 8](#)
- [Provisioning Support for Microsoft Windows, page 9](#)

Cisco UCS Director

Cisco UCS Director is a complete, highly secure, end-to-end management, orchestration, and automation solution for a wide array of Cisco and non-Cisco data infrastructure components, and for the industry's leading converged infrastructure solutions based on the Cisco UCS and Cisco Nexus platforms. For a complete list of supported infrastructure components and solutions, see the [Cisco UCS Director Compatibility Matrix](#).

Cisco UCS Director is a 64-bit appliance that uses the following standard templates:

- Open Virtualization Format (OVF) for VMware vSphere
- Virtual Hard Disk (VHD) for Microsoft Hyper-V

Management through Cisco UCS Director

Cisco UCS Director extends the unification of computing and networking layers through Cisco UCS to provide you with comprehensive visibility and management of your data center infrastructure components. You can use Cisco UCS Director to configure, administer, and monitor supported Cisco and non-Cisco components. The tasks you can perform include the following:

- Create, clone, and deploy service profiles and templates for all Cisco UCS servers and compute applications.

- Monitor organizational usage, trends, and capacity across a converged infrastructure on a continuous basis. For example, you can view heat maps that show virtual machine (VM) utilization across all your data centers.
- Deploy and add capacity to converged infrastructures in a consistent, repeatable manner.
- Manage, monitor, and report on data center components, such as Cisco UCS domains or Cisco Nexus network devices.
- Extend virtual service catalogs to include services for your physical infrastructure.
- Manage secure multi-tenant environments to accommodate virtualized workloads that run with non-virtualized workloads.

Automation and Orchestration with Cisco UCS Director

Cisco UCS Director enables you to build workflows that provide automation services, and to publish the workflows and extend their services to your users on demand. You can collaborate with other experts in your company to quickly and easily create policies. You can build Cisco UCS Director workflows to automate simple or complex provisioning and configuration processes.

Once built and validated, these workflows perform the same way every time, no matter who runs the workflows. An experienced data center administrator can run them, or you can implement role-based access control to enable your users and customers to run the workflows on a self-service basis, as needed.

With Cisco UCS Director, you can automate a wide array of tasks and use cases across a wide variety of supported Cisco and non-Cisco hardware and software data center components. A few examples of the use cases that you can automate include, but are not limited to:

- VM provisioning and lifecycle management
- Network resource configuration and lifecycle management
- Storage resource configuration and lifecycle management
- Tenant onboarding and infrastructure configuration
- Application infrastructure provisioning
- Self-service catalogs and VM provisioning
- Bare metal server provisioning, including installation of an operating system

Features and Benefits

The features and benefits of Cisco UCS Director are as follows:

Feature	Benefit
Central management	<ul style="list-style-type: none"> • Provides a single interface for administrators to provision, monitor, and manage the system across physical, virtual, and bare metal environments • Provides unified dashboards, reports, and heat maps, which reduce troubleshooting and performance bottlenecks

Feature	Benefit
Self-service catalog	<ul style="list-style-type: none"> • Allows end users to order and deploy new infrastructure instances conforming to IT-prescribed policies and governance
Adaptive provisioning	<ul style="list-style-type: none"> • Provides a real-time available capability, internal policies, and application workload requirements to optimize the availability of your resources
Dynamic capacity management	<ul style="list-style-type: none"> • Provides continuous monitoring of infrastructure resources to improve capacity planning, utilization, and management • Identifies underutilized and overutilized resources
Multiple hypervisor support	<ul style="list-style-type: none"> • Supports VMware ESX, ESXi, Microsoft Hyper-V, and Red Hat hypervisors
Computing management	<ul style="list-style-type: none"> • Provisions, monitors, and manages physical, virtual, and bare metal servers, as well as blades • Allows end users to implement virtual machine life-cycle management and business continuance through snapshots • Allows administrators to access server utilization trend analysis
Network management	<ul style="list-style-type: none"> • Provides policy-based provisioning of physical and virtual switches and dynamic network topologies • Allows administrators to configure VLANs, virtual network interface cards (vNICs), port groups and port profiles, IP and Dynamic Host Control Protocol (DHCP) allocation, and access control lists (ACLs) across network devices
Storage management	<ul style="list-style-type: none"> • Provides policy-based provisioning and management of filers, virtual filers (vFilers), logical unit numbers (LUNs), and volumes • Provides unified dashboards that allow administrators comprehensive visibility into organizational usage, trends, and capacity analysis details.

Physical and Virtual Management Features

<p>Physical Server Management</p> <ul style="list-style-type: none"> • Discover and collect configurations and changes • Monitor and manage physical servers • Perform policy-based server provisioning • Manage blade power • Manage server life cycle • Perform server use trending and capacity analysis • Perform bare metal provisioning using preboot execution environment (PXE) boot management 	<p>Virtual Computing Management</p> <ul style="list-style-type: none"> • Discover, collect, and monitor virtual computing environments • Perform policy-based provisioning and dynamic resource allocation • Manage the host server load and power • Manage VM life cycle and snapshots • Perform analysis to assess VM capacity, sprawl, and host utilization
<p>Physical Storage Management</p> <ul style="list-style-type: none"> • Discover, collect, and monitor storage filers • Perform policy-based provisioning of vFilers • Provision and map volumes • Create and map Logical Unit Number (LUN) and iGroup instances • Perform SAN zone management • Monitor and manage network-attached storage (NAS) and SAN-based storage • Implement storage best practices and recommendation 	<p>Virtual Storage Management</p> <ul style="list-style-type: none"> • Discover, collect, and monitor storage of vFilers and storage pools • Perform policy-based storage provisioning for thick and thin clients • Create new datastores and map them to virtual device contexts (VDCs) • Add and resize disks to VMs • Monitor and manage organizational storage use • Perform virtual storage trend and capacity analysis
<p>Physical Network Management</p> <ul style="list-style-type: none"> • Discover, collect, and monitor physical network elements • Provision VLANs across multiple switches • Configure Access Control Lists (ACLs) on network devices • Configure storage network s • Implement dynamic network topologies 	<p>Virtual Network Management</p> <ul style="list-style-type: none"> • Add networks to VMs • Perform policy-based provisioning with IP and DHCP allocation • Configure and connect Virtual Network Interface Cards (vNICs) to VLANs and private VLANs • Create port groups and port profiles for VMs • Monitor organizational use of virtual networks

About the Cisco UCS Director Red Hat Enterprise KVM Connector

The Cisco UCS Director Red Hat Enterprise (RHEV) VM Kernel-based Virtual Machine (KVM) Connector is a full virtualization solution for Linux on AMD64 and Intel 64 hardware. KVM is a Linux kernel module created for the standard Red Hat Enterprise Linux 6 kernel.

The Red Hat Enterprise Virtualization Manager can be managed by Cisco UCS Director through the Representational State Transfer (REST) API.

The Cisco UCS Director KVM Connector provides for basic inventory, VM/host level monitoring, VM basic power actions, and snapshot actions. The following provisioning services are also supported:

- **Compute Policy**—Memory and CPU resize options.
- **Storage Policy**—Local, NFS, and iSCSI storage types are supported.
- **Network Policy**—Multiple NICs are supported.

Prerequisites

**Note**

Cisco UCS Director recognizes Red Hat Enterprise Virtual Machine (VM), Red Hat Enterprise Virtual Hypervisor Hosts, and Red Hat Enterprise Linux Hosts for additional functionality.

- Installation of Red Hat Enterprise Virtualization Manager version 3.2 and 3.3
- Installation of Red Hat Enterprise Virtual Hypervisor Hosts/RHEL Hosts (version 6.5)
- Configured system administrator privileges
- Cisco UCS Director release 5.0 or later release

System Requirements

The minimum system requirements depend upon how many VMs you plan to manage.

**Note**

For optimal performance, reserve additional CPU and memory resources.

For information about minimum system requirements for a multi-node setup, see the [Cisco UCS Director Multi-Node Installation and Configuration Guide](#).

Up to 2000 VMs

If you plan to manage up to 2000 VMs, the Cisco UCS Director environment must meet at least the minimum system requirements in the following table.

Table 1: Minimum System Requirements for up to 2000 VMs

Element	Minimum Supported Requirement
vCPU	4
Memory	8 GB
Hard Disk	100 GB

About Workflows

Cisco UCS Director Orchestrator allows you to organize workflows so that you can automate simple or complex actions on your infrastructure (either physical or virtual). By using Orchestrator you can organize tasks into distinct workflows to accomplish specific IT services, such as adding VMs. You can then add multiple tasks to a workflow is accomplished using the workflow UI designer. Triggers help initiate actions inside a workflow. You can execute the workflow directory or have a trigger begin the process. A typical workflow consists of the following elements:

- Workflow Designer (GUI interface)
- Predefined Tasks

The simplest workflow consists of two connected tasks. A task represents a particular action or operation. The workflow determines the order in which your tasks are executed by Orchestrator. When constructing workflows, by dragging-and-dropping tasks, it is possible to route the output of one workflow into the input of another workflow. This connecting of multiple tasks is how you create more complex workflows.

About the Workflow Tasks

Cisco UCS Director includes several workflows tasks to aid in the construction of RHEV KVM-specific workflows using Workflow Designer. The following available workflow tasks are:

- RHEV KVEM VM Tasks
 - RHEV KVM Resource Allocation
 - RHEV KVM VM Provision

Workflow Designer

You use the workflow designer to implement actions or to select tasks from a list and then drag and drop them onto your **Workflow Designer** pane.

Provisioning Support for Microsoft Windows

Cisco UCS Director in conjunction with the Cisco UCS Director Baremetal Agent supports all types of Linux and Microsoft Windows operating systems in baremetal provisioning workflows. Certain operating systems are packaged out-of-the-box with the Cisco UCS Director Baremetal Agent. However, additional operating systems can be added as necessary. Any operating system that supports PXE boot and/or install is supported and can be leveraged in baremetal provisioning workflows.

RHEV KVM supports Microsoft Windows 2008/2012 provisioning.



Adding the KVM Connector

This chapter contains the following sections:

- [Creating a RHEV KVM Cloud, page 11](#)
- [Initiating Inventory Collection for a VM, page 13](#)
- [Computing Policies, page 13](#)
- [Creating a RHEV KVM Storage Policy, page 15](#)
- [Creating a RHEV KVM Networking Policy, page 16](#)
- [Virtual Data Centers, page 17](#)
- [About Managing Catalogs, page 20](#)
- [Publishing a Catalog, page 21](#)
- [Service Requests, page 28](#)

Creating a RHEV KVM Cloud

Before You Begin

Installation of Red Hat Enterprise Virtual Machine (VM) and Hypervisor.

Procedure

- Step 1** Choose **Administration > Virtual Accounts**.
- Step 2** On the **Virtual Accounts** page, click **Virtual Accounts**.
- Step 3** Click **Add (+)**.
- Step 4** On the **Add Cloud** screen, choose **Red Hat KVM** from the **Cloud Type** drop-down list.
Note The following fields are displayed when RHEV KVM is chosen. Other cloud types display fields that are specific to that cloud type.
- Step 5** On the **Add Account** screen, complete the following fields:

Name	Description
Pod drop-down list	Choose a Pod to associate the account to from the drop-down list.
Account Name field	A unique account name.
Description field	A description of the new account.
Server Address field	The RHEV KVM server address.
Use Credentials Policy check box	Check this box if you want to use a credential policy for this account rather than enter the username and password information manually.
Credential Policy drop-down list	This field appears only when the Use Credential Policy box is checked. Choose a policy from the Credential Policy drop-down list.
Server User ID field	This field appears only when the Use Credential Policy box is unchecked. The RHEV KVM server username. Note You must enter only the username in this field. Do not include the domain name with the user name. Enter the domain name in the Domain field.
Server Password field	This field appears only when the Use Credential Policy box is unchecked. The RHEV KVM server password.
Domain field	The domain associated to the new account.
Server Access Port field	The server access port used by the account (default value is 443).
Service Provider field	The service provider associated with the account
Contact field	The contact email address for the cloud.
Location field	The location of the account.

Step 6 Click **Submit**.

Initiating Inventory Collection for a VM

Procedure

- Step 1** Choose **Virtual > Compute**.
- Step 2** On the **Compute** page, choose the cloud.
- Step 3** On the **Compute** page, click **VMs**.
- Step 4** Click the row with the VM for which you want to request an inventory collection.
- Step 5** From the **More Actions** drop-down list, choose **Inventory Collection Request for VM**.
- Step 6** Click **Submit**.

Computing Policies

Computing policies determine the compute resources that can be used during provisioning to satisfy group or workload requirements.

As an administrator, you can define advanced policies by mixing and matching various conditions in the computing policy.



Note We recommend that you thoroughly understand all the fields in the computing policy. Some combinations of conditions can result in no host machines being available during self-service provisioning.

Creating a RHEV KVM Computing Policy

Procedure

- Step 1** Choose **Policies > Virtual/Hypervisor Policies > Computing**.
- Step 2** On the **Computing** page, click **RHEV KVM Computing Policy**.
- Step 3** Click **RHEV KVM Computing Policy**.
- Step 4** Click **Add (+)**.
- Step 5** On the **Add Policy** screen, complete the following fields:

Name	Description
Policy Name field	The name of the policy. Note This name is used during catalog definition
Policy Description field	The description of the policy.

Name	Description
Cloud Name drop-down list	Choose the cloud where resource allocation occurs.
Datacenter drop-down list	Choose a datacenter (Pod).
Cluster Scope drop-down list	<p>Choose a type of cluster scope.</p> <p>Note You can narrow the scope of deployment by specifying whether to use all, include selected cluster, or exclude selected clusters. Depending on the choices, a Selected Clusters field appears where the required clusters can be chosen.</p>
Filter Conditions field	Check the check boxes for one or more conditions and set the condition that should match. Any hosts that do not meet these criteria are excluded from consideration. If more than one condition is chosen, all of the chosen conditions must match.
<i>Deployment Options</i>	
Override Template check box	Check the check box to override the template properties. On selection, you will get additional fields to enter custom settings for CPU and memory.
<i>Resizing Options</i>	
Allow Resizing of VM check box	Check the check box to allow VM resizing before provisioning or to resize an existing VM.
Permitted Values of No. of CPU Sockets field	<p>The range of CPUs to use while provisioning a VM or resizing an existing VM. A range of more than 8 is visible during VM provisioning or resizing only if the chosen cloud is 5 or above and has VM version 8. Only the values specified in the box are visible.</p> <p>Note This option appears if you choose Allow Resizing of VM.</p>
Permitted Values of No. of Cores per Sockets field	<p>The range of cores permitted per socket.</p> <p>Note This option appears if you choose Allow Resizing of VM.</p>
Permitted Values for Memory in MB field	<p>The range of memory to use while provisioning a VM or resizing an existing VM. For example: 512, 768, 1024, 1536, 2048, 3072, 4096, and so on. Only the values specified in the box are visible.</p> <p>Note This option appears if you choose Allow Resizing of VM.</p>

Step 6 Click **Add**.

Creating a RHEV KVM Storage Policy

Procedure

Step 1 Choose **Policies > Virtual/Hypervisor Policies > Storage**.

Step 2 On the **Storage** page, click **RHEV KVM Storage Policy**.

Step 3 Click **Add (+)**.

Step 4 On the **Add Policy** screen, complete the following fields:

Name	Description
Policy Name field	The name of the storage policy
Policy Description field	The description of the storage policy.
Cloud Name drop-down list	Choose the cloud in which resource allocation occurs.
Datacenter drop-down list	Choose a data center.
Scope	
Data Stores Scope drop-down list	Choose All , Include Selected Datastores , or Exclude Selected Datastores as the scope of deployment.
Selected Data Stores field	This field appears when you chose Include Selected Datastores or Exclude Selected Datastores from the Data Stores Scope drop-down list. Expand Selected Data Stores and select the appropriate datastores.
Storage Options	
Filter Conditions drop-down list	Check the check boxes for one or more conditions and set the condition that should match the data store storage.

Step 5 Click **Submit**.

Creating a RHEV KVM Networking Policy

Procedure

- Step 1** Choose **Policies > Virtual/Hypervisor Policies > Network**.
- Step 2** On the **Network** page, click **RHEV KVM Networking Policy**.
- Step 3** Click **Add (+)**.
- Step 4** On the **Add Policy** screen, complete the following fields:

Name	Description
Policy Name field	The name of the network policy.
Policy Description field	The description of the network policy.
Cloud Name drop-down list	Choose the cloud account to which the policy applies.
Datacenter drop-down list	Choose a data center.
Network Name field	Expand Network Name , check the network that you want to use, and then click Validate .
Link State drop-down list	Choose On or OFF as the NIC link state.
Adapter Type drop-down list	Choose the adapter type. Check this option if you want to have the same Adapter Type that is available in the template. Note This option is not visible if the Copy Adapter from Template option is chosen.

- Step 5** Click **Next**.
- Step 6** Expand **Additional Networks** and click **Add (+)**.
- Step 7** On the **Add Entry to Additional Networks** screen, complete the following fields:

Name	Description
NIC Alias field	The name of the network policy.
Network Name field	Expand Network Name , check the network that you want to use, and then click Validate .
Link State drop-down list	Choose On or OFF as the NIC link state.

Name	Description
Adapter Type drop-down list	<p>Choose the adapter type. Check this option if you want to have the same Adapter Type that is available in the template.</p> <p>Note This option is not visible if the Copy Adapter from Template option is chosen.</p>

Step 8 Click **Submit** to add the network.

Step 9 Click **Submit** to add the policy.

Virtual Data Centers

A Virtual Data Center (VDC) is a logical grouping that combines virtual resources, operational details, rules, and policies to manage specific group requirements.

A group or organization can manage multiple VDCs, images, templates, and policies. Organizations can allocate quotas and assign resource limits for individual groups at the VDC level.

You can also define approvers specific to a VDC. The approvers assigned to a particular VDC must approve all service requests from users for VM provisioning.



Note

There is a default VDC in Cisco UCS Director, and all discovered VMs are part of this default VDC. Discovered VMs are VMs that are created outside of Cisco UCS Director or were already created on VMware vCenter before Cisco UCS Director was installed. Cisco UCS Director automatically discovers such VMs and adds them to the default VDC.

A VM that is provisioned using a service request can be associated with a specific VDC. When you create a service request, you can choose the VDC on which this VM is provisioned. You can view a list of the VDCs that are available for a particular group and choose the required VDC when provisioning VMs.

Creating a RHEV KVM Virtual Pod

In this task, you specify deployment, storage, network, and computing policies. Refer to the Cisco UCS Director System Administration Guide for additional information.

Procedure

- Step 1** Choose **Policies > Virtual/Hypervisor Policies > Virtual Data Centers**.
- Step 2** On the **Virtual Data Centers** page, click **vDC**.
- Step 3** Click **Add**.
- Step 4** On the **Add vDC** screen, choose **Red Hat KVM** from the **Account Type** drop-down list.
- Step 5** Click **Submit**.
- Step 6** On the **Add vDC** screen, complete the following fields:

Name	Description
vDC Name field	The name of the VDC. After entering the name, it cannot be edited.
vDC Locked check box	Check the check box to deny the use of the VDC for any further deployments. Actions on existing VMs, within this VDC, are disabled. Uncheck the check box to allow the use of the VDC for further deployments.
vDC Description field	The VDC-specific description.
Group field	Expand Group and check the group for which the VDC is being set up. Click the + icon to add a group.
Cloud Name drop-down list	Choose the cloud on which the VDC is being set up.
<i>Approvers and Contacts</i>	
First Level Approver(s) field	Expand First Level Approvers and check each user who must approve the service request at first level.
Second Level Approver(s) field	Expand Second Level Approver(s) and check each user who must approve the service request at second level.
Approval required from all the users check box	If checked, requires approval from all users.
Number of Approval Request Reminders drop-down list	Choose the number of reminders that has to be sent at the specified interval. Set the reminder to zero to send the reminder email at the specified interval till the request is approved or rejected.
Reminder Intervals (Hours) drop-down list	The time interval to send the next request approval reminder email.
Provider Support Email Address field	The contact or user's email address. The person who is notified about VM provisioning using this VDC.

Name	Description
Copy Notifications to Email Address field	The second contact's email for copying notifications about this VDC.
<i>Policies</i>	
Computing Policy drop-down list	Choose the computing policy applicable to the VDC.
Network Policy drop-down list	Choose the network policy applicable to the VDC.
Storage Policy drop-down list	Choose the storage policy applicable to the VDC.
System Policy drop-down list	Choose the system policy applicable to the VDC.
VM Management Policy drop-down list	Choose the VM management policy applicable to the VDC.
End User Self-Service Policies drop-down list	Choose an end user policy.

Creating a KVM Deployment Policy

Procedure

- Step 1** Choose **Policies > Virtual/Hypervisor Policies > Service Delivery**.
- Step 2** On the **Service Delivery** page, click **RHEV KVM Deployment Policy**.
- Step 3** Click **Add**.
- Step 4** On the **Add Policy** screen, complete the following fields:

Name	Description
Policy Name field	The name for the KVM deployment policy.
Policy Description field	The description of the KVM deployment policy
VM Name Template field	The VM name template to use. Cisco UCS Director allows automatically created using a set of variable names. Each variable must be enclosed in <code>\${VARIABLE_NAME}</code> . For example: <code>vm-\${GROUP_NAME}-SR\${SR_ID}</code> .
Cloud Name drop-down list	Choose a cloud from the drop-down list.

Name	Description
Recycle VM Name check box	By default, decommissioned VM names that were previously provisioned are used when creating a new VM. Uncheck this check box if you do not want to recycle previously used VM names.

Step 5 Click **Submit**.

About Managing Catalogs

You can self-provision virtual machines (VMs) and bare metal (BM) servers using predefined catalog items. Only a system administrator can create a catalog. A catalog defines parameters, such as the cloud name and the group name to which the VM is bound.

The following folders are available by default. You cannot edit or delete them.

- Standard
- Advanced
- Service Container
- Bare Metal

To aid in managing catalogs, Cisco UCS Director allows you to group similar catalogs within a folder. While creating a catalog, you can choose to add it in a previously created folder, or create a new folder. A folder is visible in the system only when it contains a catalog.

The **Manage Folder** option on the **Catalog** page allows you to perform the following tasks:

- Edit a folder—Modify the name of a user-created folder or the folder icon for all folders. You cannot modify the name of a default folder.
- Delete a folder—Delete a folder from Cisco UCS Director. If this folder contains catalogs, then these catalogs are automatically moved into the folders that are available by default, based on the catalog type. Default folders cannot be deleted.
- Re-order the list of folder—Change the order in which the folders are listed in the **Catalog** page. By default, folders are listed alphabetically.



Important

If you have upgraded Cisco UCS Director to the latest version, then all catalogs created in prior versions are grouped into folders available by default, based on their catalog types.

By default, catalogs are displayed in a tile view format. You can choose to have the catalogs displayed in a table view format as well. Use the options on the far right of the screen to switch between the table view and the tile view format. In the table view format, you can use the options to expand or collapse all folders.

Publishing a Catalog

Procedure

- Step 1** Choose **Policies > Catalogs**.
- Step 2** On the **Catalogs** page, click **Add**.
- Step 3** On the **Add Catalog** screen, choose the **Catalog Type** that you want to add. It can be one of the following:

- **Standard**—Used to create catalogs for VM provisioning, using images from a list of clouds.
- **Advanced**—Used to publish orchestration workflows, such as catalog items.
- **Service Container**—Used to publish application containers as catalog items.
- **Bare Metal**—Used to create catalogs for bare metal server provisioning.

- Step 4** Click **Submit**.

- Step 5** On the **Add Catalog: Basic Information** screen, complete the required fields, including the following:

Name	Description
Catalog Name field	Enter a name for the catalog. Note After created, a catalog name cannot be modified.
Catalog Description field	Enter a description of the catalog.
Catalog Type drop-down list	Displays the type of catalog you previously chose. To change the catalog type, you need to cancel and restart this procedure.
Catalog Icon drop-down list	Choose from a list of icons to associate this catalog with an image. This icon is seen when you are creating a service request using this catalog.
Applied to all groups check box	Check the box to enable all groups to use this catalog. Leave it unchecked to deny its use to other groups.
Support Contact Email Address field	Enter the email address of the support contact who is notified when a service request is created using this catalog item.
Selected Groups list	Click Select to check the checkboxes of specific user groups. The checked groups use this catalog to provision new VMs. After checking the checkboxes of user groups, click Select to return to the Add Catalog screen.

Name	Description
Publish to end users check box	By default, this box is checked. Uncheck this box if you do not want this catalog to be visible to users. If you do not uncheck this box, then this catalog is visible to the users of the system.
Cloud Name drop-down list	Choose the cloud with the image for VM provisioning.
Provision new VM for ISO mounting check box	Check this box to clone a new VM from a selected image. If you do not check this check box, a blank VM is created.
Image list	<p>Click Select to check the checkboxes of the type of image (any existing templates such as Windows, Linux, and other files that make up the image) to use when VMs are provisioned using this catalog. After checking the checkboxes of the required images, click Select to return to the Add Catalog screen.</p> <p>If you are a group administrator, or a user in a group with permissions to create catalogs, this field displays images that are assigned to the group to which you belong.</p> <p>If you are an MSP administrator, then this field displays images that are assigned to your MSP organization, and to the groups within the MSP organization.</p>
Provision new VM using Content Library VM Template check box	Check this box to ensure that the new VM is provisioned using the Content Library VM Template. If you choose this option, the Image list is hidden.
Content Library VM Template list	Choose the content library VM template.
Windows License Pool field	<p>Enter the Windows License.</p> <p>Note This field appears only when a Windows image is chosen. This option is not supported in the RHEV KVM Connector.</p>

Name	Description
Use ReadyClone check box	<p>Check the box to ensure that VMs are deployed using ReadyClones.</p> <p>When this box is checked, the Use Linked Clone and Provision all disks in single datastore check boxes are not available for editing.</p> <p>Note This checkbox is not visible if:</p> <ol style="list-style-type: none"> 1. The selected image is not on the HX datastore. 2. The VM has multiple disks.
Use Linked Clone check box	<p>Check the box if you want to use a linked clone.</p> <p>Linked Clone or Full Clone depends on the Linked Clone selection in the Storage Policy.</p> <p>Note This field appears only when a Snapshot image is chosen.</p>
Provision all disks in single datastore check box	<p>Check the box to provision all disks in a single datastore. You can also choose to use the datastores configured for each disk in the storage policy.</p> <p>Note This field appears only if the chosen template has multiple disks. This option is not supported in the RHEV KVM Connector.</p>
Service Container Template Name drop-down list	<p>Choose the template from the list.</p> <p>Note This field appears only when the chosen Catalog Type is Service Container.</p>
Select Folder drop-down list	<p>Choose the folder within which this catalog must be created.</p> <p>Note The drop-down list includes names of folders that are available by default. You can either choose a folder that is available, or click Create New Folder.</p> <p>On the Add New Folder screen, enter a Folder Name, choose a Folder Icon, and click Add.</p>
Bare Metal Server Provisioning Policy drop-down list	<p>Note This field appears only when the chosen Catalog Type is Bare Metal.</p>
Configure Service Request Support Email check box	<p>Check this box to enable the user to set the support email for sending service request status.</p>

Step 6 Click Next.

Step 7 On the **Add Catalog: Application Details** screen, complete the required fields, including the following:

Name	Description
Category list	Expand the list to choose a VDC category and click Select .
Override check box	Check the box to enable the user to override the selected category while provisioning a VM using a service request.
Support Contact Email Address field	Enter the email address of the contact who is notified when a service request is created using this catalog item.
Specify OS drop-down list	Choose the type of OS installed on the VM when it is provisioned. Note This option is not supported in the RHEV KVM Connector.
Specify Other OS field	Enter an OS that is not available in the Specify OS drop-down list. Note This option is not supported in the RHEV KVM Connector.
Specify Applications check boxes	Check the appropriate boxes to specify applications that are installed on the VM during provisioning. Note This option is not supported in the RHEV KVM Connector.
Specify Other Applications field	Enter other applications that are not available from the Specify Applications check boxes. Note This option is not supported in the RHEV KVM Connector.
Application Code field	Enter an application code that is used in the VM name. The application code can be between 1 to 4 characters (for example: W2K3, DB, WS). The application code can be used in a system policy for the VM name by using the variable <code>\${APPCODE}</code> . For example, if the VM Name Template is <code>vm-\${GROUP_NAME}-\${APPCODE}</code> , the VM provisioned with the system policy has the name <code>vm-groupname-W2K3</code> . Note This option is not supported in the RHEV KVM Connector.

Step 8 Click **Next**.

Step 9 On the **Add Catalog: User credentials** screen, complete the required fields, including the following:

Note These options are not supported in the RHEV KVM Connector.

Name	Description
Credential Options drop-down list	Choose to allow or disallow users to retrieve VM access credentials (shared). The following options are available: <ul style="list-style-type: none"> • Do not share • Share after password reset • Share template credentials The Do not share option is chosen if the administrator wants to send the credentials privately to another user outside Cisco UCS Director.
User ID field	Enter the user ID. Note This field is available only if a choice is made to share under Credential Options .
Password field	Enter the password. Note This field is available only if a choice is made to share under Credential Options .

Step 10 Click Next.

Step 11 On the **Add Catalog: Customization** screen, complete the required fields, including the following:

Name	Description
Automatic Guest Customization Enable check box	Check the box to enable automatic guest customization. If you do not check this check box, then Cisco UCS Director does not configure the DNS, Network, and Guest OS properties.
Pre Provisioning Custom Actions Enable	Check the Enable check box to enable execution of an orchestration workflow before VM provisioning.
Workflow field	Click Select to check the compound workflow that should be used in the orchestration workflow before VM provisioning. Check the check boxes of the required workflows, and click Select to return to the Add Catalog screen. Note This field appears when Pre Provisioning Custom Actions Enable is checked.
Post Provisioning Custom Actions Enable check box	Check the box to enable execution of an orchestration workflow after VM provisioning.

Name	Description
Workflow drop-down list	Click Select to check the check boxes of the workflows that need to be used in the orchestration workflow after VM provisioning. Check the check boxes of the required workflows, and click Select to return to the Add Catalog screen. Note This field appears when Post Provisioning Custom Actions Enable is checked.
Virtual Storage Catalog Enable check box	Check the box to choose storage entries from the Virtual Storage catalog.
Virtual Storage Catalog drop-down list	Chose a storage entry from the catalog. Note This field appears when Virtual Storage Catalog Enable is checked.
Cost Computation	
Charge Duration drop-down list	Choose Hourly or Monthly .
Active VM Application Cost USD field	Enter the cost for the application that is included in the template. Note This option is not supported in the RHEV KVM Connector.
Inactive VM Application Cost USD field	Enter the cost to this catalog of a VM in inactive state, per hour or month. Note This option is not supported in the RHEV KVM Connector.
VM Life Cycle Configuration	
Lease Time check box	Check the box to define a lease time (in days and hours).
Days field	Enter the number of days. Note This field appears when Lease Time is checked.
Hours field	Enter the number of hours. Note This field appears when Lease Time is checked.
Hide end user lease configuration check box	Check the box to prevent service users from configuring a lease time for VMs.
Hide end user VM provision later check box	Check the box to prevent service users from provisioning VMs at a later time.

Step 12 Click Next.

Step 13 On the **Add Catalog: VM Access** screen, complete the required fields, including the following:

Name	Description
Web Access Configuration Enable check box	Check the box to enable web access to the VM. By default, this check box is unchecked which means that web access to the VM is disabled.
URL field	Enter the URL of the VM. Note This field appears when Web Access Configuration Enable is checked.
Label field	Enter the label that is defined for this URL. Note This field appears when Web Access Configuration Enable is checked.
Remote Desktop Access Configuration Enable check box	Check the box to enable remote desktop access to the VM. By default, this check box is unchecked, which means that remote desktop access to the VM is disabled.
Server field	Enter the IP address of the server for remote access. Note This field appears when Remote Desktop Access Configuration Enable is checked.
Port field	Enter the port number on the server for remote access. Note This field appears when Remote Desktop Access Configuration Enable is checked.
Label field	Enter the label that is defined for this remote access. Note This field appears when Remote Desktop Access Configuration Enable is checked.
VMRC Console Configuration Enable check box	Check the box to enable VMRC console access to the VM. By default, this check box is unchecked, which means that the VMRC console access to the VM is disabled.

Step 14 Click Next.

Step 15 Review the catalog information on the **Add Catalog: Summary** screen.

Step 16 Click Submit.

Service Requests

You can use the self-service provisioning feature to create a service request to provision virtual machines (VMs), services, or applications. The service request process produces a provisioning workflow for VM creation that includes the following actions:

- Budget validation
- Dynamic resource allocation
- Approvals
- Provisioning
- Lifecycle setup and notification



Note

If you change the number of CPU Cores or memory allocation while in the **Deployment Configuration** screen, the total cost is automatically updated and displayed.

To provision a VM or execute an orchestration workflow, you must first create a service request. If desired, you can require approval from one or two administrators or designated users before the VM is provisioned or the workflow executed. VMs can be immediately approved or scheduled to be approved within a maximum of 90 days from the original request.

Creating a Service Request for a Standard Catalog

The administrator publishes catalogs to a group and an end user can choose the required catalog to create a service request. The administrator provides the Self-Service portal with orchestration workflows in the form of catalogs. A catalog, published by the administrator, can be a standard catalog, advanced, or service container.



Important

You can complete this procedure only if the administrator has enabled the **Create Service Request** permission for your role. This **Create Service Request** permission enables or disables the **Create Request** option in the **Service Requests** tab. It does not have any impact on the **Create Request** option from the **Catalog** menu option.

Procedure

- Step 1** Choose **Organizations > Service Requests**.
- Step 2** On the **Service Requests** page, click **Service Requests**.
- Step 3** Click **Create Request**.
- Step 4** On the Create Request screen, choose **Standard** as the catalog type.
- Step 5** Click **Submit**.
- Step 6** On the **Create Service Request** screen, complete the following fields:

Name	Description
Catalog Selection	
VM Ownership	Choose one of the following radio button: <ul style="list-style-type: none"> • Group—Select this radio button to choose the group for which a VM is provisioned. On selecting this radio button, expand Select Group, check the group for which the VM has to be provisioned, and then click Validate. • User—Select this radio button to choose the users to whom you want a VM is provisioned. On selecting this radio button, expand User, check the user for whom the VM has to be provisioned, and then click Validate.
Catalog Type drop-down list	Displays the catalog type.
Select Catalog drop-down list	Choose the catalog created for the KVM cloud. The chosen catalog is used for VM provisioning

Step 7 Click Next.

Step 8 On the **Deployment Configuration** screen, complete the following fields:

Name	Description
Select VDC drop-down list	The VDC on which the VM is provisioned. VDCs are defined by the administrator.
Comment field	Any comments relating to the deployment configuration.
Provision drop-down list	Choose either Now or Later . When you choose Now , the VM is provisioned immediately or up to 90 days in the future. When you choose Later , a calendar for choosing the date and a drop-down list for choosing the time appear. Important This check box is visible only if the administrator has unchecked the Hide end user VM provision later check box.

Name	Description
Lease Time check box	<p>Check this check box to configure a lease time for the VM.</p> <p>The lifetime of the VM can be assigned in terms of days and hours (automatically). The VM is terminated after the specified number of days and hours have elapsed.</p> <p>Important This field is editable only if the administrator has not specified a lease time in the catalog used for VM provisioning and has unchecked the Hide end user lease configuration check box.</p>
Days field	<p>The number of days after which the VM is terminated.</p> <p>Note This option appears when the Lease Time check box is checked.</p>
Hours field	<p>Choose the number of hours after which the VM is terminated.</p> <p>Note This option appears when the Lease Time check box is checked.</p>
Charge Duration drop-down list	<p>Choose a charge duration from the drop-down list. It can be Monthly, Daily, or Hourly.</p>
Month field	<p>If you selected Monthly as the charge duration, then specify the number of months the default cost must be calculated for.</p>
Hourly field	<p>If you selected Hourly as the charge duration, then specify the number of hours the default cost must be calculated for.</p>
Daily field	<p>If you selected Daily as the charge duration, then specify the number of days to be included in the cost computation.</p>

Step 9 Click **Next**.

Step 10 On the **KVM Custom Specification** screen, complete the following fields.

Name	Description
CPU Cores field	<p>The number of CPUs being utilized for the VM being provisioned. This list is available only if you configured the resizing option in the computing policy.</p>

Name	Description
Memory field	The amount of memory for the VM being provisioned. This list is available only if you have configured the resizing option in the computing policy.
Disks field	The datastore for the VM being provisioned. The list of datastores available for selection depends upon the conditions established in the storage policy. You can enable or disable this option in the storage policy.
Storage Tier field	The storage entry for the VM being provisioned. This list appears only if the Virtual Storage Catalog is enabled for the selected catalog.
Select Datastore drop-down list	Choose a datastore. Click Submit to confirm your selection. For templates with multiple disks, you must repeat the datastore selection process for each disk. Note You can select only one datastore for each disk category (System, Data, Database, Swap, and Log). The list of datastore items depends upon the scope conditions in the storage policy.

Step 11 Click Next.

Step 12 On the **Custom Workflow Inputs** screen, complete the following fields:

Note The custom workflow inputs are applicable, if the catalog selected for VM provisioning has Post Provisioning Custom Actions selected during catalog creation. In this scenario, the post provisioning workflow allows end users to specify custom inputs. The inputs option depends upon the workflow attached to a catalog.

Name	Description
MAC Address field	The MAC address of the server.
IP Address field	The IP address of the server.
Host Name field	The hostname of the server.

Step 13 Click Next.

Step 14 The **Summary** screen appears. Review the information for accuracy.

Step 15 Click **Submit**.

What to Do Next

View the service request status.



Managing the KVM Connector

This chapter contains the following sections:

- [Viewing Summary Information, page 33](#)
- [Using VM and Host Level Monitoring, page 34](#)
- [Reports, page 45](#)
- [Managing VM Power Settings, page 47](#)

Viewing Summary Information



Note

If the network in the Red Hat KVM account is configured with both, management and VM type, then the **Network Usage** column in the user interface displays only VM.

Before You Begin

Create a cloud account (KVM).

Procedure

Step 1 Choose **Virtual > Compute**.

Step 2 On the **Compute** page, click **Clouds**.

Step 3 Click the row with the RHEV KVM cloud account for which you want to view the summary.

Step 4 Click **View Details**.

Step 5 Click **Summary** to examine the information.

The **Summary** tab provides tabular data and charts that describe the status of the RHEV KVM cloud account and general trends. The following information is displayed:

- Number of Host Nodes (Last Week)
- Memory (Last Week)

- Disk
 - VMs Active vs Inactive graphs
 - Number of VMs (Last Week)
 - Cloud Overview
 - Host Nodes
 - New VMs
 - Deleted VMs
-

Using VM and Host Level Monitoring

After creating a RHEV KVM cloud (virtual) account and creating a computing policy, you can monitor your VMs and host-related information.

Viewing Polling Information

Before You Begin

Create a cloud account (RHEV KVM).

Procedure

Step 1 Choose **Virtual > Compute**.

Step 2 On the **Compute** page, click **Clouds**.

Step 3 Click the row with the RHEV KVM cloud account for which you want to view the polling information.

Step 4 Click **View Details**.

Step 5 Click **Polling** to examine the information.

The **Polling** tab provides tabular data that describe the polling information in use in the cloud account. The following information is displayed:

- Start Time
 - Collection Type
 - Status
 - Message
 - End Time
-

Viewing vDCs

Before You Begin

Create a cloud account (RHEV KVM).

Procedure

- Step 1** Choose **Virtual > Compute**.
 - Step 2** On the **Compute** page, click **Clouds**.
 - Step 3** Click the row with the RHEV KVM cloud account for which you want to view the VDC details.
 - Step 4** Click **View Details**.
 - Step 5** Click **vDCs** to examine the information.
The **vDCs** tab provides tabular data that describe the VDCs in use in the cloud account. The following information is presented:
 - Group
 - vDC
 - Type
 - Lock State
 - Total VMs
 - Active VMs
 - Custom Categories
 - Status
-

Viewing Data Centers

Before You Begin

Create a cloud account (KVM).

Procedure

- Step 1** Choose **Virtual > Compute**.
- Step 2** On the **Compute** page, click **Clouds**.
- Step 3** Click the row with the RHEV KVM cloud account for which you want to view the data center details.
- Step 4** Click **View Details**.
- Step 5** Click **Data Centers** to examine the information.

The **Data Centers** tab provides tabular data that describe the current pods in use in the cloud account. The following information is displayed:

- Account Name
 - Name
 - Description
 - Storage Type
 - Storage Format
 - Status
 - Minor Version
 - Major Version
 - Minor Supported Version
 - Major Supported Version
-

Viewing Clusters

Before You Begin

Create a cloud account (RHEV KVM).

Procedure

Step 1 Choose **Virtual > Compute**.

Step 2 On the **Compute** page, click **Clouds**.

Step 3 Click the row with the RHEV KVM cloud account for which you want to view the cluster details.

Step 4 Click **View Details**.

Step 5 Click **Clusters** to examine the information.

The **Clusters** tab provides tabular data that describe the current clusters in use in the cloud account. The following information is displayed:

- Account Name
 - Name
 - Description
 - On Error
 - Scheduling Policy
-

Viewing Hosts

Before You Begin

Create a cloud account (RHEV KVM).

Procedure

- Step 1** Choose **Virtual > Compute**.
 - Step 2** On the **Compute** page, click **Clouds**.
 - Step 3** Click the row with the RHEV KVM cloud account for which you want to view the host details.
 - Step 4** Click **View Details**.
 - Step 5** Click **Hosts** to examine the information.
The **Hosts** tab provides tabular data that describe the current hosts nodes in use in the cloud account. The following information is presented:
 - Name
 - Is Storage Manager
 - Ksm Status
 - OS Type
 - Type
 - IP Address
 - State
 - Step 6** Click the row with a host and click **View Details** to view the VMs, service request details, events, deleted VMs, details, NICs, and more reports of the host node.
-

Viewing VMs

Before You Begin

Create a cloud account (RHEV KVM).

Procedure

- Step 1** Choose **Virtual > Compute**.
- Step 2** On the **Compute** page, click **Clouds**.
- Step 3** Click the row with the RHEV KVM cloud account for which you want to view the VM details.
- Step 4** Click **View Details**.
- Step 5** Click **VMs** to examine the information.

The **VMs** tab provides insight into the VMs used by the RHEV KVM cloud account. The following information is displayed:

- Cloud
 - VM ID
 - VM Label
 - VM Name
 - Host Name
 - IP Address
 - Image ID
 - Power State
 - VM Protected
 - Group Name
 - VDC
 - Category
 - Provisioned Time
 - Scheduled Termination Time
 - Last Status Update
-

Viewing RHEV KVM Events

Before You Begin

Create a cloud account (RHEV KVM).

Procedure

- Step 1** Choose **Virtual > Compute**.
- Step 2** On the **Compute** page, click **Clouds**.
- Step 3** Click the row with the RHEV KVM cloud account for which you want to view the RHEV KVM events details.
- Step 4** Click **View Details**.
- Step 5** Click **RHEV KVM Events** to examine the information.
The **RHEV KVM Events** tab provides tabular data that describe the current RHEV KVM-specific events in use in the cloud account. The following information is displayed:

- Account Name
- ID

- Description
 - Severity
 - Code
 - Origin
 - Time
-

Viewing VM Action Requests

Before You Begin

Create a cloud account (RHEV KVM).

Procedure

- Step 1** Choose **Virtual > Compute**.
- Step 2** On the **Compute** page, click **Clouds**.
- Step 3** Click the row with the RHEV KVM cloud account for which you want to view the VM action request details.
- Step 4** Click **View Details**.
- Step 5** Click **VM Action Requests** to examine the information.
The **VM Action Requests** tab provides tabular data that describe the current VM action request in the cloud account. The following information is presented:

- VM ID
 - Action ID
 - User Name
 - Comment
 - Schedule Time
 - Status
-

Launching the SPICE Console for a VM



Important

The Simple Protocol for Independent Computing Environments (SPICE) console is supported with only Windows and Linux client browsers.

Before You Begin

- Create a cloud account (RHEV KVM).
- The VM must be powered on.
- Virtual Viewer must be installed.

Procedure

- Step 1** Choose **Virtual > Compute**.
- Step 2** On the **Compute** page, click **Clouds**.
- Step 3** Choose a RHEV KVM cloud account and click **VMs**.
- Step 4** Choose a VM from the list and click **Launch SPICE Console**.
- Step 5** In the **Download SPICE Console File** screen, review the information displayed, and click **Submit**.
- Step 6** Choose a location on the system to download and save the console-related files.
- Step 7** Access the folder in which the file was downloaded to, and extract the contents of the file.
- Step 8** Double-click the console file to launch the SPICE console for the VM.
-

Viewing VM Pools

Before You Begin

Create a cloud account (RHEV KVM).

Procedure

- Step 1** Choose **Virtual > Compute**.
- Step 2** On the **Compute** page, click **Clouds**.
- Step 3** Click the row with the RHEV KVM cloud account for which you want to view the VM pool details.
- Step 4** Click **View Details**.
- Step 5** Click **VM Pools** to examine the information.
- The **VM Pools** tab provides tabular data that describe the VM pools in use in the cloud account. The following information is displayed:
- Account Name
 - Name
 - Description
 - Size
-

Viewing Events

Before You Begin

Create a cloud account (RHEV KVM).

Procedure

- Step 1** Choose **Virtual > Compute**.
 - Step 2** On the **Compute** page, click **Clouds**.
 - Step 3** Click the row with the RHEV KVM cloud account for which you want to view the event details.
 - Step 4** Click **View Details**.
 - Step 5** Click **Events** to examine the information.
The **Events** tab provides tabular data that describe the current events in the cloud account. The following information is displayed:
 - Cloud Name
 - Severity
 - Event Time
 - Event ID
 - Event Code
 - Description
 - Instance Name
 - Host Name
 - VM Type
 - Parent Node
-

Viewing Roles

Before You Begin

Create a cloud account (RHEV KVM).

Procedure

- Step 1** Choose **Virtual > Compute**.
- Step 2** On the **Compute** page, click **Clouds**.
- Step 3** Click the row with the RHEV KVM cloud account for which you want to view the role details.
- Step 4** Click **View Details**.
- Step 5** Click **Roles** to examine the information.
The **Roles** tab provides tabular data that describe the current roles in use in the cloud account. The following information is displayed:
- Account Name
 - ID
 - Name
 - Description
 - Is Mutable
 - Is Administrative
-

Viewing Images

Before You Begin

Create a cloud account (RHEV KVM).

Procedure

- Step 1** Choose **Virtual > Compute**.
- Step 2** On the **Compute** page, click **Clouds**.
- Step 3** Click the row with the RHEV KVM cloud account for which you want to view the image details.
- Step 4** Click **View Details**.
- Step 5** Click **Images** to examine the information.
The **Images** tab provides insight into the images used by the RHEV KVM cloud account. The following information is displayed:
- Description
 - Image ID
 - Image Name
 - Guest OS
 - Memory (MB)

- Number of CPUs
- Last time the image was updated
- Tag

Click the row with the image and click **View Details** to view the disks and NICs details of the image.

Viewing Tags

Before You Begin

Create a cloud account (KVM).

Procedure

Step 1 Choose **Virtual > Compute**.

Step 2 On the **Compute** page, click **Clouds**.

Step 3 Click the row with the RHEV KVM cloud account for which you want to view the tag details.

Step 4 Click **View Details**.

Step 5 Click **Tags** to examine the information.

The **Tags** tab provides tag data that describe the current roles in use in the cloud account. Tags allow system resources to be arranged into groups or categories on the RHEV KVM connector. The following information is displayed:

- Account Name
 - ID
 - Name
 - Description
-

Viewing Users

Before You Begin

Create a cloud account (RHEV KVM).

Procedure

- Step 1** Choose **Virtual > Compute**.
- Step 2** On the **Compute** page, click **Clouds**.
- Step 3** Click the row with the RHEV KVM cloud account for which you want to view the user details.
- Step 4** Click **View Details**.
- Step 5** Click **Users** to examine the information.
The **Users** tab provides information on which users are associated to a particular cloud account. The following information is displayed:
- Account Name
 - ID
 - Name
 - User Name
-

Viewing Deleted VMs

Before You Begin

Create a cloud account (RHEV KVM).

Procedure

- Step 1** Choose **Virtual > Compute**.
- Step 2** On the **Compute** page, click **Clouds**.
- Step 3** Click the row with the RHEV KVM cloud account for which you want to view the data center details.
- Step 4** Click **View Details**.
- Step 5** Click **Deleted VMs** to examine the information.
The **Deleted VMs** tab provides information on VMs which have been deleted for a particular cloud account. The following information is displayed:
- Cloud
 - VM ID
 - VM Label
 - Instance Name
 - Host Name
 - IP Address
 - Image ID

- Group Name
 - Deleted Time
-

Reports

Cisco UCS Director can help you monitor virtual infrastructure and system resources. It displays a wide variety of reports that provide insight into how the system is performing

Following are the types of reports:

- Tabular reports for system information, including overview, host nodes, new VMs, and deleted VMs.
- Bar and pie graph comparisons, including VMs active versus inactive, and CPU provisioned versus capacity.
- Trend graphs about system resources, including CPU trends, memory trends, and VM additions and deletions.
- Other reports include Top 5 reports at the group, VDC, host node, and VM levels. The Top 5 reports focus on groups with the highest number of VMs, groups with the greatest CPU usage, VDCs with the highest number of VMs, and host nodes with the greatest CPU usage.
- Map reports, displaying the system resource information in the form of heat maps or color-coded maps.

Additional trend reports are available for certain accounts (for example: KVM accounts). Trend reports display data over a selected time frame.

Accessing Reports

Procedure

- Step 1** Choose **Virtual > Compute**.
 - Step 2** On the **Compute** page, choose the cloud.
 - Step 3** Click the name of the report that you want to view (**Map**, **Top 5**, or **More Reports**).
-

Accessing Trend Reports (Summary Level)

Before You Begin

Create a cloud account (RHEV KVM).

Procedure

- Step 1** Choose **Virtual > Compute**.
- Step 2** On the **Compute** page, click **Clouds**.
- Step 3** Click the row with the RHEV KVM cloud account for which you want to view the report.
- Step 4** Click **View Details**.
- Step 5** Click **Summary** to examine the information.
The **Summary** tab provides access to trend reports (at the summary level). Trend reports display data collected over a selected time period. The drop-down list (at the right-side of menu bar) lets you choose last day, last week, or last month durations for the trending report. The following information is presented (based upon configuration):
- Trend: Number of Host Nodes (Last Week)
 - Memory
 - Disk
 - VMs Active vs Inactive
 - Trend: Number of VMs (Last Week)
 - Overview
 - Host Nodes
 - New VMs
 - Deleted VMs
-

Accessing Trend Reports (VM Level)

Before You Begin

Create a cloud account (RHEV KVM).

Procedure

- Step 1** Choose **Virtual > Compute**.
- Step 2** On the **Compute** page, click **Clouds**.
- Step 3** Click the row with the RHEV KVM cloud account for which you want to view the trend report at VM level.
- Step 4** Click **View Details**.
- Step 5** Click **VMs**.
- Step 6** Click the row with the VM for which you want to view the trend report.
- Step 7** Click **View Details**.

Trend reports display data collected over a selected time period. The **Duration for Trending** drop-down list (right-side of menu bar) lets you choose daily, weekly, or monthly durations. The following information is presented (based on configuration):

- Trend: CPU Usage (Percent) (Last Week)
- Trend: Memory Consumption (Bytes) (Last Week)
- CPU Usage
- Memory Usage
- Overview
- Ownership
- Resources
- Host Nodes
- Display
- Hard Disk 1
- Nic 1
- Catalog Details

Managing VM Power Settings

Before You Begin

You must be logged in to the appliance to complete this task.

Procedure

- Step 1** Choose **Virtual > Compute**.
- Step 2** On the **Compute** page, choose the cloud.
- Step 3** On the **Compute** page, click **VMs**.
- Step 4** Click the row with the VM on which you want to perform an action.
- Step 5** Choose an action and the **VM Task** screen appears.

Name	Description
VM Name display-only field	The name of the VM that is the subject of the action.
Power Off display-only field	The task to power off the VM.
Power On display-only field	The task to power on the VM.
Suspend display-only field	The task to put the VM in a suspended state.

Name	Description
Shutdown Guest display-only field	The task to shut down the guest OS on the VM.
Standby display-only field	The task to move the VM into a standby state. Note Not supported in the RHEV KVM Connector.
Reset display-only field	The task to perform a hard reset of the VM. Note Not supported in the RHEV KVM Connector.
Reboot display-only field	The task to perform a soft reboot of the VM. Note Not supported in the RHEV KVM Connector.
Comments field	Enter any comments that help identify the VM.
Schedule Action radio button	The task to power on a VM now or later at a specific date and time.

Step 6 Click **Proceed**.
